COMPREHENSIVE DATA HANDLING SYSTEM (CDHS), EMISSIONS INVENTORY SUBSYSTEM USERS GUIDE

U.S. ENVIRONMENTAL PROTECTION AGENCY
Office of Air and Water Programs
Office of Air Quality Planning and Standards
Research Triangle Park, North Carolina 27711

COMPREHENSIVE DATA HANDLING SYSTEM (CDHS), EMISSIONS INVENTORY SUBSYSTEM USERS GUIDE

by

International Business Machines Corporation Federal Systems Division 18100 Frederick Pike Gaithersburg, Maryland 20760

Contract No. 68-02-0638

EPA Project Officer: Lloyd Hedgepeth

Prepared for

ENVIRONMENTAL PROTECTION AGENCY
Office of Air and Water Programs
Office of Air Quality Planning and Standards
Research Triangle Park, North Carolina 27711

July 1973

The APTD (Air Pollution Technical Data) series of reports is issued by the Office of Air Quality Planning and Standards, Office of Air and Water Programs, Environmental Protection Agency, to report technical data of interest to a limited number of readers. Copies of APTD reports are available free of charge to Federal employees, current contractors and grantees, and non-profit organizations - as supplies permit - from the Air Pollution Technical Information Center, Environmental Protection Agency, Research Triangle Park. North Carolina 27711 or may be obtained, for a nominal cost, from the National Technical Information Service, 5285 Port Royal Road, Springfield, Virginia 22151.

This report was furnished to the Environmental Protection Agency by International Business Machines Corporation, Federal Systems Division, Gaithersburg, Maryland, in fulfillment of Contract No. 68-02-0638. The contents of this report are reproduced herein as received from the contractor. The opinions, findings, and conclusions expressed are those of the author and not necessarily those of the Environmental Protection Agency

Publication No. APTD-1550

TABLE OF CONTENTS

1.0	Intr	oduction	1
2.0	Emis	sions Inventory System Overview	2
	2.1	Organization	3
	2.2	Communication and Data Formats	8
		2.2.1 Master File	8
		2.2.2 Transaction Records	15
3.0	File	Maintenance and Retrieval	46
	3.1	File Maintenance	47
	3.2	Retrieval	52
		3.2.1 Retriever Language and Operators	53
		3.2.2 Retrieval Logic	65
4.0	Outp	ut Programs	72
	4.1	File List	73
	4.2	Summary Report	75
	4.3	NEDS Point Source	84
	4.4	NEDS Area Source	86
	4.5	NEDS Area Source Report	88
5.0	Data	Conversion Programs	90
	5.1	NEDS Point Source to EIS	91
	5.2	NEDS Area Source to EIS	92
6.0	Emis	sion Factors Table Programs	100
	6.1	Emission Factors Table Generator	101
	6.2	Emission Factors Transaction Generator	103
	6 3	Emission Factors Insert	105

7.0	Syste	em Opera	ation	107
	7.1	Catalog	ged Procedures	108
		7.1.1	EISANCNV - NEDS Area Source Output	109
		7.1.2	EISANRPT - NEDS Area Source Report	114
		7.1.3	EISCNVRT - NEDS Point Source to EIS	119
		7.1.4	EISEFGEN - Emission Factors Table Generator	124
		7.1.5	EISEFINS - Emission Factors Insert	130
		7.1.6	EISEFUPD - Emission Factors Transaction Generator	137
		7.1.7	EISFUPDT - File Maintenance	143
		7.1.8	EISNACNV - NEDS Area Source to EIS	149
		7.1.9	EISNCONV - NEDS Point Source Output	154
		7.1.10	EISPREPT - File List Output	159
		7.1.11	EISRETVR - Retrieval	164
		7.1.12	EISSREPT - Summary Report Output	173
	7.2	Use of	Cataloged Procedures	180
Appen	dix .	• • • • • • •		183

FIGURES

2.1-1	EIS System Flow	5
2.2.1-1	EIS Master Record Structure	9
2.2.1-2	EIS Master Record Format	10
2.2.2-1	EIS Transaction Cards	16
4.1-1	File List Data Flow and Deck	74
4.2-1	Permanent Summary Report Generation	81
4.2-2	Permanent Summary Report Execution	82
4.2-3	Temporary Summary Report Generation and Execution	83
4.3-1	NEDS Point Source Output Data Flow and Deck	85
4.4-1	NEDS Area Source Data Flow and Deck Setup	87
4.5-1	NEDS Area Source Report Data Flow and Deck	89
7.1.1-1	EISANCNV Data Flow	110
7.1.1-2	EISANCNV DDNAMES	111
7.1.1-3	EISANCNV Substitutable Parameter	112
7.1.1-4	EISANCNV Procedure	113
7.1.2-1	EISANRPT Data Flow	115
7.1.2-2	EISANRPT DDNAMES	116
7.1.2-3	EISANRPT Substitutable Parameters	117
7.1.2-4	EISANRPT Procedure	118
7.1.3-1	EISCNVRT Data Flow	120
7.1.3-2	EISCNVRT DDNAMES	121
7.1.3-3	EISCNVRT Substitutable Parameters	122
7.1.3-4	EISCNVRT Procedure	123

7.1.4-1	EISEFGEN	Data Flow	125
7.1.4-2	EISEFGEN	DDNAMES	126
7.1.4-3	EISEFGEN	Substitutable Parameters	127
7.1.4-4	EISEFGEN	Procedure	128
7.1.5-1	EISEFINS	Data Flow	131
7.1.5-2	EISEFINS	DDNAMES	132
7.1.5-3	EISEFINS	Substitutable Parameters	133
7.1.5-4	EISEFINS	Procedure	135
7.1.6-1	EISEFUPD	Data Flow	138
7.1.6-2	EISEFUPD	DDNAMES	139
7.1.6-3	EISEFUPD	Substitutable Parameters	140
7.1.6-4	EISEFUPD	Procedure	141
7.1.7-1	EISFUPDT	Data Flow	144
7.1.7-2	EISFUPDT	DDNAMES	145
7.1.7-3	EISFUPDT	Substitutable Parameters	146
7.1.7-4	EISFUPDT	Procedure	147
7.1.8-1	EISNACNV	Data Flow	150
7.1.8-2	EISNACNV	DDNAMES	151
7.1.8-3	EISNACNV	Substitutable Parameters	152
7.1.8-4	EISNACNV	Procedure	153
7.1.9-1	EISNCONV	Data Flow	155
7.1.9-2	EISNCONV	Data Flow	156
7.1.9-3	EISNCONV	Substitutable Parameters	157
7.1.9-4	EISNCONV	Procedure	158
7.1.10-1	EISPREPT	Data Flow	160

7.1.10-2	EISPREPT DDNAMES	161
7.1.10-3	EISPREPT Substitutable Parameters	162
7.1.10-4	EISPREPT Procedure	163
7.1.11-1	EISRETVR Data Flow	166
7.1.11-2	EISRETVR DDNAMES	167
7.1.11-3	EISRETVR Substitutable Parameters	168
7.1.11-4	EISRETVR Procedure	169
7.1.12-1	EISSREPT Data Flow	174
7.1.12-2	EISSREPT DDNAMES	175
7.1.12-3	EISSREPT Substitutable Parameters	176
7.1.12-4	EISSREPT Procedure	177
7 2-1	Sample FIS Joh Stream	182

TABLES

3.2-1	Retrieval Names	57
3.2-2	Repeating Retrieval Names	59
5.2-1	Area Source Categories	95
5.2-2	EIS Area Source Records	97

1.0 INTRODUCTION

This document is intended to provide instruction in the use of the Emission Inventory Subsystem (EIS) of the Comprehensive Data Handling System (CDHS). With this goal in mind the document is organized in the following manner:

- o SECTION 2.0 Contains an overview of the EIS system, a brief functional description of each component program comprising the system and a detailed discussion of the system master file and the general transaction cards required to build the master file.
- o SECTIONS 3.0 through 6.0 Contain detailed functional descriptions of each program in the EIS system, along with complete instructions on the use of all program functions. The sections are organized as follows:

SECTION 3.0 - File Maintenance and Retrieval

SECTION 4.0 - Output Programs

SECTION 5.0 - Data Conversion Programs

SECTION 6.0 - Emission Factors Table Programs

o SECTION 7.0 - Contains complete instructions, with examples, on how to run the EIS system on the computer.

If a more complete knowledge of the logic of the EIS system is desired it is suggested that the user consult the EIS Program Documentation Manual.

2.0 EMISSIONS INVENTORY SUBSYSTEM (EIS) OVERVIEW

When dealing with atmospheric pollution, it is necessary to amass, catalog, sort, evaluate, and perform calculations upon large volumes of data. The Emissions Inventory Subsystem of the Comprehensive Data Handling System provides a systematic method for collecting this data in a data base that will provide a central source for the information needed to help control air pollution. If the system is to be helpful it must maintain the data base, keeping the information current, and provide a means for access to the information, presenting it in a usable form.

The Emissions Inventory Subsystem provides the ability to create and maintain, and to retrieve and print data from the data base. The creation and maintenance is accomplished with the File Maintenance program. This program allows the user to keep his data base information current and useful. Access to the data base information is provided by the Retrieval program set. These programs provide the means of extracting desired information from the data base. The output print programs are then used to convert the extracted information to a form readable by the user. These three functions form the basic system.

In addition to the basic system, several preprocessor and postprocessor programs are provided which perform functions necessary to make this system compatible with existing systems. Other programs provide services which help make the maintenance process automatic. All of the system programs are described in detail in the following sections.

2.1 ORGANIZATION


The Emission Inventory Subsystem of CDHS is organized around two main programs, File Maintenance and Retrieval. There are ten other programs in the system that perform service functions. The interface for the programs that feed the File Maintenance program is the EIS transaction card. The Master File serves as the interface for the rest of the programs.

The EIS components are:

- o File Maintenance This program is used to create and maintain the Master File.
- o Retrieval Language Processor This program generates the retrieval program.
- o Retrieval This program is used to extract information from the Master File.
- o File List This program provides a detailed listing of the Master File.
- o Summary Report Output This program will produce a listing of emission totals for selected control breaks.
- o NEDS Point Source Output This program converts the Master File to NEDS Point Source card formats.
- o NEDS Area Source Output This program converts the Master File area records to NEDS Area Source card formats.
- o NEDS Area Source Report This program prints a formatted listing of NEDS Area Source cards.


- o NEDS Point Source Conversion This program converts NEDS Point Source cards to EIS transaction cards.
- o NEDS Area Source Conversion This program converts NEDS Area Source cards to EIS transaction cards.
- o Emission Factor Table Generator This program is used to generate the emission factors table.
- o Emission Factor Insertion This program inserts the emission factors into the (23 card) EIS transactions.
- o Emission Factor Transaction Generator This program generates transaction cards to update emission factors in the Master File.

Figure 2.1-1 illustrates the flow of the EIS system.




EIS System Flow

Figure 2.1-1



EIS System Flow

Figure 2.1-1 (cont.)




EIS System Flow

Figure 2.1-1 (cont.)

2.2 COMMUNICATION AND DATA FORMATS


2.2.1 MASTER FILE

The EIS master file is a three level hierarchical file with three different segment types. The highest, or master record level segment is called the



plant segment. There is no limit to the number of master records allowed on an EIS master file. Subordinate to each master record (plant segment) may be up to 99 point source segments, each describing a different source of pollution (air stack) within the plant described by the plant segment. And subordinate to each point source segment are 1 to 6 machine process segments, each describing a different polluting process or machine feeding into the given point source. Figure 2.2.1-1 illustrates the hierarchical structure of an EIS master record.

The format of each segment type on the master file is illustrated in Figure 2.2.1-2. Each field illustrated relates directly to a field on one of the input transaction cards.



- o unlimited plant segments (type 0)
- o up to 99 point source segments (type 1 subordinate to each plant segment.
- o up to 6 machine process segments

 (type 2) subordinate to each point
 source

EIS MASTER RECORD STRUCTURE Figure 2.2.1-1

Fixed (Plant) Segment (Segment 0)

Position	Format		Symbol Symbol	Description
1 - 2	жx		Numeric	State Code
3 - 6	ххх		Numeric	County Code
7 - 9	ххх		Numeric	AQCR Number
10 - 13	хххх		Numeric	Plant Id
14 - 18	ххххх	*	Numeric	Date of Segment 1
19 - 21	ххх	*	Numeric	Segment Id
22 - 24	жж	*	Alphanumeric	User Control Region
25 - 26	хx	*	Alphanumeric	Local Control
27 - 38	x-x	*	Alphanumeric	User Plant Id
39 - 42	хххх		Numeric	City
43 - 44	xx		Numeric	UTM Zone
45	A		Alphabetic	Ownership
46 - 60	A-A		Alphabetic	Contact
61 - 70	х-х	*	Alphanumeric	Telephone
71 - 80	х-х	*	Alphanumeric	Principal Product
81 - 128	х-х		Alphanumeric	Name and Address
129 - 132	жжж	*	Numeric	Number of Employees
133 - 138	ххххх. х	*	Numeric	Property Area
139 - 186	x-x	*	Alphanumeric	Mailing Address

EIS Master Record Format

Figure 2.2.1-2

Position	Format		Symbol Symbol	Description
1 - 2	ж		Numeric	State Code
3 - 6	хххх		Numeric	County Code
7 - 9	жж		Numeric	AQCR Number
10 - 13	хххх		Numeric	Plant Id
14 - 18	XXXXX	*	Numeric	Date of Segment ¹
19	x	*	Numeric	Segment Id
20 - 21	xx		Numeric	Segment Id Sequence
22 - 23	хх		Numeric	Point Id (NEDS)
24 - 26	xxx	*	Alphanumeric	Point Id (User)
27 - 30	хххх		Numeric	SIC Code
31 - 32	xx		Numeric	IPP Code
33 - 36	xxx.x		Numeric	UTM Horizontal Coordinates
37 - 41	хххх. х		Numeric	UTM Vertical Coordinates
42 - 47	x- x	*	Numeric	Latitude
48 - 54	x -x	*	Numeric	Longitude
55 - 62	x -x		Numeric	Annual Throughput
63 - 67	xxxxx		Numeric	Normal Operating
68 - 72	XXXXX		Numeric	Boiler Design Capacity
73 - 75	ж. х		Numeric	Space Heat
76 - 79	жжж		Numeric	Stack Height
80 - 82	x x. x		Numeric	Stack Diameter
83 - 86	xxxx		Numeric	Stack Temperature

EIS Master Record Format

Figure 2.2.1-2 (Continued)

Position	Format		Symbol Symbol	Description
87 - 93	x -x		Numeric	Exhaust Flow Rate
94 - 98	ххххх	*	Numeric	Velocity
99 - 102	xxxx		Numeric	Plume-Height
103 - 106	хххх		Numeric	Points with Common Stack
107	x		Numeric	Compliance Status
108 - 111	хххх		Numeric	Compliance Schedule
112 - 117	x-x		Numeric	Compliance Update
118	x		Numeric	ECAP
119 - 130	x - x		Numeric	Control Regulations
131 - 132	xx		Numeric	Number of Pollutants ²
133 - 137	жжж	*	Numeric	Pollutant Id
137 - 144	жжжж. жж	*	Numeric	Control Equipment Cost
145 - 147	ххх		Numeric	Primary Control Equipment
148 - 150	жж		Numeric	Secondary Control Equipment
151 - 153	xx.x		Numeric	Estimated Control Efficiency
154 - 160	x - x		Numeric	Emissions Estimate
161 - 167	x-x	*	Numeric	Emissions Measured
168 - 174	x -x		Numeric	Allowable Emissions
175	x	*	Numeric	Emission Units
176	x		Numeric	Estimation Method
177	x	*	Numeric	Test Method

Note: Positions 133 - 177 may be repeated up to 15 times to allow for 16 pollutants from a single source. The Number of Pollutants field determines the number of repetitions.

EIS Master Record Format

Machine Process Segment (Segment 2)

Position	Format		Symbol Symbol	Description
1 - 2	xx		Numeric	State Code
3 - 6	хххх		Numeric	County Code
7 – 9	xxx		Numeric	AQCR Number
10 - 13	xxxx		Numeric	Plant Id
14 - 18	XXXXX	*	Numeric	Date of Segment ¹
19	x	*	Numeric	Segment Id
20 - 21	xx		Numeric	Segment 1 Id
22 - 23	xx	*	Numeric	Segment 2 Id
24 - 31	х-х		Numeric	SCC Code
32 - 36	xxxxx	*	Numeric	BEC Code
37	x	*	Numeric	Fuel Units
38 - 44	x-x		Numeric	Fuel, Process, Solid Waste
45 - 51	xxx.xxx		Numeric	Maximum Design
52 - 54	x.xx		Numeric	Sulfur Content
55 - 57	xx. x		Numeric	Ash Content
58 - 62	ххххх		Numeric	Heat Content
63	x		Numeric	Confidentiality of Data
64	A		Alphabetic	Source Code
65 - 89	x-x		Alphanumeric	Source Description
90	x	*	Alphabetic	Emission Factor Source
91 - 92	хх	*	Numeric	Number of Emission Factors ²
93 - 97	жжжж	*	Numeric	Pollutant Id

EIS Master Record Format

Figure 2.2.1-2 (Continued)

Position	Format	Symbol Symbol	Description
98 - 106	xxx,xxxxxx	* Numeric	Emission Factor
107	A	* Alphabetic	Ash/Sulfur Code
108	x	* Numeric	Emission Factor Units

Note: Positions 93-108 may be repeated up to 15 times to allow for 16 emission factors per process. The number of Emission Factors field determines the number of repetitions.

- * Not part of NEDS point source file.
- Only year portion of date obtained from NEDS point source file. Remainder of field filled with zeroes.
- 2 Determined by File Maintenance program.

EIS Master Record Format

Figure 2.2.1-2 (Continued)

2.2.2 TRANSACTION RECORDS

The master file is constructed from the information contained on the EIS input transaction cards. There are three classes (or types) of cards: a zero card, a one card and a two card. The zero card contains general identification for the plant or source; the one card contains information relative to specific emission points within a source; the two card contains fuel and process information. The following paragraphs explain the contents of each field on the transaction cards. Figure 2.2.2-1 illustrates the format of the cards. The same formats are used to enter both point source data and area source data. However, the meanings of some fields will be changed when area source data is to be entered.

Card Columns 1-18 of all Cards (Key)

CC	Format	Symbol	Description
1 - 2	ж	Numeric Code	State Code
3 - 6	хххх	Numeric Code	County Code
7 - 9	ххх	Numeric Code	AQCR Number
10 - 13	хххх	Numeric Code	Plant Id
14 - 18	ххххх	Numeric	Date of Record

Card Ø1 - Plant Identification

CC	Format	Symbol Symbol	Description
19 - 21	ххх	Alphanumeric Code	Control Region
22 - 23	xx	Alphanumeric Code	Local Control
24 - 35	x-x	Alphanumeric Code	Plant Id
36 - 39	xxxx	Numeric Code	City
40 - 41	xx	Numeric Code	UTM ZONE
42	A	Alphabetic Code	Ownership
43 - 57	A-A	Alphabetic	Contact
58 - 67	x-x	Alphanumeric	Telephone
68 - 77	x-x	Alphanumeric	Principal Product
78 - 79	хx	Numeric	Card Number
80	x	Alphabetic Code	Transaction Code

EIS TRANSACTION CARDS

Figure 2.2.2-1

Card Ø2 - Plant Identification

СС	Format	Symbol	Description
19 - 66	x-x	Alphanumeric	Name and Address
67 - 70	x-x	Numeric	Number of Employees
71 - 76	xxxxx.x	Numeric	Property Area
77			Not Used
78 – 79	xx	Numeric	Card Number
80	x	Alphabetic Code	Transaction Code

Card 03 - Plant Identification

CC	Format	Symbol Symbol	Description
19 - 66	x-x	Alphanumeric	Mailing Address
67 - 77			Not Used
78 - 79	хx	Numeric	Card Number
80	x	Alphabetic Code	Transaction Code

EIS TRANSACTION CARDS

Card 11 - Point Source Parameters

CC	Format	Symbol	Description
19 - 20	xx	Numeric	Segment ID
21 - 22	хx	Numeric	Point Id (NEDS)
23 - 25	xxx	Alphanumeric	Point Id (Local)
26 - 29	xxxx	Numeric	SIC Code
30 - 31	xx	Numeric	IPP Code
32 - 35	xxx.x	Numeric	UTM Horizontal Coordinates
36 - 40	xxxx.x	Numeric	UTM Vertical Coordinates
41 - 46	x-x	Numeric	Latitude
47 - 53	x-x	Numeric	Longitude
54 - 61	x-x	Numeric	% Annual Throughput
62 - 66	xxxxx	Numeric	Normal Operating
67 - 71	ххххх	Numeric	Boiler Design Capacity
72 - 74	xx.x	Numeric	Space Heat %
75 - 77			Not Used
78 - 79	хх	Numeric	Card Number
80	×	Alphabetic Code	Transaction Code

EIS TRANSACTION CARDS

Card 12 - Point Source Parameters

CC	Format	Symbol Symbol	Description
19 - 20	xx	Numeric	Segment ID
21 - 24	хххх	Numeric	Stack Height
25 - 27	xx.x	Numeric	Stack Equivalent Diameter
28 - 31	хххх	Numeric	Stack Temperature
32 - 38	x-x	Numeric	Exhaust Flow Rate
39 - 43	ххххх	Numeric	Velocity
44 - 47	хххх	Numeric	Plume Height
48 - 51	хххх	Numeric	Points with Common Stack
52	x	Numeric	Compliance Status
53 - 56	хххх	Numeric	Compliance Schedule
57 - 62	хххххх	Numeric	Compliance Update
63	x	Numeric	ECAP
64 - 75	x- x	Numeric	Control Regulations
76 - 77			Not Used
78 – 79	xx	Numeric	Card Number
80	x	Alphabetic Code	Transaction Code

Card 13 - Point Source Parameters

CC	Format	Symbol Symbol	Description
19 - 20	xx	Numeric	Segment ID
21 - 25	XXXXX	Numeric	Pollutant ID
26 - 32	xxxxxxxx	Numeric	Control Equipment Cost
33 - 35	жж	Numeric	Primary Control Equipment
36 - 38	xxx	Numeric	Secondary Control Equipment
39 - 41	xx.x	Numeric	Estimated Control Efficiency
42 - 48	XXXXXXXXX	Numeric	Emissions Estimate
49 - 55	XXXXXXX	Numeric	Emissions Measured
56 - 62	xxxxxxxx	Numeric	Allowable Emissions
63	x	Numeric	Emission Units
64	x	Numeric	Estimation Method
65	x	Numeric	Test Method
66 - 77			Not Used
78 – 79	xx	Numeric	Card Number
80	x	Alphabetic	Transaction Code

Card 21 - Fuel, Process Parameters

CC	Format	Symbol	Description
19 - 20	хх	Numeric	Segment 1 ID
21 - 22	хх	Numeric	Segment 2 ID
23 - 30	x-x	Numeric Code	SCC Code
31 - 35	жжжж	Numeric Code	BEC Code
36	x	Numeric Code	Fuel Units
37 - 43	хххххх	Numeric	Fuel, Process, Solid Waste
44 - 50	xxxxx.xxx	Numeric	Maximum Design
51 - 53	x.xx	Numeric	Sulfer Content
54 - 56	xx.x	Numeric	Ash Content
57 - 61	жжж	Numeric	Heat Content
62 - 77			Not Used
78 – 79	хх	Numeric	Card Number
80	x	Alphabetic Code	Transaction Code

Card 22 - Fuel, Process Parameters

CC	Format	Symbol Symbol	Description
19 - 20	xx	Numeric	Segment 1 ID
21 - 22	xx	Numeric	Segment 2 ID
23	x	Numeric	Confidentiality of data
24	x	Alphabetic	Source Code
25 - 49	x-x	Alphanumeric	Source Description
50	x	Alphabetic	Emission Factor Source
51 - 77			Not Used
78 - 79	xx	Numeric	Card Number
80	×	Alphabetic	Transaction Code
		Code	

Card 23 - Fuel, Process Parameters

CC	Format	Symbol	Description
19 - 20	xx	Numeric	Segment 1 ID
21 - 22	xx	Numeric	Segment 2 ID
23 - 27	xxxxx	Numeric	Pollutant ID Code
28 - 36	xxxxxxxx	Numeric	Emission Factor
37	x	Alphabetic Code	Ash/Sulfur Code
38	x	Numeric Code	Emission Factor Units
39 - 54			Repeat CC 23 - 38
55 - 70			Repeat CC 23 - 38
71 - 77			Not Used
78 - 79	ж	Numeric	Card Number
80	x	Alphabetic Code	Transaction Code

o Card Columns 1-18 of all cards:

- 1. State Code: State identification number as defined by the SAROAD air quality numbering system.
- 2. County Code: Codes to be used are listed in the <u>SAROAD Station</u> <u>Coding Manual for Aerometric Sampling Networks</u>, Publication No. APTD-0907 of the Environmental Protection Agency.
- AQCR Number: Number for the Air Quality Control Region in which the Plant is located.
- 4. Plant ID: This field identifies each source in a county. The numbering system is sequential, starting with the number one and continuing until all facilities containing point sources that are located in a given county are assigned a number.
- Date of Record: The Julian date for the data recorded on the card. The format for this field is YYDDD.

o Card Ø1

- Control Region: A user defined field to identify state or county control areas.
- Local Control: A user defined field to identify plants that
 are physically in one control region but have control responsi bility in another region.
- Plant ID: A user defined field to be used if the local identification conventions differ from NEDS.
- 4. City: The four-digit SAROAD code number corresponding to the city in which the source is located. There are a few cities in the United States that are not considered to be inside any county but are considered independent entities. In such cases, enter the city code in both the City and County Code fields.
- 5. UTM Zone: The zone number must be known in order to locate the point source via the UTM coordinate system; this number is found on all USGS maps showing UTM coordinates. Although most states are within a single UTM zone, a few states and counties are in two UTM zones. For this reason a UTM zone number is required for each record.

6. Ownership: A single alphabetic character ownership code.
The code should be selected from the following list:

Symbol Symbol	Ownership
P	Private
L	Local Government
S	State Government
F	Federal Government
U	Utility

- 7. Contact: The last name of the person responsible for pollution control activity at the source. If the responsible individual is not identifiable, then record a descriptive and appropriate title.
- 8. Telephone: The area code and telephone number of the person to be contacted should be entered in this field.
- 9. Principal Product: A brief description of the principal product produced by this plant.
- 10. Card Number: Ø1
- 11. Transaction Code: The transaction codes are:
 - A Add
 - C Change
 - D Delete.

o Card Ø2

- Name and Address: Provide a descriptive name for the facility and a usable mailing address. Use common abbreviations as much as possible. The address should include a street number, city and a zip code. The zip code should appear in the last five positions of the field.
- Number of Employees: Record the number of persons actually working at this location.
- Property Area: The area, to the nearest tenth acre, of the land occupied by the facility.
- 4. Card Number: Ø2
- 5. Transaction Code: The transaction codes are:
 - A Add
 - C Change
 - D Delete.

o Card Ø3

- 1. Mailing Address: The address of the person to contact if it is different than the establishment name and address.
- 2. Card Number: Ø3.
- 3. Transaction Code: The transaction codes are:
 - A Add
 - C Change
 - D Delete.

- 1. Segment ID: Each point source set (11, 12, and a 13 card) creates a point source segment in the master file. Each point source segment under the same facility segment must have a unique segment ID number. This number must also be used to reference a particular segment when making a change or deleting a segment.
- 2. Point ID (NEDS): This is a sequential number designated for each pollutant discharge point within the facility.
- 3. Point ID (Local): This is a field for a user defined point source identification when the NEDS Point Id is not sufficient to show local control.
- 4. SIC code: This information is necessary to use the source data for modeling air quality. Enter the appropriate Standard Industrial Classification code.
- 5. IPP code: This column should be completed with the standard process code.

- 6. UTM Horizontal and Vertical Coordinates: The UTM coordinate system is another means of identifying the location of the point source. Coordinates are obtained from USGS maps or their equivalent with scales less than 1:62,500. All spaces in these columns must be filled in with numbers and zeros. Accuracy to 0.1 kilometer accuracy is desired.
- 7. Latitude and Longitude: This is an alternate means of identifying the location of the point source. Coordinates may be obtained from USGS maps or their equivalent.
- 8. % Annual Throughput: The annual production, consumption, throughput, or other valid number representing the operating of the source should be proportionally divided into the four 3-month categories listed below. The wieghted portion of production occurring in each category is reported as a percentage of total annual throughput. The field is divided into four equal subfields of two numbers each. The first two positions are for December through February. The next two are for March through May. The next two are for June through August. The last two are for September through November.
- 9. Normal Operating: The hours per day, days per week, and weeks per year that the source operates under normal and usual conditions should be entered here.

- 10. Boiler Design Capacity: Numerical values in this field should be entered if the boiler burns fuel to heat water or steam, or if it is normally sold according to the heating capacity (BTU per hour). Units are in millions of BTU per hour based on the maximum capacity or design of the boiler.
- 11. Space Heat %: An estimate of the percent of total fuel used for space heating at the plant should be entered here. If no fuel is used for space heating, enter zeros in this field.
- 12. Card Number: 11
- 13. Transaction Code: The transaction codes are:
 - A Add
 - C Change
 - D Delete

- Segment ID: Enter the same number as in the Segment ID
 of the 11 card.
- 2. Stack Height: If the exact location of the discharge of pollutants is well defined there will be a stack or some other enclosed, constrained, or physically-bounded area where pollutants are emitted. In such instances, the stack height is the vertical distance between the point of emission and ground level. If no stack can be identified or there is a changing locus of emissions within the facility then complete only the Plume Height field and leave the rest of the stack data blank.
- 3. Stack Equivalent Diameter: The stack diameter is the inside diameter of a round gas exit at the point of emission; for non-round exits, it is an equivalent diameter calculated from the cross-sectional area at point of discharge. Using a measured or estimated cross-sectional area, the equivalent diameter (De) is calculated as follows:

De = 1.128
$$\sqrt{A}$$

where A is in square feet.

- 4. Stack Temperature: The temperature of the exhaust stream at the stack exit should be reported in degrees Fahrenheit under normal operating conditions. If measured temperatures are not available, an estimate to the nearest 50°F should be made.
- 5. Exhaust Flow Rate: This number should be specified by recording the design or maximum exhaust-gas volume unless actual measurements are available. Units are actual cubic feet per minute and represent the total volume of exhaust gas released at the operating temperature of the stack (assume gas pressure is the same as normal atmospheric pressure).
- 6. Velocity: This number should be specified by recording the design or maximum exhaust-gas velocity unless actual measurements are available. Units are feet per minute.
- 7. Plume Height: This field is to be filled in if the previous fields on stack data are all blank. The plume height is a gross estimate and is used only when the source has no definable stack.
- 8. Points with Common Stack: Columns 48 and 49 contain the NEDS Point ID of the first point source discharging through the stack. Columns 50 and 51 contain the NEDS Point ID of the last point source discharging through the stack. For a complete definition of common stack see EPA publication APTD-1135, Guide For Compiling A Comprehensive Emission Inventory, for March 1973.

9. Compliance Status: One of the following codes must be selected to record the present status of the source under existing legal requirements:

Code

- Source is in compliance with the most stringent air pollution control requirements.
- 2 Source is not in compliance with existing legislation and no variance has been given.
- 3 Source is not in compliance with existing legislation but a variance has been given.
- 4 Compliance status is unknown.
- 10. Compliance Schedule: If the compliance status code is 2 or 3, enter the year and month by which this source must be in compliance.
- 11. Compliance Update: The day, month, and year of the most recent change in compliance status for the source be entered in this field. Leave the field blank if compliance status has been reported as unknown (code 4). If the source is in compliance with existing air pollution control legislation, then record the record the time that such legislation was enacted.
- 12. ECAP: Certain point sources are required to submit to government agencies on Emergency Control Action Program

that specifies a detailed plan for immediately reducing emissions whenever air pollution in an area is considered an emergency condition. The following list shall be used to denote whether or not an ECAP has been submitted to an appropriate government agency. Leave blank if status is unknown.

- Ø ECAP is not required
- 1 ECAP is required but has not been submitted
- 2 ECAP has been submitted.
- 13. Control Regulations: This field is used to identify air pollution control regulations that are in effect and apply to the source.
- 14. Card Number: 12
- 15. Transaction Code: The transaction codes are:
 - A Add
 - C Change
 - D Delete

- Segment ID: Enter the same number as in the Segment Id of the
 card.
- Pollutant ID: This field is a five digit code that represents the pollutants whose emissions are being measured. Source is SAROAD Parameter Coding Manual, EPA Publication No. APTD-0633.
- Control Equipment Cost: Enter the annual cost of maintenance and operation of pollution control equipment.
- 4. Primary Control Equipment: This field should be completed with the Control Equipment Identification Code. Only control devices that reduce the uncontrolled emission normally associated with the specific source process should be reported.
- 5. Secondary Control Equipment: If there is an additional control device installed for this pollutant enter the Control Equipment Identification Code in this field.

- 6. Estimated Control Efficiency: The overall collection efficiencies in weight percent of all control equipment at the point source should be entered. Assume that the pollutant load entering the control equipment is the normal, uncontrolled quantity for that specific process.
- 7. Emissions Estimate: The annual, controlled emissions from the point source, in tons per year, should be entered here. These calculations should include the effect of pollutant removal by installed control equipment.
- 8. Emissions Measured: The annual, controlled emissions from the point source, in tons per year, as actually measured by test equipment should be entered here. These measurements can be compared against the estimates to check the validity of the emission factors.
- 9. Allowable Emissions: Entered here should be the maximum emissions, in tons per year, that the source is legally allowed to discharge into the atmosphere.
- 10. Emission Units: This field is for future expansion of the system. It will eventually allow the user to specify units for the emissions in other than NEDS units. It is currently ignored by the system.

11. Estimation Method: The following code list must be used to specify the method used to ascertain the estimated emissions:

Code	Description of Method
0	Not applicable (if emissions are negligible)
1	Stack-test results or other emission
	measurement
2	Material balance using engineering knowledge
	and expertise of process
3	Emission calculated using emission factors
4	Guess

If code 3 is used the file maintenance program will calculate the estimated emissions if all the factors are present.

- 12. Test Method: A user defined code to indicate the method used to ascertain the measured emissions.
- 13. Card Number: 13
- 14. Transaction Code: The transaction codes are:
 - A Add
 - C Change
 - D Delete.

- Segment 1 ID: Enter the same number as in the Segment ID of the 11 card for the point source to which this segment belongs.
- 2. Segment 2 ID: Each Fuel-Process set (21,22,23) creates a Fuel-Process segment in the master file. Each Fuel-Process segment under the same point source segment must have a unique Segment 2 ID number. This number must also be used to reference a particular segment when making a change or deleting a segment.
- 3. SCC Code: The Source Classification Code process description that most nearly describes the process should be entered by its eight-digit numerical code. If the most appropriate SCC description appears to be significantly different from the actual process, enter nothing in this field, but enter NEW SCC NEEDED in the Source Description field of the 22 card.
- 4. BEC Code: Enter the Basic Equipment Classification Code that describes the equipment or process for this source. The last two digits are used to sequentially number identical units at the same source.

- 5. Fuel Units: This field is for future expansion of the system.

 It will eventually allow the user to specify units for the fuelprocess field in other than NEDS units. It is currently ignored
 by the system.
- 6. Fuel, Process, Solid Waste: The annual figures will be reported in this field using the units associated with the SCC code for this process.
- 7. Maximum Design: The maximum hourly design rate of the most important process equipment, or the upper operating limit that generally would not be exceeded in normal practice, should be entered here. Units are expressed in those corresponding to the SCC for the process.
- 8. Sulfur and Ash Content: Entries are to be made in these columns for all combustion processes. If the process does not burn fuel, leave the field blank.
- 9. Heat Content: This field is to be completed only when the process involves combustion. Units are millions of BTU per SCC.
- 10. Card Number: 21

- 11. Transaction Code: The transaction codes are:
 - A Add
 - C Change
 - D Delete.

- Segment 1 ID: Enter the same number as on the Segment 1 ID
 of the 21 card.
- Segment 2 ID: Enter the same number as on the Segment 2 ID
 of the 21 card.
- 3. Confidentiality of Data: Process information occasionally is collected by a government agency under a guarantee that the data will be treated in a confidential manner and will not be released to the public. This column indicates whether or not any data for this source are officially considered confidential. A one (1) indicates confidential classification, a two (2) no classifiaction and a blank indicates an unknown status.
- 4. Source Code: this is needed for NEDS reporting. Enter the following codes for the process category: B Boiler, P Process, C Other Combustion unit.
- 5. Source Description: Enter a brief description of the source or comments as needed.

- 6. Emission Factor Source: If this field contains a T the
 Emission Factors insertion program will insert the appropriate
 Emission Factors from a table of SCC codes.
- 7. Card Number: 22
- 8. Transaction Code: The transaction codes are:
 - A Add
 - C Change
 - D Delete.

- Segment 1 ID: Enter the same number as in the Segment 1 ID of the 21 card.
- Segment 2 ID: Enter the same number as in the Segment 2 ID of the 21 card.
- 3. Pollutant ID Code: This field is a five digit code that represents the pollutant whose emissions are being measured. Source is <u>SAROAD</u>

 Parameter Coding Manual, EPA Publication No. APTD-0633.
- 4. Emission Factor: The emission factor is a statistical average of the rate at which a pollutant is released to the atmosphere as a result of some activity, such as combustion or industrial production, divided by the level of that activity. The emission factors for each SCC may be found in the EPA publication Compilation of Air Pollutant Emission Factors, Publication No. AP-42.
- 5. Ash/Sulfur Code: This code indicates whether or not the Ash or Sulfur percentage is to be used in the calculation of the estimated emissions. The codes are: A Ash, S Sulfur and blank is neither apply.
- 6. Emission Factor Units: This field is for future expansion.

 Eventually it will indicate the units in which the emission

factors are expressed. The emission factors are now treated as standard NEDS units. Reference OAP Publication No. AP-42.

- 7. Card Number: 23
- 8. Transaction Code: The transaction codes are:
 - A Add
 - C Change
 - D Delete.

Note: Card columns 23 to 38 may be repeated two more times on the same 23 card. This allows the storing of up to three sets of emission factors information on each card.

3.0 FILE MAINTENANCE AND RETRIEVAL

There are two major EIS programs for building, maintaining and retrieving data from the EIS master file. These are the File Maintenance program and the Retrieval program.

3.1 FILE MAINTENANCE

The File Maintenance program performs two basic functions, the creation of a new system master file and the modification of an existing system master file. The program can operate in any of three modes to support the two basic functions. These modes are add, change and delete. Every transaction card input to the file maintenance program must be either an add, change or delete card, identified by an A, C or D in column 80.

Add cards are used to create a new system master file, and to add new records to an existing file. Add cards are always entered in logical segment groupings. Thus, a type Ø segment must be added as a complete entity of one Ø1 card, one Ø2 card and one Ø3 card. Similarly, a type 1/type 2 segment combination must be added subordinate to an already existing type Ø segment as a complete entity of one 11 card, one 12 card, one or more 13 cards, and multiple occurrences of one 21 card, one 22 card and one or more 23 cards. A type 2 segment cannot be added by itself. That is, it must be added in conjunction with a type 1 segment. Up to six type 2 segment can exist subordinate to one type 1 segment.

Change and delete cards are used to modify an existing system master file. Any data field specified as non-blank on a change card will replace the corresponding field in the designated file record. Change cards use the same format as add cards except that all data fields except the fields being changed are left blank. Thus any field on any card can be changed except the record key, segment 1 and segment 2 ID's and pollution ID.

Delete cards can be used to delete an entire logical record (type Ø segment and all subordinate type 1 and 2 segments), a type 1 segment (with all subordinate type 2 segments) or a single type 2 segments.

All transaction cards entered into the file maintenance program must be sorted in master file sequence either by the user or by the emission factors insertion program, as the master file is passed only once per run for fast performance.

Add Cards

Records are created or added to the master file using the following combinations of ADD cards. Only those fields with the name filled in are required. All other fields may be blanks. At least the three cards shown in each segment are required to create each segment.

o To add a plant segment (type Ø segment):

KEY	DATE	Ø1	A
KEY		Ø2	A
KEY		Ø 3	A
T 13	14 18		

To add a point source segment (type 1 segment), which is allowed to have subordinate to it up to six machine process segments (type 2 segments):

	KEY	DATE	ID		11	A	
	KEY		ID		12	A	
ļ	KEY		ID	POLL. ID	13	A	up to 16
•	1 13	14 18	19 20	21 25	78 79	80	cards

	KEY		D.A	TE	I	_D	II)2			21		A	up to 6
,	KEY				I	D	II)2			22		A	sets with up to 16
	KEY				I	D	ΙI)2	POLL.	ID	23		A	23 cards per set
1		13	14	18	19	20	21	22	23	27	78	79	80	-

Up to 16 unique pollutant ID's are allowed. Thus multiple type 13A and 23A cards are allowed. One, two or three pollutant ID's can be present on any type 23A card. Also, since up to six (there must be at least one) machine process (type 2) segments can be subordinate to any point source (type 1) segment, there can be up to six sets of the 21A/22A/multiple 23A type cards following the last 13A card of each point source segment.


Change Cards

Any record on an existing master file can be changed through the use of a change card. Depending on the segment type being changed, certain fields on the card are required to be filled in. Other than these required fields, any other fields on the card which is non-blank will replace the corresponding field of the indicated record on the master file.


To change a field in a master file record, only the single transaction card which contains that field need be used. For example, assume that the field called COMPLIANCE-STATUS is to be changed. This field is part of the point source (type 1) segment and is included in the type 12 transaction card. Thus only a type 12 change card is required. The types 11 and 13 cards are unnecessary.

The following is the format for each type of change card, with the required fields filled in by name.

o Type Øl change card:




o Type 02 change card:




o Type Ø3 change card:




o Type 11 change card:




o Type 12 Change card:




o Type 13 change card:



o Type 21 change card:



o Type 22 change card:




o Type 23 change card:


Delete Cards

Three segments (or segment combinations) can be seleted from an existing master file. The following cards, with required fields filled in, illustrate how to delete these segments.


O Delete an entire logical record of plant (type Ø) segment and all subordinate point source (type 1) and machine process (type 2) segments:



o Delete a point source (type 1) segment and all subordinate machine process (type 2) segments:



o Delete a machine process (type 2) segment:



In general, the KEY, IDs, card number and transaction code are required for all types of transactions. In addition, the POLL. ID and DATE are required for adding or changing information in the master file.

3.2 RETRIEVAL

The CDHS retrieval component retrieves data from files based on Englishlike retrieval statements. The retrieved data records are placed on an answer data set for future processing. The answer data set may be sorted or not depending on the sort specifications.

The functions of the language processor/retriever are:

- a. Editing and processing of retrieval and control statements.
- b. Compilation of the retrieval logic to produce a COBOL program for actual retrieval.
- c. Execution of the COBOL program and the construction of the answer data set containing records qualified for retrieval by the retrieval specification.

3.2.1 RETRIEVAL LANGUAGE AND OPERATORS

The CDHS retrieval language consists of \$\$ control statements, retrieval statements and sort statements. The statements must be specified in a prescribed order. A retrieval that produces an unsorted answer set requires three control statements. If the answer set is to be sorted an additional control statement is required. The two valid statement sequences are:

a. Unsorted Answer Set

\$\$QUERY

\$\$IF

Retrieval Statements

\$\$END

b. Sorted Answer Set

\$\$QUERY

\$\$SORT

Sort Statements

\$\$IF

Retrieval Statements

\$\$END

QUERY Control Card

The query control indicates the beginning of the set of statements for a retrieval. This card is required and contains four fixed format fields as follows:

Cols 1-7 \$\$QUERY

Cols 12-13 Major sort key

Cols 16-23 Query name

Col 26 Type 2 Record processing indicator

The major sort key field is used to separate the answer sets from batched retrievals. The batched retrieval feature is not implemented. Therefore, this field may contain blanks or any other two characters.

The query name field contains a one to eight character name that is assigned to the query.

The type 2 record processing indicator field may contain a blank indicating that the type 2 records are to be included with each qualifying record or the letter N indicating that the type 2 records are to be omitted.

SORT Control Card

The sort control card indicates that a sorted answer set is desired. This card is optional and if present contains one fixed format field as follows:

Cols 1-6 \$SSORT

Immediately following the sort control cards are from one to five sort specification statements. The sequence of these cards determine the order of the sort minor key. The first card will be the high subfield of the minor key, the next will be the next lower subfield and the last card will be the lowest subfield of the sort minor key. Each sort statement consists of two fixed format fields as follows:

Col 7-36 Sort name

Col 38-47 Sort order

The sort name field contains the name of a data file field which is to be sorted. This name must be one of the names listed in Table 3.2-1 or 3.2-2.

The sort order field describes the order of sorting the specified field.

This field must contain the word ASCENDING or DESCENDING depending on the desired sort order.

For example, if the order of the sort control cards is as follows:

AQCR ASCENDING

PLANT DESCENDING

POLLUTANT ID DESCENDING

The retrieved data will be sorted first by AQCR in ascending order, then by plant in descending order within each AQCR, then by Pollutant ID within each Plant in descending order. The user must visualize how the sort specifications will cause the data to be presented in the requested report as this can make a significant difference in the amount of printout which will result assuming a report is generated.

The following list of names from the fixed segment may be referenced in a retrieval specification statement in either EIS fixed format or COBOL language.

AQCR PROPERTY-AREA

CITY SEGMENT-DAY

CONTACT SEGMENT-ID

COUNTY SEGMENT-YEAR

DATE-OF-SEGMENT STATE

LOCAL-CONTROL TELEPHONE

NUMBER-OF-EMPLOYEES USER-CONTROL-REGION

OWNER USER-PLANT-ID

PLANT-ID UTM-ZONE

PRINCIPAL-PRODUCT

The following two names from the fixed segment may be referenced in a retrieval specification in the COBOL language only.

ESTABLISHMENT

MAILING-ADDRESS

RETRIEVAL NAMES

Table 3.2-1

The following list of names from the point source segment may be referenced in a retrieval specification statement in either EIS fixed format or COBOL language.

ANNUAL-THRUPUT	JUN-AUG	SPACE-HEAT
ANNUAL-LUNUFUL	2011-2013	DI AGE-DEAL

BOILER-DESIGN-CAPACITY LATITUDE STACK-DATA

COMPLIANCE-SCHEDULE LATITUDE-DEGREE TEMPERATURE

COMPLIANCE-SCHEDULE-MONTH LATITUDE-MINUTE USER

COMPLIANCE-SCHEDULE-YEAR LATITUDE-SECOND UTM-COORDINATES

COMPLIANCE-STATUS LONGITUDE UTM-HORIZONTAL

COMPLIANCE-STATUS-DAY LONGITUDE-DEGREE UTM-VERTICAL

COMPLIANCE-STATUS-MONTH LONGITUDE-MINUTE VELOCITY

COMPLIANCE-STATUS-UPDATE LONGITUDE-SECOND WEEK-YEAR

COMPLIANCE-STATUS-YEAR MAR-MAY

CONTROL-REGULATIONS NEDS

DAY-WEEK NORMAL-OPERATING

DEC-FEB PLUME

DIAMETER POINT-ID

ECAP POINT-SOURCE-DATA

POINTS-PER-STACK

EMISSION-NBR REG-1

FLOW-RATE REG-2

HEIGHT REG-3

HOURS-DAY SEP-NOV

IPP SIC

RETRIEVAL NAMES

Table 3.2-1 (Continued)

The following list of names from the repeating portion of the point source segment may be referenced in a retrieval specification statement in either EIS fixed format or COBOL language.

ALLOWABLE

ESTIMATION-METHOD

CNTL-EQUIP-COST

MEASURED

CONTROL-EQUIPMENT

POLLUTION-ID

EMISSION-UNITS

PRIMARY

EMISSIONS

SECONDARY

EST-CONTROL-EFF

TEST-METHOD

ESTIMATES

REPEATING RETRIEVAL NAMES

Table 3.2-2

IF Control Card

The IF control card indicates the beginning of the retrieval specifications for this query. This card is required and may be in one of three formats.

o IF Format 1.

This format of the IF control card is as follows:

Cols 1-4 \$\$IF

The IF format 1 is used when it is desired to state the retrieval specification in EIS fixed format form.

Immediately following the IF format 1 card are the EIS fixed format retrieval specification cards. Each of these cards contain a clause of the retrieval specification where a clause is defined to consist of subject name, a relational operator and an object name. For example, A = B is a clause with A the subject name, = the relational operator and B the object name. A multiple clause retrieval specification, i.e., A = B AND C = D, consists of two clauses A = B, C = D connected by the logical connector AND. The format of fixed format retrieval specification cards is as follows:

Cols 8-6 Left Parenthesis

Cols 7-36 Subject name

Cols 38-39 Relational operator code

Cols 41-74 Object name

Cols 76-78 Logical connector

The left parenthesis field may contain up to four parentheses right justified in the field.

The subject name field must contain one of the data file field names listed in Table 3.2-1 or Table 3.2-2. Any other name will cause a diagnostic.

The relational operator field must contain one of the following codes left justified in the field.

Code	Meaning
=	equal
<	less than
>	greather than
N=	not equal
N<	not less than
N>	not greater than

The object name field may contain one of the data file field names listed in Table 3.2-1 or Table 3.2-2, a numerical literal, or an alphanumeric literal delineated by quotes. If right parentheses are needed to balance any left parentheses they must be placed in the object name field immediately after the last character of the object name.

The logical connector field may contain blanks or the words AND or OR.

Blanks in this field terminate the editing of the retrieval specification.

The words AND or OR indicate that another clause follows and editing is to continue.

o IF Format 2.

This format of the IF control card consists of three fixed format fields as follows:

Cols 1-4 SSIF

Cols 10-13 USER

Col 26 Qualification Type

The IF format 2 is used when it is desired to state the retrieval specification in COBOL language.

Immediately following the IF format 2 control cards are one or more cards containing the retrieval specification. These cards are punched according to COBOL rules for syntax and punctuation. The first word on the first card must be IF. Data file field names referenced in the retrieval specification must be one of those listed in Table 3.2-1 or Table 3.2-2. Since the EIS language processor does not examine these cards nay improper punching could result in COBOL diagnostics or unpredictable retrieval.

The qualification type field must be the character Y if the retrieval specification refers to any of the data file field names listed in Table 3.2-2.

o IF Format 3.

This format of the IF control card consists of four fixed format fields as follows:

Cols 1-4 \$\$IF

Cols 10-13 USER

Cols 16-23 Library member name

Col 26 Qualification Type

The IF format 3 is used when it is desired to insert a previously written COBOL language retrieval specification statement into a query. The retrieval specification must follow the rules defined for a retrieval specification following an IF format 2 control card. The main difference between IF format 2 and IF format 3 is that for format 2 the retrieval specification is in-line immediately following the IF format 2 control card while for format 3 the retrieval specification is from a user library by means of the member name field.

END Control Card

The END control card indicates the end of the set of statements for a retrieval. This card is required and contains \$\$END in card columns 1-5.


3.2.2 RETRIEVAL LOGIC

The following discussion will illustrate how the retriever processes the logical records of the data file. The processing varies depending on what fields are being used for qualification and whether or not a sort is specified and if so what field is being used for the sort.

For qualification purposes a logical record consists of the fixed segment (type Ø record) and a single point source segment (type 1 record).

Qualification cannot be performed on just the fixed segment. The machine process segments (type 2 records) cannot be used for qualification. At the user's option (the N in the query control card) they are either omitted or added to each qualifying logical record.


Assume that the following logical records exist on some data file.



The first logical record has a STATE value of 10, SIC value of 32 and five repetitions containing POLLUTION-ID values of 00001 to 00005 and ESTIMATES of 13 to 27. The second logical record has a STATE value of 09, SIC value of 35 and three repetitions. The following query examples will show how the two logical records will appear on the answer set.

It is desired to qualify all records that have a STATE value of 10 or 09. Sorting is not desired. The query is:

The answer set will contain the following two records. Since a sort was not specified the records will be in file order.




It is desired to qualify all records that have a STATE value of 10 or 09 and to sort the qualifying records in ascending order of STATE values. The query is:

\$\$QUERY EXAMPLE 2
\$\$SORT

STATE ASCENDING
\$\$IF USER

IF STATE = '10' OR = '09'
\$\$END

The answer set will contain the following two records and since a sort was specified to record order is changed.



It is desired to qualify all records that contain a POLLUTION-ID of 00001 or 00002 and to sort the qualifying records in ascending order of STATE values. This query is qualifying on a field in the repetitions data. The retriever cycles through the repetition data and marks those repetitions that meet the qualification. The repetitions that did not qualify are removed. The query for this is:

\$\$QUERY EXAMPLE 3


\$\$SORT

STATE ASCENDING

\$\$IF USER

IF POLLUTION-ID = '00001' OR = '00002'

The answer set will contain the following two records:



\$\$END

It is desired to qualify all records that contain a POLLUTION-ID of 00003 or 00005 and to sort the qualifying records according to POLLUTION-ID for STATE. This query is qualifying on a field in the repetitions data and also sorting on a field in the repetition data. The retriever cycles through the repetition data and for each repetition that meets the qualification outputs a logical record on the answer set. The query is:

\$\$QUERY EXAMPLE 4

\$\$\$ORT


STATE ASCENDING


POLLUTION-ID DESCENDING

\$\$IF USER

IF POLLUTION-ID = '00003' OR '00005'

The answer set for this query will contain the following four records:





4.0 OUTPUT PROGRAMS

There are five output programs in the EIS system, each producing a different form of output. These five are the File List, Summary Report, NEDS Point Source, NEDS Area Source, and NEDS Area Source Report output programs.


4.1 FILE LIST

This program produces a detail listing of the EIS master file. The master file is listed with one point source record per page. If a single plant location has more than one point source, the plant/location information is repeated for each point source page. If area source data is in the same file as point source, the point source data should be selected by use of the EIS retrieval capability (IF USER-PLANT-ID N = 'AREA SOURCE').


This program can also be used to print a detail listing of all of the retrieval answer files. It will list the area source records but the field headings will be meaningless.

The data flow and run deck setup are illustrated in Figure 4.1-1.

Data Flow



Deck



FILE LIST DATA FLOW AND DECK

Figure 4.1-1

4.2 SUMMARY REPORT

The EIS Summary capability is intended to be a tool for Air Pollution Control Agencies. It is used with the EIS Retrieval capability, i.e., the retrieval program will select data and sort it in order to produce the summary.

The following data values are summed.

- 1 Source Count This is a sum of sources emitting a pollutant.
- 2 Estimated Emissions This is a sum of estimated emissions.
- 3 Actual Emissions This is a sum of actual (measured) emissions.
- 4 Allowable Emissions This is a sum of allowable (standard) emissions.
- 5 Control Equipment Cost This is a sum of the cost for the control equipment.

A number (any combination of any five data fields in the point and stack data) of summarys can be produced. There can be from one to five levels of totals. These are specified by supplying simple "Move" statements.

Example:

MOVE AQCR TO BREAK-ONE

The field to be summed is moved into a system control field. There are five such control fields, each corresponding to the five levels of totals. The control fields are:

BREAK-ONE Lowest level of total

BREAK-TWO Next higher level

BREAK-THREE Next higher level

BREAK-FOUR Next higher level

BREAK-FIVE Highest level of total

The data must be sorted to correspond to the Summary being produced. This is accomplished by executing the EIS retrieval capability to produce the Summary input data. Note that because emissions are by pollutant, one of the sorts must be pollutant identification to produce a meaningful summary.*

o Example 1:

To produce a summary of emissions by SIC within a county, the following retrieval and summary statements must be provided by the user (retrieval qualifications are not shown).

^{*}The only meaningful summary totals are those at the POLLUTION-ID level. If all of the data items are for the same pollutant then all totals are meaningful. If two or more pollutants have been selected, only the totals up to the level for POLLUTION-ID are meaningful. For example, if POLLUTION-ID were at BREAK-THREE level, BREAK-ONE, BREAK-TWO, and BREAK-THREE level sums would be meaningful but BREAK-FOUR and BREAK-FIVE sums would not be meaningful.

Retrieval

SORT SIC, COUNTY, POLLUTION-ID (major to minor)

Summary

MOVE MSTR-POLLUTION-ID (EM-SET-INDEX) TO BREAK-ONE.

MOVE MSTR-COUNTY TO BREAK-TWO.

MOVE MSTR-SIC TO BREAK-THREE.

o Example 2:

To produce a summary of emissions by PLANT within SIC within CITY within COUNTY the following retrieval and summary statements must be provided.

Retrieval

SORT COUNTY, CITY, SIC, PLANT, POLLUTION-ID

Summary

MOVE MSTR-POLLUTION-ID (EM-SET-INDEX) to BREAK-ONE.

MOVE MSTR-PLANT TO BREAK-TWO.

MOVE MSTR-SIC TO BREAK-THREE.

MOVE MSTR-CITY TO BREAK-FOUR.

MOVE MSTR-COUNTY TO BREAK-FIVE.

The summary report can be personalized, i.e., certain page header and column header information can be provided by the user. This information is provided on control cards. The information can be changed each time the summary is executed.

Control cards for providing information to the summary report are described below.

Card 1		
Cols	Content	Default
1-3	OP1	
6-37	Line 1 of Report Title	EMISSIONS INVENTORY SYSTEM
38-69	Line 2 of Report Title	STANDARD SUMMARY OUTPUT
71-78	Date	
Card 2		
Cols	Content	Default
1-3	OP2	
6-37	From Organization	AIR POLLUTION CONTROL AGENCY
38-69	To Organization	INFORMATION

Card 3		
Cols	Content	Default
1-3	OP3	
6-13	Part 1 of Column 1 Header	BREAK
14-21	Part 2 of Column 1 Header	FIVE
22-29	Part 1 of Column 2 Header	BREAK
30-37	Part 2 of Column 2 Header	FOUR
38-45	Part 1 of Column 3 Header	BREAK
46-53	Part 2 of Column 3 Header	THREE
54-61	Part 1 of Column 4 Header	BREAK
62-69	Part 2 of Column 4 Header	TWO
Card 4		
Cols	Content	Default
1-3	OP4	
6-13	Part 1 of Column 5 Header	BREAK
14-21	Part 2 of Column 5 Header	ONE

The Summary Report Control Cards are used to "personalize" this report.

A report header defaults are as follows:

AIR POLLUTANT EMISSIONS SUMMARY

EMISSIONS INVENTORY SYSTEM FROM AIR POLLUTION CONTROL AGENCY


STANDARD SUMMARY OUTPUT TO INFORMATION


BREAK BREAK BREAK BREAK

FIVE FOUR THREE TWO ONE

The summary statements (MOVE) are actually compiled into a program and executed. It is this program which reads the control cards (if any) and produces the summary report.


A summary program can be temporary (for ad-hoc reports) or permanent (for standard reports), i.e., the program can be compiled, used and deleted from the system or it can be compiled and stored on a library to be used over and over again. These options are illustrated by figures 4.2-1 through 4.2-3.






PERMANENT SUMMARY REPORT GENERATION


Figure 4.2-1






PERMANENT SUMMARY REPORT EXECUTION

Figure 4.2-2





TEMPORARY SUMMARY REPORT GENERATION AND EXECUTION


Figure 4.2-3


4.3 NEDS POINT SOURCE OUTPUT

The NEDS point source output program converts the records on an EIS file to NEDS format point source records. Each EIS record is converted as follows: the type Ø record produces an AP1 record; the type 1 record produces AP2, AP3, AP4 and AP5 records; and each type 2 record produces an AP6 record. If a single plant (type Ø record) has more than one point source (type 1 record), the AP1 record is repeated for each new type 1 record. If area source data is in the same file as point source data, the point source data should be selected onto a separate file by use of the EIS retrieval capability (IF USER-PLANT-ID N = 'AREA SOURCE').

The data flow and run deck setup are illustrated in Figure 4.3-1.

Data Flow





NEDS POINT SOURCE OUTPUT - DATA FLOW AND DECK Figure 4.3-1

4.4 NEDS AREA SOURCE OUTPUT

This program produces NEDS Area Source output from EIS Area Source data.

The program expects input to be Area Source data. Therefore, if Area

Source data is in the same file as Point Source data, it must be

selected onto a separate file by use of the EIS retrieval capability

(IF USER-PLANT-ID = AREA SOURCE).


There is one control card which allows the user to specify whether the NEDS "action" code will be A (add), D (delete) or C (change). All action codes must be the same for a given run. Default (no control card) will be A.

Control Card Format


Cols	Content
1-16	NEDS AREA SOURCE
17	Not Used
18	Action Code
19-80	Not Used

The data flow and deck setup is illustrated in Figure 4.4-1.

Data Flow



Deck



NEDS AREA SOURCE OUTPUT - DATA FLOW AND DECK


Figure 4.4-1

4.5 NEDS AREA SOURCE REPORT

The NEDS area source report program produces a formatted listing from NEDS area source records. One complete set of NEDS area source records (AAl through AA6) will be listed per page. If errors exist in the NEDS records, the results will be unpredictable.

The data flow and run deck setup are illustrated in Figure 4.5-1.

Data Flow



Deck

NEDS Area Source JCL

NEDS AREA SOURCE REPORT - DATA FLOW AND DECK

Figure 4.5-1

5.0 DATA CONVERSION PROGRAMS

There are two EIS conversion programs which convert other types of data to EIS format. These are the NEDS Point Source to EIS and the NEDS Area Source to EIS.

5.1 NEDS POINT SOURCE TO EIS

This Program converts NEDS Point Source input to the Emission Inventory System transaction card format. The one (1) card in the NEDS Point Source input creates the EIS zero (0) record transaction cards. Cards two (2) through five (5) in the NEDS Point Source input create the EIS one (1) record transaction cards. The six (6) card in the NEDS Point Source input creates the EIS two (2) record transaction cards.

All data items in the EIS transaction records which have no corresponding data items in the NEDS input records are set to blanks with the exception of the following:

- 1. SET-ID (SEGMENT-1-ID) Set to the same value as the NEDS POINT-ID.
- 2. POLLUTANT-ID Five digit parameter codes are given to pollutants reported in NEDS input data. These codes are taken from the <u>SAROAD Parameter Coding Manual</u>, EPA Publication No. APTD-0633.-
- 3. SEGMENT-2-ID Initialized to 5 and incremented by 5 for each AP6 card. (2 digits)
- 4. EMISSION-FACTOR-SOURCE (EF-SOURCE) A one byte code telling the emission factor program to provide POLLUTANT-ID's. Set to "A" for the Emission Factors Insertion Program.

5.2 NEDS AREA SOURCE TO EIS

This program converts NEDS Area Source input to the Emission Inventory System transaction card format. The first five (5) area source input cards are all required to generate the EIS transaction records.

All data items in the EIS transaction records which have no corresponding data items in the NEDS input records are set to blanks with the exception of the following:

- USER-PLANT-ID A literal of 'AREA SOURCE' is placed in this field.
- PLANT-ID PLANT-ID is set to 9999 since the lowest level addressed is the Area Quality Control Region (AQCR).
- 3. NUMBER-OF-EMPLOYEES This field is filled by the value in the county population field of the three (3) cards in NEDS Area Source input.
- 4. SET-ID SET-ID is initialized to \$\psi1\$ and incremented sequentially by 1 for each emission category reported on the NEDS

 Area Source input records (e.g., RESIDENTIAL FUEL = \$\psi1\$,

 COMMERCIAL AND INSTITUTIONAL FUEL = \$\psi2\$, INDUSTRIAL = \$\psi3\$, etc.)
- 5. NEDS-POINT-ID The NEDS-POINT-ID is set to 99 since the AQCR is again the smallest area reported on. (2 digits)

- 6. USER-POINT-ID There are thirteen USER-POINT-IDs corresponding to the thirteen major categories reported in NEDS Area Source input. (3 digits.)
 - 901 = RESIDENTIAL FUEL
 - 902 = COMMERCIAL AND INSTITUTIONAL FUEL
 - 903 = INDUSTRIAL FUEL
 - 904 = ON SITE INCINERATION
 - 905 = OPEN BURNING
 - 906 = GASOLINE FUEL
 - 9Ø7 = DIESEL FUEL
 - 908 = AIRCRAFT
 - 909 = VESSELS
 - 910 = EVAPORATION
 - 911 = MEASURED VEHICLE MILES
 - 912 = MISCELLANEOUS DUST
 - 913 MISCELLANEOUS BURNING
- 7. SIC SIC is set to 9999. (4 digits.)
- 8. IPP IPP is set to 99. (2 digits.)
- 9. POLLUTANT-ID POLLUTANT-ID is given the five digit code from the SAROAD Parameter Coding Manual, EPA Publication No. APTD-0633 representing the five major pollutants reported.
- 10. ESTIMATION METHOD ESTIMATION METHOD is set to '3' indicating that emissions are to be calculated.

- 11. SCC SCC codes are supplied by the program reflecting the area code, SDD-ID, sulfur indicator, and ash indicator.
- 12. FUEL PROCESS SOLID WASTE RATE The value here will be the value found in each fuel reported under the major emission categories.

		Category	EIS ID (USER-POINT-ID)	Fuel/Pollutant Source	(AREA) SCC
		Residential Fuel	901	Anthracite Coal	90100111
				Bituminous Coal	90100222
				Distillate Oil	90100330
				Residual Oil	90100440
				Natural Gas	90100500
				Wood	90100600
		Commercial and Insti-	902	Anthracite Coal	90200111
		tutional Fuel		Bituminous Coal	90200222
				Distillate Oil	90200330
				Residual Oil	90200440
	>			Natural Gas	90200500
	AREA			Wood	90200600
		Industrial Fuel	903	Anthracite Coal	90300111
	SOURCE Table			Bituminous Coal	90300222
	OURCE Tab le			Coke	90300700
	CE le			Distillate Oil	90300330
				Residual Oil	90300440
	AT			Natural Gas	90300500
	EG -1			Wood	90300600
	i g			Process Gas	90300800
	CATEGORIES 5.2-1	On Site Incineration	904	Residential	90401100
	S			Industrial	90401200
				Commercial/Institutional	90401300
		Open Burning	905	Residential	90501100
		-		Industrial	90501200
				Commercial/Institutional	90501300
		Gasoline Fuel	906	Light Vehicle	90602100
				Heavy Vehicle	90602200
				Off Hiway	90602300
		Diesel Fuel	907	Heavy Vehicle	90702200
				Off Hiway	90702300
				Rail Locomotive	90702400

			(USER-POINT-ID)		
		Aircraft	908	Military Civil Commercial	90803100 90803200 90803300
		Vessels	909	Anthracite Coal Diesel Oil Residual Oil Gasoline	90900111 90904230 90900440 90904430
		Evaporation	910	Solvent Purchased Gasoline Marketed	91005100 91005200
	AREA	Measured Vehicle Miles	911	Limited Access Roads Rural Roads Suburban Roads Urban Roads	91106100 91106200 91106300 91106400
96	SOURCE CATEG Table 5.2-1 (continued)	Miscellaneous Dust	912	Dirt Roads Traveled Dirt Air Strips Construction Land Area Rock Handling & Storing	91207100 91207200 91207300 91207400
	CATEGORIES 5.2-1 lnued)	Miscellaneous Burning	913	Forest Fires Slash Burning Frost Control Structure Fires Coal Refuse Burning	91308100 91308200 91308300 91308400 91308500

Fuel/Pollutant Source

(AREA) SCC

EIS ID

Category

CARD Ø1:

FIELD

State County AQCR Plant ID

Date of Record User Plant ID

Own
Action
Card Number
All Other Fields

CONTENTS

NEDS State NEDS County NEDS AQCR 9999

NEDS Year of Record-Day ØØØ

AREA SOURCE NEDS Density NEDS Action

Ø1 Blanks

CARD Ø2:

FIELD

State through Date of Record Number of Employees Action Card Number All Other Fields

CONTENTS

Same as Card Ø1 NEDS County Population NEDS Action Ø2 Blanks

CARD Ø3:

FIELD

State through Date of Record Action Card Number All Other Fields

CONTENTS

Same as Card Ø1 NEDS Action Ø3

Blanks

CARD 11:

CONTENTS FIELD State through Date of Record Same as Card Ø1 Set ID Emission Source Count Internally Generated Point ID - NEDS Point ID-User Category Code SIC 9999 IPP 99 Action NEDS Action

11

Blank

CONTENTS

CARD 12:

FIELD

Card Number

All Other Fields

			
State through Set ID	Same as Card 11		
Action NEDS Actio			
Card Number	12		
All Other Fields	Blanks		

CARD 13:

CONTENTS		
Same as Caro	1 11	
Pollutant ID Cod Particulates - 11101		
NOX	- 42602	
нс	- 43101	
CO	- 421Ø1	
ØØØ		
3		
NEDS Action		
13		
B la nks		
	Same as Card Pollutant II Particulat SO2 NOX HC CO ØØØ 3 NEDS Action 13	

EIS AREA SOURCE RECORDS Table 5.2-2 (cont.)

CARD 21:

FIELD

State through segment 1 ID

Segment 2 ID

SCC

Fuel, Process, Solid Waste

Percent Sulfur Percent Ash Heat Content

Action Card Number All Other Fields

CARD 22:

FIELD

State through Segment 2 ID Action

Card Number All Other Fields

CARD 23:

FIELD

State through Segment 2 ID

Action Card Number All Other Fields CONTENTS

Same as Card 11 Internally Generated

Segment Count

NEDS Fuel/Pollution times

Heat Content if not

zero

NEDS Percent Sulfur

NEDS Percent Ash

Zero or NEDS quantity (Forest fires, slash burning, frost control and coal

refuse burning) .

NEDS Action

21 Blanks

CONTENTS

Same as Card 21

NEDS Action

22

Blanks

CONTENTS

Same as Card 21

NEDS Action

23

Blanks

EIS AREA SOURCE RECORDS Table 5.2-2 (cont.)

6.0 EMISSION FACTORS TABLE PROGRAMS

There are three EIS programs to facilitate the creation, maintenance and use of the emissions factors tables. These are the Emissions Factors

Table Generator, Emission Factors Transaction Generator and Emission

Factors Insert Programs.


6.1 EMISSION FACTORS TABLE GENERATOR

The CDHS Emission factors table generator constructs a two page table consisting of SCC numbers and their associated emission factors. The first page contains the SCC number, the date assigned to the SCC number and any ash and/or sulfur content percentage for that SCC number. The table generator program will assign to each SCC number an index value which points to the emission factors for the SCC. The emission factors are in the second page of the table. Each emission factor entry has an associated pollutant identification number, an emission factor units indicator and a flag indicating whether the ash or sulfur percentage is to be used when emission values are computed.

The emission factors table is generated from card input. There are two types of cards and they may be arranged in any order convenient to the user. The table capacity is 800 SCC numbers and 1200 emission factors. The two card formats are the SCC card format (type 1) and the emission factor card format (type 2).

o SCC Card Format

There must be one of these cards for each SCC number which is to be entered into the table. The format is:



o Emission Factors Card Format

There may be from one to sixteen of these cards for each SCC number.

The format is:

Cols 1 - 8	SCC Number
Cols 9 - 13	Pollutant Identification Number
Cols 14 - 22	Emission Factor (three assumed decimal places - XXXXXX.XXX)
Col 23	Units of Measure Code
Col 24	Ash/Sulfur (contains an A or S)
Col 79	2
SCC POLL. ID	EM. FACT. UNIT A/S 2 79

6.2 EMISSION FACTORS TRANSACTION GENERATOR

The emission factors transaction generator will allow the user to automatically update the EIS master file to reflect new emission factors according to an SCC data criteria. This program has a single fixed format control card as follows:

Cols 1 - 5 SCC Date (Julian format YYDDD)

Col / Mode of Operation.

The SCC date field contains a date value which is used as a lower limit for the SCC emission factors table search. Each SCC in the emission factors table has an associated date. When the date associated with the SCC number in the table is equal to or chronologically later than the date on the control card, the new factors will be inserted into the transactions which are created by the transaction generator. These transactions are then used to update the file.

The user should keep a log of SCC codes versus dates so that all necessary emission factors may be updated. The mode of operation field should contain an A, T or N indicating A mode, T mode or N mode of operation.

If blank the default mode is T.

T mode: In this mode, the program examines the EF-SOURCE field of the type 2 master file record. If this field is not T, the type 2 record is skipped. If T, then the emission factors table is searched using the SCC as an argument. Each pollutant identification number in the type 2 record is used to search for the emission factors associated with the SCC number. If a previous emission factor is found, the new emission factor, the emission factor units of measure code, and the A/S (ash-sulfur) flag are inserted into that repetition.

N mode: In this mode, operation is identical to the T mode except that the EF-SOURCE field is not examined. Therefore, this mode will insert emission factors into all type 2 records which meet the SCC date criteria. The pollutant identification number search is still performed.

A mode: In this mode, the EF-SOURCE field is not examined and the pollutant identification number search is not performed. Therefore, this mode of operation will replace all the emission factors in all type 2 records with matching SCC codes whose SCC dates meet the date criteria.

6.3 EMISSION FACTORS INSERT

The CDHS emission factors insert program will search the emission factors table using the SCC number as an argument and insert one or more of the associated emission factor values into EIS file maintenance transactions prior to their input to file maintenance.

To perform this function, this program requires the EIS 21, 22 and one or more 23 transactions. The 21 transaction contains the SCC number to be used as the search argument. The EF-SOURCE field in the 22 transaction may contain a blank or the character A or T. If blank, emission factors insertion does not occur. If A or T, the program will operate in the ALL mode or the TABLE mode respectively.

ALL mode: In this mode the program will search the emission factors table using the SCC number in the 21 transaction as a search argument and insert all the emission factors that are associated with this SCC number. The ALL mode requires a single 23 transaction to immediately follow the 22 transaction containing the A in EF-SOURCE. The 23 transaction must contain the key fields; the remaining fields are ignored. For each emission factor a 23 transaction will be constructed by the program from the information supplied by the user's 23 card and from the emission factors table. The data inserted into the 23 transaction will be the pollutant identification number, the emission factor, the emission factor units of measure code and the A/S ash sulfur percentage flag.

TABLE mode: In this mode the program will search the emission factors table using the SCC number in the 21 transaction as a search argument and insert only those emission factors whose insertion is requested.

The TABLE Mode requires one or more 23 transactions to immediately follow the 22 transaction containing the T in EF-SOURCE. Each 23 transaction must contain from one to three pollutant identification numbers. The pollutant identification number is used to search the list of emission factors associated with the SCC number. If found the emission factor, the emission factor units of measure code and the A/S ash sulfur percentage flag are inserted into the 23 transaction.

7.0 SYSTEM OPERATION


This section explains how the various components of the EIS System are run on the computer. There are two parts to this Section. The first explains the use of the Job Control Language (JCL) cataloged procedures for executing each EIS component and the next gives an example of the use of the cataloged procedures.

7.1 CATALOGED PROCEDURES

The cataloged procedures supplied with EIS are discussed in the following pages. The documentation of each procedure consists of the following: a brief narrative discussing the function of the procedure and its inputs and outputs; a block flow diagram of the data flow through the procedure; a table of DDNAMES used by the EIS programs involved; a table of substitutable parameters controlling the procedure; and a listing of the procedure itself. Non-EIS DDNAMES such as STEPLIB and those needed by COBOL are not discussed in this section. Generally, most input data sets supplied by the user (control cards, etc.), are defined by the deferred DDNAME of INPUT.

7.1.1 EISANCNV - NEDS AREA SOURCE OUTPUT

EISANCNV is executed to output NEDS area source data from EIS file records. The input to the program consists of an EIS file (either master or answer) and is defined by EISFILE. There are two output files used by the program. The first, defined by NEDASFIL, contains the NEDS area source records produced by the program. The second, defined by NEDASLOG, contains diagnostic messages generated during the output process.



EISANCNV - Data Flow

Figure 7.1.1-1

DD NAME	Description
EISFILE	EIS master file to be converted
NEDASFIL	Data set to contain NEDS records
NEDASLOG	Print file for diagnostic messages

EISANCNV - DDNAMES

Figure 7.1.1-2

Parameter Name	Default Value	Description
PROJECT	EIS	Highest level index of data set names
		(e.g., EIS.DATA.EFTABLE)
PROGRAM	AXASNEDS	Program to convert EIS area source
		file to NEDS records
MSTRFIL	FTMSTRAA	Lowest level index of EIS file to be
		converted
NEDSOUT	В	Sysout class of NEDS records
OUT	A	Sysout class of all print files
		·

EISANCNV - Substitutable Parameters
Figure 7.1.1-3

113

//#	EISANCNV	HURLEY RF	WF4	06/30/74	00000100
//*					00000200
//EISANCNV P	ROC PROJECT=EIS.				00000300
11	PRUGRAM= AX ASNEDS	•			00000400
11	MSTRFIL=FTMSTRAA	•			00000500
11	NEDSOUT=B.				00000600
11	OUT=A				00000700
//*					03000800
//CONVERT EX	EC PGM=GPROGRAM.				00000900
11	REGION=24K.				00001000
11	TIME=(1.0)				00001100
// *					00001200
//* CONVERT	EIS AREA SOURCE FIL	E TO NEDS FORMAT			00001300
//*	-				00001400
//STEPLIB	DD DSNAME=& PRUJECT.	·LUAD.			00001500
11	VOLUME = (PRIVATE .				0001600
11	DISP=(SHK.PASS)				00001700
11	DD DSNAME=SYS1.ANS.	COBSUBR •			00001800
//	DISP=(SHR.PASS)				00001900
//*					00002000
	TA SET - EIS MASTER	FILE			00002100
//*					03002200
	DD DSNAME=&PRUJECT.	_OATA_EMSTREIL.			00002300
//	VOLUME = (PRIVATE.				00002400
"	DISP=(SHR.PASS)				00002500
//*	0.5. (5(7.25)				00002600
	ATA SET - NEDS FILE				00002700
//*	ATT SET MESS TICE				00002800
	DO SYSOUT=ENEDSOUT				00002900
//*	50 513001 - 4 112 53001				00003000
	ATA SET - DIAGNUSTI	C MESSAGES			00003100
//*	717 321 017070311	0 112334023			00003200
• •	TUO3=TUOSYS OUT				00003300
//*	00 3:300:-400:				00003400
	ATA SETS - SYSTEM O	DEDATION			00003500
//*	MIN 3213 - 3131EN 0	FERALION			03003500
//SYSPRINT	DD SYSUUT=&OUT				00003700
//*	00 313001-2001				00 00 3 8 0 0
	DD CVCDUT-COUT				00003900
//SYSOUT	DD SYSOUT=&OUT				00004000
//*	DD EXECUT-COLT				00004000
//SYSUROUT	DD SYSOUT=EOUT				
//*	DD EXECUT-COLF				00004200
//SYSDTERM	DD SYSOUT=EOUT				00004300
//*	OR CHECHT COUT				00004400
//SYSUDUMP	DD SYSOUT=&OUT				00004500
//#					03004600

7.1.2 EISANRPT - NEDS AREA SOURCE REPORT

EISANRPT is executed to produce a formatted listing of NEDS area source records. The input to the program consists of NEDS area source records and is defined by NEDSFILE. There are two output files used by the program. The first, defined by EISPRINT, contains diagnostic messages produced during the reporting process. The second, defined by NEDSPRINT, contains the formatted listing of the NEDS records.




Figure 7.1.2-1

DDNAME	Description
NEDSFILE	NEDS Area Source Records to be Listed
NEDSPRINT	Print File for Area Source Listing
EISPRINT	Print File for Diagnostic Messages
,	

EISANRPT - DDNAMES

Figure 7.1.2-2

Parameter	Default Value	Description
Name	value	Description
PROJECT	EIS	Highest level index of data set
;		names (e.g., EIS.DATA.EFTABLE)
PROGRAM	HXANREPT	Program to list NEDS area source
		records
NEDSFIL	NEDS	Lowest level index of NEDS file to
		be listed
OUT	A	Sysout class of all print files

EISANRPT - Substitutable Parameters

Figure 7.1.2-3

EISANRPT Procedure


Figure 7.1.2-4

EIS CATALOGED PROCEDURES

//*	EISANRPT	HURLEY	RF	WF4	06/30/74	00000100
//*						00000200
//EISANRPT PRO	C PROJECT=EIS.					00000300
//	PKOGRAM=HXANREPT.					00000400
//	NEUSFIL=NEUS.					00000500
11	OUT = A					00000600
//#						00000700
//REPURT EXEC	PGM= &PROGRAM .					00000800
//	REGION=40K.					00000900
11	TIME=(1.0)					00001000
//#	:					001100
	DS AREA SOURCE DETAIL RE	EPGRT				00001200
//*						00001300
//STEPLIB DD	DSNAME=&PRUJECTLUAD,					00001400
//	VOLUME=(PRIVATE , RETAIN	1.				0001500
//	DISP=(SHR.PASS)					00001600
// 00	DSNAME=SYS1.ANS.CUBSUB	R•				0001700
11	DISP=(SHR.PASS)					00001800
//#						00001900
	SET - NEDS AREA SOURCE	FILE				00002000
//*						0002100
//NEDSFILE DD	DSNAME=&PRUJECTDATA.	ENEDSFIL	•			0002200
//	VOLUME=(PRIVATE, RETAIN	1,				00002300
//	DISP=(SHR.PASS)					00002400
//*						00002500
	E - NEDS AREA SOURCE DE	TAIL REPO	DRT			0002600
//*						0072700
	SYSOUT=EOUT					0002800
//*			•			00002900
	E - DIAGNOSTIC MESSAGES					00063000
//*						00003100
	SYSOUT=&OUT					0003200
//*		•				00003300
	A SETS - SYSTEM UPERATI	ON				00003400
//*						00003500
	TUO3=TUO2Y2					00003600
//=						00003700
	SYSOUT=&OUT					00003800
//*·						00003900
//SYSDBOUT DD	SYSOUT=&OUT					00004000
//*						00004100
//SYSDTERM DD	SYSOUT=&OUT					0004200
//#						00004300
/ / T						
• •	SYSOUT=COUT					00004400

7.1.3 EISCNVRT - NEDS POINT SOURCE TO EIS

EISCNVRT is executed to convert NEDS point source records to EIS transactions. The input to the conversion program consists of a NEDS point
source file and is defined by NEDSFILE. There are two output files
used by the conversion program. The first, defined by EISTRANS, contains
the EIS file maintenance transactions produced by the conversion program.
The second, defined by EISPRINT, contains diagnostic messages generated
during the conversion process.



EISCNVRT - Data Flow Figure 7.1.3-1

DD NAME	Description
NEDSFILE	Data set containing NEDS point source records
EISTRANS	Data set to contain generated EIS transactions
EISPRINT	Print file for diagnostic messages
	·
	·

EISCNVRT - DDNAMES

Figure 7.1.3-2

Parameter Name	Default Value	Description
PROJECT	EIS	Highest level index of data set
		names (e.g., EIS.DATA.EFTABLE)
PROGRAM	CXNEDSCV	Program to convert NEDS point source
		records to EIS transactions
OUT	A	Sysout class of all print files

EISCNVRT - Substitutable Parameters

Figure 7.1.3-3


EIS CATALOGED PROCEDURES

//# EISCNVRT HURLEY RF 06/30/74 00000100 WF4 // 00000200 //EISCNVRT PROC PROJECT=EIS. 00000300 00000400 11 PROGRAM=CXNEDSCV. 11 $\Omega UT = A$ 00000500 //* 00000600 //CONVERT EXEC PGM=&PROGRAM. 00000700 REGION=20K. 00800000 11 TIME=(1.0) 00000900 //# 00001000 //* CONVERT NEDS POINT SOURCE RECORDS TO EIS TRANSACTIONS 00001100 00001200 00001300 //STEPLIB DD DSNAME=&PROJECT..LOAD, 11 VOLUME = (PRIVATE . RETAIN) . 00001400 00001500 11 DISP=(SHR.PASS) 'DD DSNAME=SYSI.ANS.COBSUBR. 00001600 11 00001700 11 DISP=(SHR, PASS) //+ 00001800 //* INPUT DATA SET - NEDS RECORDS 00001900 0002000 //NEDSFILE DD DDNAME=INPUT. 00002100 0002200 11 DCB=BLKSIZE=80 //* 00002300 //# OUTPUT DATA SET - EIS TRANSACTIONS 00002400 00002500 //# 00002600 //EISTRANS DD DDNAME=OUTPUT 00002700 00002800 1/ DUTPUT DATA SET - DIAGNOSTIC MESSAGES 1/# 00002900 00003000 //EISPRINT DD SYSOUT=&OUT 02003100 1/* 0003200 //* OUTPUT DATA SETS - SYSTEM UPERATION 00003300 //* //SYSPRINT DD SYSOUT=&OUT 00003400 03003500 **//**‡ 00003600 //SYSOUT DD SYSOUT=&OUT 00003700 1/# //SYSOBOUT DD SYSOUT=&CUT 00003800 00003900 1/# //SYSDTERM DD SYSOUT=&OUT 00004000 00004100 //SYSUDUMP DD SYSOUT=&OUT 00004200 00004300 //#

ISCNVRT Procedure
Figure 7.1.3-4

7.1.4 EISEFGEN-EMISSION FACTORS TABLE GENERATOR

EISEFGEN is executed to generate an emission factors table. The input to the generation program consists of emission factors table transactions and is defined by ETBGIN. There are two output files used by the generation program. The first, defined by ETBGTABL, contains the emission factors table produced by the generation program. The second, defined by ETBGERR, contains diagnostic messages generated during the emission factors table generation process.



EISEFGN - Data Flow

Figure 7.1.4-1

DD NAME	Description
ETBGIN	Emission factor table transactions
ETBGERR	Print file for diagnostic messages
ETBGTABL	Data set to contain emission factors table
1	1

EISEFGEN - DDNAMES

Figure 7.1.4-2

Parameter	Default	Description
PROJECT	EIS	Highest level index of data set
		names (e.g., EIS.DATA.EFTABLE)
PROGRAM	EXTBGN	Program to generate emission factors
		table
EFTABLE	EFTABLE	Lowest level index of emission
		factors table
UNIT	2314	Unit type upon which the emission
		factors table is to reside
SERIAL	ØØ9 858	Volume serial of volume upon which
		emission factors table is to reside
DISP	'NEW, CATLG,	Disposition of emission factors
	DELETE '	table
SPCUNIT	TRK	Units in which space for the emis-
		sion factor table is to be allocated
PRIMARY	5	Number of units to be allocated for
		the emission factors table's
		primary allocation
SECNDRY	1	Number of units to be allocated for
		the emission factors table's
		secondary allocation
TEMP	SYSOUT	Unit type for temporary work space
OUT	A	Sysout class for all print files

EISEFGEN - Substitutable Parameters

Figure 7.1.4-3

128

Figure 7.1.4-4

```
//#
                EISEFGEN
                                        HURLEY RF
                                                           WF4
                                                                 06/30/74 00000100
//#
                                                                          02000200
//EISEFGEN PROC PROJECT=EIS.
                                                                          02000300
11
                PROGRAM=EXTRGN.
                                                                          02000400
11
                EFTABLE = EFTABLE.
                                                                          00000500
11
                TEMP=SYSOUT.
                                                                          00000600
11
                                                                          00000700
                UNIT=2314.
11
                SERIAL =009858.
                                                                          00000800
 11
                DISP= NEW. CATLG. DELETE .
                                                                          00000900
11
                SPCUNIT=TRK.
                                                                          00001000
11
                PRIMARY= 5.
                                                                          00001100
 11
                SECNDRY=1.
                                                                          00001200
11
                OUT≠A
                                                                          02001300
//#
                                                                          02001400
//GENERATE EXEC PGM=&PROGRAM.
                                                                          00001500
11
                REGION=100K.
                                                                          03001600
11
               TIME=(1,0)
                                                                          03001700
//#
                                                                          00810000
//* GENERATE EIS EMISSION FACTORS TABLE
                                                                          00001900
 //#
                                                                          00002000
//STEPLIB DD DSNAME=&PROJECT..LOAD.
                                                                          00002100
11
                VOLUME=(PRIVATE.RETAIN).
                                                                          0002200
11
                                                                          00002300
                DISP=(SHR:PASS)
11
             DD DSNAME=SYS1.ANS.COBSUBR.
                                                                          00002400
11
                DISP=(SHR. PASS)
                                                                          00002500
1/*
                                                                          00002600
//# INPUT DATA SET - EF TABLE TRANSACTIONS
                                                                          0002700
                                                                          0002800
//ETBGIN
            DD DDNAME=INPUT.
                                                                          00002900
11
                DCB=BLKSIZE=80
                                                                          00003000
 //#
                                                                          00003100
 //# INPUT DATA SET - SORT PROGRAM LIBRARY
                                                                          00003200
 //#
                                                                          00003300
 //SORTLIB DD DSNAME=SYS1.SURTLIB.
                                                                          00003400
 11
                VOLUME=(PRIVATE.RETAIN).
                                                                          00003500
 11
                DISP=(SHR.PASS)
                                                                          00003600
                                                                          00003700
 //#
 //# UUTPUT DATA SET - DIAGNOSTIC MESSAGES
                                                                          00003800
 //#
                                                                          00003900
 //ETBGERR DD SYSOUT=COUT
                                                                          00004000
                                                                          00004100
 //# OUTPUT DATA SET - EMISSION FACTORS TABLE
                                                                          00004200
                                                                          02004300
 //*
 //ETBGTABL DD UNIT=EUNIT,
                                                                          00004400
                                                                          00004500
 11
                VULUME=(PRIVATE, KETAIN, SER=&SERIAL),
                DISP=(&DISP).
 11
                                                                          00004600
                SPACE=(&SPCUNIT,(&PRIMARY,&SECNORY),RLSE).
                                                                          00004700
 11
 11
                DSNAME=&PROJECT .. DATA. &EFTABLE
                                                                          00840000
 //#
                                                                          00004900
 //* UTILITY DATA SETS
                                                                          00005000
                                                                          00005100
. //*
 //SURTWKO1 DD UNIT-ETEMP.
                                                                          00005200
                                                                          00005300
 11
                SPACE=(TRK,(10,5),,CONTIG)
 //#
                                                                          00005400
 //SURTWKO2 DD UNIT=(&TEMP.SEP=SURTWK01).
                                                                          00005500
                                                                          00005600
                SPACE=(TRK,(10,5)..CUNTIG)
```


EIS CATALOGED PROCEDURES

//SURTWK03 DD UNIT=(&TEMP.SEP=(SURTWK01,SORTWK02)), 00005800 // SPACE=(TRK.(10.5)CUNTIG) 00005900 //*
00006000
.,
//* UUTPUT DATA SETS - SYSTEM UPERATION 00006100
//*
//SYSPRINT DD SYSOUT=&OUT 00006300
//*
//SYSOUT
//*
//SYSDBOUT DD SYSDUI=&OUT 00006700
//*
//SYSDTERM DD SYSOUT=&OUT 00006900
//*
//SYSUDUMP DD SYSUUT=&OUT 00007100
// * 0007200

EISEFGEN Procedure

7.1.5 EISEFINS - EMISSION FACTORS INSERT

EISEFINS is executed to insert emission factors into EIS file maintenance transactions. There are two input files used by the insertion program. The first, defined by EFIXTIN, contains the EIS transactions into which the emission factors are to be inserted. The second, defined by EFIXTABL, contains the emission factors table. There are two output files used by the insertion program. The first, defined by EFIXTOUT, contains the EIS transactions into which the emission factors have been inserted. The second, defined by EFIXERR, contains diagnostic messages generated during the insertion process.



EISEFINS - Data Flow

Figure 7.1.5-1

DD NAME	Description		
EFIXTIN	EIS Transactions into which emission factors are to be		
	inserted		
EFIXTABL	Emission factors table		
EFIXERR	Print file for diagnostic messages		
EFIXTOUT	Data set to contain EIS transactions into which		
	emission factors have been inserted.		
1			

EISEFINS - DDNAMES

Figure 7.1.5-2

Parameter	Default	T
Name	Value	Description
PROJECT	EIS	Highest level index of data set
		names (e.g., EIS.DATA.EFTABLE)
PROGRAM	EXEFIX	Program to insert emission factors
		into EIS transactions
EFTABLE	EFTABLE	Lowest level index of emission
		factors table
TRANS	TRANS	Lowest level index of EIS trans-
		actions
UNIT	2314	Unit type upon which the EIS trans-
		actions are to reside
SERIAL	ØØ9858	Volume serial of volume upon which
:		the EIS transactions are to reside
DISP.	'NEW, PASS,	Disposition of EIS transactions
	DELETE'	
SPCUNIT	TRK	Units in which space for the EIS
]	transactions is to be allocated
PRIMARY	5	Number of units to be allocated for
		the EIS transactions' primary
		allocation
SECNDRY	1	Number of units to be allocated for
		the EIS transactions' secondary
		allocation

EISEFINS - Substitutable Parameters (Sheet 1 of 2)

Figure 7.1.5-3

TEMP	SYSOUT	Unit type for temporary work space
OUT	A	Sysout class of all print files.
		<u> </u>

EISEFINS - Substitutable Parameters (Sheet 2 of 2)

135

Figure 7.1.5-4

```
//#
               EISEFINS
                                         HURLEY RF
                                                           WF4
                                                                  06/30/74 00000100
//#
                                                                           00000200
                                                                           00000300
//EISEFINS PROC PROJECT=EIS.
                                                                           02000400
               PROGRAM=EXEFIX.
11
                                                                           00000500
11
                EFTABLE = EFTABLE.
               TEMP=SYSOUT.
                                                                           00000600
11
                                                                           00000700
11
               UNIT=2314.
               SER I AL = 009858.
                                                                           00000800
11
11
               DISP='NEW. PASS. DELETE'.
                                                                           00000900
                                                                           00001000
11
               SPCUNIT=TRK.
11
               PRIMARY=5.
                                                                           00001100
11
                SECNDRY=1.
                                                                           00001200
                                                                           00001300
11
               TRANS=TRANS.
                                                                           00001400
11
                DUT=A
1/4
                                                                           02001500
                                                                           00001600
//INSERT EXEC PGM=&PROGRAM.
                REGION=100K.
                                                                           00001700
11
11
               TIME=(1.0)
                                                                           0001300
                                                                           00001900
114
//* INSERT EMISSION FACTORS INTO EIS TRANSACTIONS
                                                                           00002000
                                                                           00002100
//STEPL18
            DD USNAME=&PROJECT .. LOAD.
                                                                            00002200
                                                                            0002300
11
                VOLUME = ( PRIVATE . RETAIN) .
11
                                                                            00002400
                DISP=(SHR.PASS)
11
                                                                            00002500
            DD DSNAME=SYS1.ANS.COBSUBR.
11
                DISP=(SHR.PASS)
                                                                           00002600
//#
                                                                            00002760
//# INPUT DATA SET - EIS TRANSACTIONS
                                                                            00002800
                                                                            00002900
//#
//EFIXTIN
            DD DDNAME=INPUT.
                                                                            00003000
                DCB=BLKSIZE=80
                                                                            00003100
11
1/#
                                                                            00003200
//* INPUT DATA SET - EMISSION FACTORS TABLE
                                                                            00003300
//#
                                                                            00003400
//EFIXTABL DD DSNAME=&PRUJECT..DATA.&EFTABLE.
                                                                            00003500
11
                VOLUME=(PRIVATE.RETAIN).
                                                                            00 003600
11
                DISP=(SHR.PASS)
                                                                            00003700
1/#
                                                                            0003800
//* INPUT DATA SET - SORT PRUGRAM LIBRARY
                                                                            00003900
                                                                            00004000
//#
//SORTLIB
            DD USNAME=SYS1.SDRTLIB.
                                                                            00004100
11
                VULUME=(PRIVATE, RETAIN),
                                                                            00004200
                                                                            00004300
11
                DISP=(SHR.PASS)
                                                                            02004400
1/4
//* OUTPUT DATA SET - DIAGNOSTIC MESSAGES
                                                                            00004500
                                                                            00004600
//#
//EFIXERR
            TOD3=TUDSYS OU
                                                                            02004700
                                                                            0004800
//#
//#
                                                                            00004900
                                                                            00005000
//* OUTPUT DATA SET - UPDATED TRANSACTIONS
1/#
                                                                            00005100
                                                                            00005200
//EFIXTOUT DU UNIT=&UNIT.
11
                VOLUME = ( PRIVATE . RETAIN . SER = & SERIAL ) .
                                                                            00005300
                                                                            00005400
11
                . (YZIG3)=PZIG
11
                SPACE=(&SPCUNIT,(&PRIMARY, &SECNDRY), RLSE),
                                                                            00005500
11
                DSNAME=&PRUJECT..UATA.&TRANS
                                                                            00005600
```


EIS CATALOGED PROCEDURES

//*		00005700
//# UTILIT	Y DATA SETS	00005800
//*		00005900
//SORTWKO1	DD UNIT=&TEMP,	00006000
11	SPACE=(TRK,(10,5),,CONTIG)	00006100
//#		00 006 200
. //SORTWKO2	DD UNIT=(&TEMP,SEP=SURTWKO1),	00006300
11 .	SPACE=(TRK,(10,5),,CONTIG)	00 006400
//#		00006500
//SORTWK03	DD UNIT=(&TEMP.SEP=(SORTWKO1.SORTWKO2)).	0006600
11	SPACE=(TRK,(10,5),,CUNTIG)	00006700
//*		00 006800
//# DUTPUT	DATA SETS - SYSTEM OPERATION	00006900
//*	•	00007000
//SYSPRINT	DD SYSOUT=EOUT	00007100
//*		0007200
//SYSOUT	OD SYSOUT=&OUT.	00 00 73 00
//*	:	00007400
//SYS DBOUT	TUO3'=TUO2Y2 OO	00007500
//*		00007600
//SYSDTERM	DD SYSOUT=COUT	00007700
//*		0007800
//SYSUDUMP	DD SYSOUT=&OUT	00007900
//#		00008000

Figure 7.1.5-4 (cont.)

7.1.6 EISEFUPD - EMISSION FACTORS TRANSACTION GENERATOR

EISEFUPD is executed to update emission factors existing in the EIS master file with new emission factors from the emission factors table. There are three input files used by the emission factors transaction generator program. The first, defined by EFIFMSTR, contains the EIS file to be updated. The second, defined by EFIFTABL, contains the emission factors table. The third, defined by EFIFIN, contains the control card which determines the emission factors to be updated. There are two output files used by the program. The first, defined by EFIFXOUT, contains the EIS file maintenance transactions to update the emission factors in the master file. The second, defined by EFIFERR, contains diagnostic messages generated during the transaction generation process.



EISEFUPD - Data Flow

Figure 7.1.6-1

DD NAME	Description
EFIFIN	Control card
EFIFMSTR	EIS master file to be updated
EF I FT AB L	Emission factors table
EFI FERR	Print file for diagnostic messages
EFIFXOUT	Data set to contain generated EIS transactions

EISEFUPD - DDNAMES

Figure 7.1.6-2

Parameter Name	Default Value	Description
PROJECT	EIS	Highest level index of data set
		names (e.g., EIS.DATA.EFTABLE)
PROGRAM	EXEFIF	Program to create EIS transaction to
		update emission factors
MSTRFIL	FTMSTRAA	Lowest level index of EIS master
		file to be updated
EFTABLE	EFTABLE	Emission factors table
TRANS	TRANS	Lowest level index of data set to
		contain generated EIS transactions
UNIT	2314	Unit type upon which the EIS trans-
		actions are to reside
SERIAL	ØØ9858	Volume serial of volume upon which
		the EIS transactions are to reside
DISP	'NEW, PASS,	Disposition of EIS transactions
	DELETE'	
SPCUNIT	TRK	Units in which space for the EIS
		transactions are to be allocated
PRIMARY	5	Number of units to be allocated for
		the EIS transactions' primary
		allocation
SECNDRY	1	Number of units to be allocated for
		the EIS transactions' secondary
		allocation
OUT	A	Sysout class for all print files

EISEFUPD - Substitutable Parameters Figure 7.1.6-3

ISEFUPD

Procedure

```
//#
               EISEFUPD
                                        HURLEY RF
                                                                06/30/74 00000100
1/4
                                                                          00000200
//EISEFUPD PROC PROJECT=EIS.
                                                                          00000300
//
               PROGRAM=EXEFIF.
                                                                          00000400
11
               MSTRFIL=FTMSTRAA.
                                                                          00000500
11
               EFTABLE-EFTABLE.
                                                                          03000600
11
               TRANS=TRANS.
                                                                          00000700
11
               UNIT=2314.
                                                                          00000800
11
               SERIAL = 009858.
                                                                          00000900
11
               DISP= 'NEW. PASS. DELETE'.
                                                                          00001000
11
               SPCUNIT=TRK.
                                                                          00001100
11
               PRIMARY=5.
                                                                          00001200
11
               SECNDRY=1.
                                                                          00001300
11
               OUT = A
                                                                          00001400
//*
                                                                          00001500
//EFUPOATE EXEC PGM=&PROGRAM.
                                                                          00001600
11
               REGION=80K.
                                                                          00001700
               TIME=(1.0)
11
                                                                          00001800
//#
                                                                          00001900
//* PRODUCE EIS TRANSACTIONS TO UPDATE EMISSION FACTORS
                                                                          00002000
1/4
                                                                          00002100
//STEPLIB
            DD DSNAME=EPROJECT..LOAD.
                                                                          00002200
11
               VOLUME=(PRIVATE.RETAIN).
                                                                          00002300
11
               DISP=(SHR.PASS)
                                                                          00002400
11
            DD DSNAME=SYS1.ANS.CUBSUBR.
                                                                          00002500
11
               DISP=(SHR.PASS)
                                                                          00002600
//*
                                                                          00002700
//# INPUT DATA SET - CONTROL CARD
                                                                          00002800
1/*
                                                                          00002900
//EFIFIN
            DO DONAME-INPUT.
                                                                          00003000
11
               DCB=BLKS IZE=80
                                                                          00003100
//#
                                                                          00003200
//# INPUT DATA SET - EIS MASTER FILE
                                                                          00003300
                                                                          00003400
//EFIFMSTR DD DSNAME=&PROJECT..DATA.&MSTRFIL,
                                                                          00003500
11
               VOLUME=(PRIVATE.RETAIN).
                                                                          00003600
11
               DISP=(SHR, PASS)
                                                                          00003700
1/4
                                                                          03003800
//# INPUT DATA SET - EMISSION FACTORS TABLE
                                                                          00003900
                                                                          00004000
//EF1FTABL DD DSNAME=&PROJECT.. DATA. &EFTABLE.
                                                                          00004100
11
               VOLUME = ( PRIVATE . RETAIN ) .
                                                                          00004200
11
               DISP=(SHR.PASS)
                                                                          00004300
                                                                          00004400
//#
//* OUTPUT DATA SET - DISGNOSTIC MESSAGES
                                                                          00004500
//*
                                                                          00004600
//EFIFERR OD SYSOUT=EOUT
                                                                          00004700
//#
                                                                          03004800
//* DUTPUT DATA SET - EIS TRANSACTIONS
                                                                          00004900
//*
                                                                          00005000
//EFIFXOUT DD UNIT=&UNIT.
                                                                          00005100
11
               VOLUME=(PRIVATE, RETAIN, SER=&SERIAL),
                                                                          0005200
11
               DISP=( CDISP) .
                                                                          00005300
11
               SPACE= (&SPCUNIT, (&PKIMARY, &SECNDRY), RLSE),
                                                                          00005400
11
               DSNAME=&PRUJECT..DATA.&TRANS
                                                                          00005500
1/#
                                                                          00005600
```

EIS CATALOGED PROCEDURES


//* OUTPUT	DATA SETS - SYSTEM OPERATION	00005700
//*		00005800
//SYSPRINT	DU SYSUUT=EOUT	00005900
/ / *		0000000
//SYSOUT	DD SYSOUT=EOUT	00 00 61 00
//#		00 00 62 00
//SYSDBOUT	TUG3=TUG2Y2 DO	00006300
/ / *		00006400
//SYSDTERM	DD SYSOUT=&OUT	00 006 500
/ /		00006600
//SYSUDUMP	DD SYSOUT=&OUT	00006700
//* .	•	00006800

EISEFUPD Procedure

Figure 7.1.6-4 (cont.)

7.1.7 EISFUPDT - FILE MAINTENANCE

EISFUPDT is executed to perform file maintenance functions upon the EIS master file. There are two input files used by the file maintenance program. The first, defined by EISOLDMS, contains the EIS master file to be updated (if any). The second, defined by EISTRANS, contains the EIS file maintenance transactions. There are two output files used by the file maintenance program. The first, defined by EISMASTR, contains the updated or created EIS master file. The second, defined by EISERROR, contains diagnostic messages generated during the file maintenance process and a listing of the input file maintenance transactions.



EISFUPDT - Data Flow Figure 7.1.7-1

DD NAME	Description
EISTRANS	EIS transactions to update the master file
EISOLDMS	EIS master file to be updated
EISMASTR	New EIS master file
EISERROR	Print file for diagnostic messages
:	
1	

EISFUPDT - DDNAMES

Figure 7.1.7-2

Parameter	Default		
Name	Value	Description	
PROJECT	EIS	Highest level index of data set	
PROGRAM	FXFILMNT	EIS file maintenance program	
OLDMSTR	FTMSTRAA	Lowest level index of EIS master	
		file to be updated	
NEWMS TR	FTMSTRAB	Lowest level index of updated EIS	
		master file.	
UNIT	2314	Unit type upon which new file is to	
		reside	
SERIAL	ØØ9858	Volume serial of volume upon which	
		new file is to reside	
DISP	'New, Catlg,	Disposition of new file	
	Delete'		
SPCUNIT	TRK	Units in which space for the new	
		file is to be allocated	
PRIMARY	10	Number of units to be allocated for	
		the new file's primary allocation	
SECNDRY	5	Number of units to be allocated for	
		the new file's secondary allocation	
OUT	A	Sysout class of all print files.	

EISFUPDT - Substitutable Parameters

Figure 7.1.7-3

146

//*
//SYSDTERM DD SYSOUT=&OUT
//*
//SYSUDUMP DD SYSOUT=&OUT
//*


00005700 00005800 00005900 00006000 00006100

EISFUPDT Procedure

re 7.1.7-4 (cont.)

7.1.8 EISNACNV - NEDS AREA SOURCE TO EIS

EISNACNV is executed to convert NEDS area source records to EIS transactions. The input to the conversion program consists of a NEDS area source file and is defined by NEDSFILE. There are two output files used by the conversion program. The first, defined by EISATRAN, contains the EIS file maintenance transactions produced by the conversion program. The second, defined by EISAERRS, contains diagnostic messages generated during the conversion process.



EISNACNV - Data Flow Figure 7.1.8-1

DD NAME	Description
NEDSFILE	Data set containing NEDS area source records
EISATRAN	Data set to contain generated EIS transactions
EISAEERS	Print file for diagnostic messages
	·

EISNACNV - DDNAMES

Figure 7.1.8-2

Parameter Name	Default Value	Description
Name	value	Description
PROJECT	EIS	Highest level index of data set
		names (e.g., EIS.DATA.EFTABLE)
PROGRAM	CXASUMRY	Program to convert NEDS area source
		record to EIS transactions
NEDSFIL	NEDS	Lowest level index of data set
		containing NEDS records
EISOUT	В	Sysout class of EIS transactions
OUT	A	Sysout class of all print files
1		
}		

EISNACNV - Substitutable Parameters

Figure 7.1.8-3

HURLEY RF

WF4

06/30/74 00000100

00000200

ISNACNV


//#

//*

EISNACNV

7.1.9 EISNCONV - NEDS POINT SOURCE OUTPUT

EISNCONV is executed to produce NEDS point source data from EIS file records. The input to the program consists of an EIS file (either master or answer) and is defined by EISMASTR. There are two output files used by the program. The first, defined by NEDSFILE, contains the NEDS point source records produced by the program. The second, defined by EISPRINT, contains dianostic messages generated during the output process.



EISNCONV - Data Flow Figure 7.1.9-1

DD NAME	Description
EISMASTR	EIS master file
NEDSFILE	Data set to contain generated NEDS records
EISPRINT	Print file for diagnostic messages
	·

EISNCONV - DDNAMES

Figure 7.1.9-2


Default	
Value	Description
EIS	Highest level index of data set
	names (e.g., EIS.DATA.EFTABLE)
NXNEDSCV	Program to convert EIS point source
	file to NEDS point source records
FTMSTRAA	Lowest level index of EIS file to
	be converted
В	Sysout class of NEDS records
A	Sysout class of all print files
	EIS NXNEDSCV FTMSTRAA B

EISNCONV - Substitutable Parameters
Figure 7.1.9-3

			•			
//*	EISNCONV	HURLEY	RF	WF4	06/30/74	00000100
7/#						0000200
//EISNCONV PROC	PROJECT=E1S.					00000300
//	PROGRAM=NXNEDSCV.					00000400
11	MSTRFIL=FTMSTRAA.					00000500
11	NEDSOUT=B.					00000600
11	OUT=A					00000700
//*						00000800
//CUNVERT EXEC	PGM=&PROGRAM.					00000900
//	REGION=20K.					00001000
"	TIME=(1.0)					00001100
//*						00001200
	S POINT SOURCE FILE TO NE	DS FOR	MAT			00001300
//*						00001400
	DSNAME=&PROJECT LUAU.					00001500
//	VOLUME = (PRIVATE . RETAIN)					00001600
<i>;;</i>	DISP=(SHR.PASS)	•				00001700
	DSNAME=SYS1.ANS.COBSUBR					00001800
//	DISP=(SHR.PASS)	,				00001900
//*	D13F-13 R1F#337					00002000
	SET - EIS MASTER FILE					00002100
//# INFOI DATA	SET - ETS MASTER FIEL					0002200
* *	DSNAME=&PRUJECT DATA . &M	4CT0E11				00002300
			•			00002300
//	VOLUME = (PRIVATE, RETAIN),	,				
//	DISP=(SHR.PASS)					00 00 2 5 0 0
//*	A CEY NEOF FILE					00002800
	A SET - NEDS FILE					03002700
// *	EVERUT-CHESCOUT					00002900
	SYSOUT=& NEDSOUT					
//#	A CET - DIACNOSTIC MESSA					00003000
_	A SET - DIAGNOSTIC MESSAC	,E2				0003100
//*						00003200
	1003=TU02Y2					00003300
//*						00003400
	A SETS - SYSTEM OPERATION	4				00003500
/ /*						00003600
	SYSOUT=&OUT					00003700
//*						00003800
//SYSOUT DD	SYSOUT=&OUT					00003900
//#						00004000
//SYS DBOUT DD	SYSUUT=&OUT					00004100
//#						0004200
//SYSDTERM DD	SYSOUT=&OUT					00004300
//*						0004400
//SYSUDUMP DD	SYSOUT=&OUT					00004500
//*						00004600

7.1.10 EISPREPT - FILE LIST OUTPUT

EISPREPT is executed to produce a detailed listing of an EIS file. The input to the file list program consists of an EIS file (either master or answer) and is defined by EISMASTR. The output from the file list program consists of a detailed listing of each record in the file and is defined by EISFILE.



EISPREPT - Data Flow Figure 7.1.10-1

DD NAME	Description
EISMASTR	EIS file to be listed
EISFILE	Print file for EIS file listing

EISPREPT - DDNAMES

Figure 7.1.10-2

Parameter Name	Default Value	Description
PROJECT	EIS	Highest level index of data set
		names (e.g., EIS.DATA.EFTABLE)
PROGRAM	PXFILPRT	Program to format and list EIS file
MSTRFIL	FTMSTRAA	Lowest level index of EIS file
		(master or answer) to be listed
OUT	A	Sysout class of all print files
		·

EISPREPT - Substitutable Parameters

Figure 7.1.10-3

163

EISPREPT Procedure

Figure 7.1.10-4

EIS CATALOGED PROCEDURES

//#	ELSPREPT	HURLEY	ge .	HF4 0	6/30/74	00000100
1/#			•••			0000000
	OC PROJECT=EIS.					00000300
11	PROGRAM=PXFILPKT.					00000420
"	MSTRFIL=FTMSTRAA.					00000500
"	QUT = A					0000600
//*						00000700
//REPORT EXE	C PGM=&PROGRAM.					00000000
11	TIME=(1,0).					00000900
77	REGION=24K					00001000
/ /#						001100
//¥ FORMAT EI	S MASTER FILE					00001200
/ /*						0001300
//STEPLIB U	D DSNAME=&PROJECT L	.OAD.				00001400
//	VOLUME=(PRIVATE.RE	TAIN).				00001500
11	DISP=(SHR.PASS)					00001600
	D DSNAME=SYS1.ANS.CO	BSUBR.				0001700
//	DISP={SHR.PASS}					00001800
/ /*						00001900
	A SET - EIS MASTER F	ILE				00002000
//*	•					00002100
	D DSNAME=&PROJECTD		,			00002200
//	VOLUME=(PRIVATE . KE	TAINI				00 00 23 00
//	DISP=(SHR.PASS)					00002400
//*				_		00002500
	TA SET - FORMATTED L	131 ING OF EL	MASIER FIL	t.		03002600
//#						00 002 700
	D SYSOUT=&OUT					00002800
//*	TA	0471711				00002900
	TA SETS - SYSTEM OPE	KATION				00003000
//* //SYSPRINT D	D SYSOUT=&OUT					00003200
//*	0 313001=6001					00003200
• •	D SYSOUT=&OUT					03003300
//313001 U	0 313001-6001					03003400
• •	D SYSOUT=60UT					00003600
//#	J 313001-6001					00003700
	D SYSOUT=&OUT					00003800
//*	5.5001-4001					00003900
• •	D SYSOUT=&OUT					00004000
//*	5 5.5561-4001					03004100

7.1.11 EISRETVR - RETRIEVAL

EISRETVR is executed to retrieve an answer file from the EIS master file.


The procedure consists of four separate steps.

The first step, the retrieval language processor, generates a COBOL program to perform the actual retrieval of the answer file. The input to the language processor consists of retrieval query cards specifying the qualifications of the answer file to be retrieved and is defined by CINPUT. There are two output data sets used by the language processor. The first, defined by COUTPUT, contains the COBOL source code produced by the language processor. The second, defined by CERROR, contains diagnostic messages generated during the language processing process.

The second step, the COBOL compiler, compiles the source code produced by the language processor and produces an object module which is passed to the third step, the linkage editor. The linkage editor combines the retriever object code with COBOL subroutines and produces an executable load module of the retriever program.

The fourth step, the retriever, processes the EIS master file and produces the answer file. The input to the retriever consists of the EIS master file and is defined by RINPUT. There are two output files used by the retriever. The first, defined by ROUTPUT, contains the answer

file produced by the retriever. The second, defined by RERROR, contains diagnostic messages generated during the retrieval process.



EISRETVR - Data Flow

Figure 7.1.11-1

DD NAME	Description
CINPUT	Retrieval query cards
COUTPUT	COBOL retrieval program source code
CERROR	Print file for diagnostic messages
RINPUT	EIS master file from which answer file is to be retrieved
RERROR	Print file for diagnostic messages
ROUTPUT	Answer file retrieved from EIS master file.

EISRETVR - DDNAMES

Figure 7.1.11-2

Parameter	Default	Paradata
Name	Value	Description
PROJECT	EIS	Highest level index of data set
		names (e.g., EIS.DATA.EFTABLE)
PROGRAM	RXCMAIN1	Program to generate retrieval
		program
MSTRFIL	FTMSTRAA	Lowest level index of EIS master file
		from which answer file is to be
		retrieved
ANSWRFL	ANSWER	Lowest level index of EIS answer file
UNIT	2314	Unit type upon which answer file is
		to reside
SERIAL	ØØ9858	Volume serial of volume upon which
		answer file is to reside
DISP	'NEW, PASS,	Disposition of answer file
	DELETE '	
SPCUNIT	TRK	Units in which space for the answer
		file is to be allocated
PRIMARY	10	Number of units to be allocated for
		the answer file's primary allocation
SECNDRY	5	Number of units to be allocated for
		the answer file's secondary allocation
TEMP	SYSOUT	Unit type for temporary work space
SORTSPC	5Ø	Number of tracks to be allocated for
		sort work space
OUT	A	Sysout class of all print files

EISRETVT - Substitutable Parameters Figure 7.1.11-3

EISRETVR

Procedure

169

```
//#
               EISRETVR
                                        HURLEY RF
                                                           WF4
                                                                 06/30/74 00000100
//*
                                                                          00000200
//EISRETVR PROC PROJECT=EIS.
                                                                          00000300
11
               PROGRAM=RXCMAIN1.
                                                                          00000400
11
               TEMP=SYSOUT.
                                                                          00000500
11
               SURTSPC=50.
                                                                           00000600
11
                                                                          00000700
               QUT=A.
11
               MSTRFIL=FIMSTRAA.
                                                                          00000800
                                                                          00000900
11
               ANSWRFL = ANSWER.
11
               UNIT=2314.
                                                                          00001000
11.
                                                                          00001100
               SERIAL=009858.
11
               DISP= * NEW. PASS. DELETE* .
                                                                          00001200
11
                                                                          00001300
               SPCUNIT=TRK.
11
               PRIMARY=10.
                                                                          00001400
               SECNDRY=5
                                                                          00001500
11
//#
                                                                          00001600
//CUMPILE EXEC PGM=&PROGRAM.
                                                                          00001700
                                                                          00001800
11
               REGION=26K.
11
               TIME=(1.0)
                                                                          00001900
//#
                                                                          00002000
//* PRODUCE EIS RETRIEVAL PROGRAM
                                                                          0002100
//#
                                                                          0002200
//STEPLIB
            DD DSNAME=&PROJECT .. LOAD.
                                                                          00002300
               VOLUME = ( PRIVATE , RETAIN) .
                                                                          02002400
11
11
               DISP=(SHR.PASS)
                                                                          00002500
11
            DD DSNAME=SYS1.ANS.CUBSUBR.
                                                                          00002600
11
                                                                          00002700
               DISP=(SHR.PASS)
//#
                                                                           0002800
//* INPUT DATA SET - RETRIEVAL REQUEST CARDS
                                                                           00002900
//#
                                                                          00003000
//CINPUT
            DD DDNAME= INPUT,
                                                                           00003100
11
               DCB=BLKSIZE=80
                                                                           00003200
//#
                                                                           00003300
//# UUTPUT DATA SET - COBUL RETRIEVAL PROGRAM SOURCE CODE
                                                                           00003400
//*
                                                                           00003500
//COUTPUT
            DD UNIT= & TEMP .
                                                                           00003600
11
               DISP=(NEW. PASS).
                                                                           00003700
11
               SPACE=(TRK.(5.2).KLSE).
                                                                           00003800
11
               DSNAME=&&PROGRAM
                                                                           00003900
1/#
                                                                           00004000
//* OUTPUT DATA SET - DIAGNOSTIC MESSAGES
                                                                           00004100
                                                                           00004200
1/#
//CERRUR
            DD SYSOUT=&OUT
                                                                           00004300
                                                                           03004400
//*
//# OUTPUT DATA SETS - SYSTEM OPERATION
                                                                           00004500
                                                                           00004600
1/#
                                                                           00004700
//SYSPRINT DD SYSOUT=&OUT
                                                                           00004800
//#
//SYSOUT
            DD SYSOUT=&OUT
                                                                           00004900
//#
                                                                           00005000
//SYSDBOUT DD SYSOUT=&OUT
                                                                           00005100
                                                                           00005200
1/#
                                                                           0005300
//SYSDIERM DD SYSOUT=&OUT
                                                                           0005400
//#
//SYSUDUMP DD SYSOUT=&OUT
                                                                           00005500
                                                                           00005600
1/#
```

Figure 7.1.11-4 (cc

(cont.)

```
//COBOL
          EXEC PGM= [KFCBL00.
                                                                          00005700
11
               PARM= "SIZE = 94K . BUF = 10K . NOSEQ . NOSOURCE . FLAGE . .
                                                                           00005800
11
               REGION=100K.
                                                                          00005900
11
               TIME=(2.0)
                                                                          00006000
//#
                                                                          00006100
//# COMPILE RETRIEVAL PROGRAM
                                                                          00006200
//#
                                                                          00006300
//STEPLIB DD DSNAME=SYS1.ANS.COBLIB.
                                                                          00006400
11
               DISP=(SHR.PASS)
                                                                          00006500
//#
                                                                          02006600
//* INPUT DATA SET - SOURCE LIBRARY
                                                                          00006700
//#
                                                                          0006800
1/SYSLIB
            DD DSNAME=&PROJECT .. SOURCE.
                                                                          00006900
11
               VOLUME=(PRIVATE.RETAIN).
                                                                          00007000
11
               DISP=(SHR.PASS)
                                                                          00007100
//#
                                                                          00007200
//# INPUT DATA SET - COBOL RETRIEVAL PROGRAM SOURCE CODE
                                                                           00007300
//#
                                                                           00007400
//SYSIN
            DD DSNAME=&&PRDGRAM.
                                                                           00007500
11
               DISP=(CLD. DELETE)
                                                                          03007600
//*
                                                                          00007700
//# OUTPUT DATA SET - DIAGNOSTIC MESSAGES
                                                                          00007800
                                                                          00007900
//SYSPRINT DD SYSOUT=&UUT
                                                                          0008000
                                                                          0008100
//#
//# OUTPUT DATA SET - COBOL RETRIEVAL PROGRAM OBJECT CODE
                                                                          0008200
1/4
                                                                          0008300
//SYSLIN
            DD UNIT=&TEMP.
                                                                           00008400
                                                                          0008500
11
               DISP=(NEW.PASS).
11
               SPACE=(TRK.(5,2),RLSE).
                                                                          00008600
                                                                           00008700
11
               DSNAME=ECOBJMOD
//#
                                                                          0008800
                                                                          00008900
//* UTILITY DATA SETS
1/4
                                                                           0000000
//SYSUT1
            DD UNIT=&TEMP.
                                                                           00009100
11
               SPACE=(TRK . (50.100))
                                                                           0009200
                                                                           00009300
//#
//SYSUT2
            DD UNIT=(&TEMP.SEP=SYSUT1).
                                                                           03009400
                                                                           00009500
11
               SPACE=(TRK, (50, 100))
1/#
                                                                           00009600
//SYSUT3
            DD UNIT=(&TEMP.SEP=(SYSUT1.SYSUT2)).
                                                                           00009700
11
                                                                           00009800
               SPACE=(TRK, (50, 100))
//#
                                                                           00009900
//SYSUT4
            OD UNIT=(&TEMP.SEP=(SYSUT1.SYSUT2.SYSUT3)).
                                                                           00010000
                                                                           00010100
11
                SPACE=(TRK+(50,100))
//*
                                                                           002010200
//LKED
          EXEC PGM= IEWL.
                                                                           00010300
                                                                           00010400
11
               PARM="LIST.LET.XREF".
11
                REGION=100K.
                                                                           00010500
                                                                           00010600
11
               T1ME=(1.0)
                                                                           00010700
//*
//# LINK-EDIT RETRIEVAL
                                                                           00010800
//#
                                                                           00010900
                                                                           00011000
//#
//# INPUT DATA SET - AUTO-CALL LIBRARY
                                                                           00011100
1/#
                                                                           00011200
```

Figure 7.1.11-4 (cont.)

```
'//SYSLIB
            DD DSNAME=&PRUJECT .. LOAD.
                                                                        00011300
11
               VOLUME=(PRIVATE, RETAIN),
                                                                        00011400
11
               DISP=(SHR.PASS)
                                                                        00011500
11
            DD DSNAME=SYS1.ANS.COBSUBR.
                                                                        00011600
11
               VOLUME = ( PRIVATE , RETAIN) ,
                                                                        00011700
11
               DISP=(SHR, PASS)
                                                                        00011800
1/4
                                                                        00011900
//* INPUT DATA SET - COBUL RETRIEVAL PRUGRAM OBJECT CODE
                                                                        00012000
//#
                                                                        0012100
//SYSLIN
            OD DSNAME=&&USJMOD.
                                                                        00012200
11
               DISP=(ULD.DELETE)
                                                                        00012300
11
            DD DDNAME=INPUT.
                                                                        00012400
11
               DCB=BLKSIZE=80
                                                                        00012500
1/#
                                                                        00012600
//# OUTPUT DATA SET - DIAGNUSTIC MESSAGES
                                                                        00012700
                                                                        00012800
//SYSPRINT DD SYSOUT=&OUT
                                                                        00012900
                                                                        00013000
//# OUTPUT DATA SET - COBOL RETRIEVAL PROGRAM LOAD MODULE
                                                                        00013100
//#
                                                                        00013200
//SYSLMGD DD UNIT=ETEMP.
                                                                        00013300
11
               DISP=(MOD.PASS).
                                                                        00013400
11
               SPACE=(TRK.(10.5.1)).
                                                                        03013500
11
               DSNAME=&&LUADMUD(RETRIEVE)
                                                                        00013600
//*
                                                                        00013700
//* UTILITY DATA SET
                                                                        00013800
//#
                                                                        00013900
            DD UNIT=&TEMP.
//SYSUT1
                                                                        00014000
11
               SPACE=(TRK . (10.5))
                                                                        00014100
//*
                                                                        00014200
//RETRIEVE EXEC PGM=+.LKED.SYSLMOD.
                                                                        00014300
11
               REGIUN=40K.
                                                                        00014400
11
               TIME=(1.0)
                                                                        00014500
/ / *
                                                                        00014600
//* RETRIEVE RECORDS FROM EIS MASTER FILE
                                                                        00014700
1/#
                                                                        00014800
//STEPLIB DD DSNAME=&PRUJECT..LOAD.
                                                                        00014900
                                                                        00015000
11
               VOLUME=(PRIVATE.RETAIN),
11
               DISP=(SHR, PASS)
                                                                        00015100
11
                                                                        00015200
            DD DSNAME=SYS1.ANS.COBSUBR.
11
               DISP=(SHR, PASS)
                                                                        00015300
                                                                        00015400
//#
//* INPUT DATA SET - ELS MASTER FILE
                                                                        20015500
                                                                        00015600
//RINPUT
            DD DSNAME=&PROJECT..DATA.&MSTRFIL.
                                                                        00015700
                                                                        00015800
11
              VOLUME=(PRIVATE.RETAIN).
11
               DISP=(SHR, PASS)
                                                                        00015900
                                                                        00016000
//#
//# INPUT DATA SET - SORT PROGRAM LIBRARY
                                                                        00016100
                                                                        00016200
                                                                        00016300
//SURTLIB DD DSNAME=SYS1.SURTLIB,
11
               VOLUME=(PRIVATE.RETAIN).
                                                                        00016400
                                                                        00016500
11
               DISP=(SHR.PASS)
                                                                        00016600
//#
//* OUTPUT DATA SET - DIAGNUSTIC MESSAGES
                                                                        00016700
//#
                                                                        00861000
```

EISRETVR Procedure


```
//RERROR
           TUG3=TUGSYZ DD
                                                                         00016900
//#
                                                                         00017000
//* OUTPUT DATA SET - RECORDS RETRIEVED FROM EIS MASTER FILE
                                                                         00017100
//*.
                                                                         00017200
//ROUTPUT
           DD UNIT-EUNIT.
                                                                         00017300
11
               VOLUME={PRIVATE . RETAIN . SER = & SERIAL ] .
                                                                         00017400
11
               OISP=(EDISP).
                                                                         00017500
11
               SPACE=(&SPCUNIT,(&PRIMARY, &SECNDRY), RLSE),
                                                                         00017600
11
               DSNAME=&PROJECT..DATA. &ANSWRFL
                                                                         00017700
//*
                                                                         00017800
//* UTILITY DATA SETS
                                                                         00017900
                                                                         00018000
//#
//SURTWKO1 DD UNIT=&TEMP.
                                                                         00018100
               SPACE=(TRK .(&SORTSPC)..CONTIG)
                                                                         00018200
11
//#
                                                                         00018300
//SORTWKO2 DD UNIT=(&TEMP.SEP=SORTWKO1).
                                                                         00018400
11
               SPACE=(TRK.(&SORTSPC)..CUNTIG)
                                                                         00018500
//#
                                                                         00018600
//SORTWKO3 DD UNIT=(&TEMP.SEP=(SURTWKO1.SORTWKO2)),
                                                                         00018700
               SPACE=(TRK,(&SURTSPC),,CONTIG)
                                                                         00018800
11
//#
                                                                         00018900
//* DUTPUT DATA SETS - SYSTEM UPERATION
                                                                         00019000
//#
                                                                         00019100
//SYSPRINT DD SYSUUT=&OUT
                                                                         00019200
                                                                         00019300
//*
//SYSOUT
            DD SYSOUT=&OUT
                                                                         00019400
                                                                         00019500
1/#
//SYSCHOUT DD SYSOUT=&OUT
                                                                         00019600
                                                                         00019700
//#
//SYSDTERM DD SYSOUT=&OUT
                                                                         00019800
110
                                                                         00019900
//SYSUDUMP DD SYSOUT=&OUT
                                                                         0002000
//#
                                                                         001020100
```

7.1.12 EISSREPT - SUMMARY REPORT OUTPUT

EISSREPT is executed to produce a summary report of an EIS file (either master or answer). The procedure consists of three separate steps.

The first step, the COBOL compiler, compiles the skeleton summary program with user supplied control cards. The input to the COBOL compiler consists of COBOL statements controlling the breaks in the report to be produced. The output from the COBOL compiler consists of an object module which is passed to the second step, the linkage editor. The linkage editor combines the summary program object code with COBOL subroutines and produces an executable load module of the summary report program.

The third step, the summary report program, generates the summary of the EIS file. There are two input files used by the summary program. The first, defined by SUMCARDS, contains the control cards for the titling of the report. The second, defined by EISFILE, contains the EIS file to be summarized. There are two output files used by the summary program. The first, defined by CARDLOG, contains the control card log. The second, defined by SUMFILE, contains the summary report of the EIS file.



EISSREPT - Data Flow

Figure 7.1.1241

DD NAME	Description
SUMCARDS	Control cards for summary report
EISFILE	EIS file to be summarized
CARDLOG	Print file for control card log
SUMFILE	Print file for summary report
	·
	·

EISSREPT - DDNAMES

Figure 7.1.12-2

Parameter	Default	
Name	Value	Description
PROJECT	EIS	Highest level index of data set
		names (e.g., EIS.DATA.EFTABLE)
MEMBER	BDSUMARY	Name of first member of summary
		program
M2	BDFILSEC	Name of second member
мз	BDWORK77	Name of third member
м4	BDWORKØ1	Name of fourth member
м5	BDRPTSEC	Name of fifth member
м6	BPSUMARY	Name of sixth member
MSTRFIL	FTMSTRAA	Lowest level index of EIS file to
		be summarized
TEMP	SYSOUT	Unit type to be used for temporary
		workspace
OUT	A	Sysout class for all print files

EISSREPT - Substitutable Parameters
Figure 7.1.12-3

Figure

7.1.12-4

EISSREPT

Procedure

1/# EISSREPT HURLEY RF WF4 06/30/74 00000100 00000200 1/# 00000300 //ESISREPT PROC PROJECT=EIS. 03000400 11 TEMP=SYSOUT. 00000500 11 MSTRFIL=FTMSTRAA. MEMBER=BDSUMARY. 0000000 11 M2=BDFILSEC, 00000700 11 11 M3=BDWDRK77. 00000800 00000900 M4=BDWORKO1. 11 11 M5=BDRPTSEC. 00001000 M6=8PSUMARY. 00001100 11 11 OUT=A 00001200 00001300 114 //COMPILE EXEC PGM=IKFCBLOO. 00001400 PARM= SIZE=94K, BUF=10K, NOSEQ, NOSOURCE , 00001500 11 11 REGION=100K. 0001600 11 TIME=(2.0) 20001700 1/* 0001800 00001900 //* COMPILE EIS SUMMARY PROGRAM 00002000 1/# //STEPLIB DD DSNAME=SYS1.ANS.COBLIB. 00002100 DISP=(SHR, PASS) 00002200 11 00002300 1/# //* INPUT DATA SET - SOURCE LIBRARY 00002400 00002500 1/# DD DSNAME=&PROJECT .. SUURCE. //SYSLIB 00002600 00002700 11 VOLUME=(PRIVATE.RETAIN); 00002800 11 DISP=(SHR.PASS) 00002900 //# //# INPUT DATA SET - COBOL SUMMARY PROGRAM SOURCE CODE 00003000 02003100 1/4 //SYSIN DD DSNAME=& PROJECT .. SOURCE (&MEMBER) + 00003200 00003300 11 VOLUME={PRIVATE.KETAIN}. 02003400 11 DISP=(SHR.PASS) 1/4 00003500 DD DSNAME=&PROJECT .. SOURCE(&M2). 00003600 11 VOLUME=(PRIVATE.RETAIN). 0003700 11 00003800 11 DISP=(SHR.PASS) 00003900 //# DD DSNAME=&PROJECT .. SOURCE(&M3). 00004000 11 00004100 11 VOLUME=(PRIVATE.RETAIN). DISP=(SHR, PASS) 02004200 11 //# 00004300 00004400 11 DD DSNAME=&PRUJECT .. SOURCE(&M4). 00004500 11 VOLUME={PRIVATE . RETAIN). DISP=(SHR, PASS) 00004600 11 00004700 //# 00004800 DD DSNAME=&PRUJECT .. SUURCE(&M5). 11 00004900 11 VOLUME=(PRIVATE.RETAIN). 00005000 DISP=(SHR.PASS) 11 00005100 1/# 00005200 DD DSNAME=&PRUJECT .. SOURCE(&M6). 11 VOLUME=(PRIVATE.RETAIN). 00005300 11 00005400 DISP=(SHR.PASS) 11 00005500 //# 00005600 11 DD DDNAME = INPUT.

EISSREPT Procedure

7

1.12 - 4

11 DCB=BLKS IZE=80 0005700 1/4 00005800 //* DUTPUT DATA SET - DIAGNUSTIC MESSAGES 00005900 //# 00006000 //SYSPRINT DD SYSOUT=&OUT 00006100 00006200 //# OUTPUT DATA SET - COBOL SUMMARY PROGRAM OBJECT CODE 00006300 //# 00006400 //SYSLIN DD UNIT=&TEMP. 00006500 11 DISP=(NEW.PASS). 0006600 11 SPACE=(TRK, (5,2), RLSE), 00006700 11 GOMLBO33=3MANZO 00006800 //* 00006900 //# UTILITY DATA SETS 00007000 00007100 //* //SYSUT1 DD UNIT=&TEMP. 00007200 11 SPACE=(TRK . (50.100)) 00007300 //# 00007400 //SYSUT2 DD UNIT=(&TEMP.SEP=SYSUT1), 03007500 SPACE=(TRK,(50,100)) 11 00007600 //# 00007700 //SYSUT3 DD UNIT=(&TEMP.SEP=(SYSUT1.SYSUT2)). 0007800 11 SPACE= (TRK . (50, 100)) 00007900 //* 00008000 //SYSUT4 DD UNIT=(&TEMP.SEP=(SYSUT1.SYSUT2.SYSUT3)). 00.008100 SPACE=(TRK, (50, 100)) 11 0008200 //# 0008300 EXEC PGM=IEWL. //LKED 00008400 PARM='LIST,LET, XREF', 00008500 REGION=100K. 00008600 11 11 TIME=(1.0) 0008700 1/# 00008800 //# LINK-EDIT SUMMARY PROGRAM 00008900 1/# 0009000 //# 00009100 //* INPUT DATA SET - AUTU-CALL LIBRARY 00009200 //* 00009300 //SYSLIB DD DSNAME=&PROJECT .. LOAD. 00.009400 00009500 11 VOLUME=(PRIVATE, RETAIN), 11 DISP=(SHR.PASS) 00009600 11 00009700 DD DSNAME=SYS1.ANS.COBSUBR. 11 VULUME=(PRIVATE.RETAIN). 00009800 11 DISP=(SHR.PASS) 00009900 00010000 //# INPUT DATA SET - COBOL SUMMARY PROGRAM OBJECT CODE 00010100 00010200 //# 00010300 //SYSLIN . COMLEGS 3=3MANZ CC 00010400 DISP=(OLD.DELETE) 11 00010500 11 DD DDNAME=INPUT. 02010600 11 DCB=BLKSIZE=80 00010700 //* OUTPUT DATA SET - DIAGNUSTIC MESSAGES 00010800 00010900 //# //SYSPRINT OD SYSOUT=&OUT 00011000 114 00011100 00011200 //* DUTPUT DATA SET - COBUL SUMMARY PROGRAM LOAD MODULE

EISSREPT Procedure Figure 7.1.12-4 (con

110 00011300 //SYSLMOD DD UNIT=&TEMP. 00011400 11 DISP=(MOD, PASS). 00011500 11 SPACE=(TRK,(10,5,1)). 00011600 11 DSNAME=&&LUADMUD(SUMMARY) 00011700 1/4 00011800 //* UTILITY DATA SET 00011900 //# 00012000 //SYSUT1 DD UNIT=&TEMP. 00012100 SPACE=(TRK,(10,5)) 00012200 11 1/4 00012300 //SUMMARY EXEC PGM= +. LKED. SYSLMOD. 00012400 11 REGION=30K. 00012500 11 TIME=(1.0) 00012600 00012700 114 //* PRODUCE EIS SUMMARY REPORT 00012800 110 00012900 //STEPLIB DD DSNAME=GPROJECT..LOAD. 00013000 VOLUME=(PRIVATE, RETAIN). 00013100 11 DISP=(SHR.PASS) 00013200 11 DD DSNAME=SYS1.ANS.CURSURR. 00013300 11 DISP=(SHR.PASS) 00013400 00013500 1/4 //# INPUT DATA SET - CONTROL CARDS 00013600 00013700 //SUMCARDS DD DDNAME=INPUT. 00013800 11 DCB=BLKSIZE=80 00013900 1/# 00014000 //* INPUT DATA SET - EIS MASTER FILE 00014100 1/# 00014200 //EISFILE DD DSNAME=&PRUJECT..DATA.&MSTRFIL. 00014300 VOLUME=(PRIVATE.RETAIN). 00014400 11 11 DISP=(SHR.PASS) 00014500 1/4 00014600 //* OUTPUT DATA SET - CONTROL CARD LOG 00014700 00014800 //# //CARDLOG DD SYSOUT=&OUT 00014900 00015000 //# //* UUTPUT DATA SET - SUMMARY REPORT 00015100 00015200 1/# //SUMFILE DD SYSOUT=&OUT 00015300 00015400 1/* //# OUTPUT DATA SETS - SYSTEM OPERATION 00015500 00015600 //# 00015700 //SYSPRINT DD SYSOUT=&OUT 00015800 //# //SYSOUT DD SYSOUT=EOUT 00015900 00016000 1/# 00016100 //SYSDBOUT DD SYSOUT=&OUT //# 00016200 00016300 //SYSDTERM DD SYSOUT=&OUT 00016400 //* 00016500 //SYSUDUMP DD SYSOUT=&OUT //* 00016600

7.2 USE OF CATALOGED PROCEDURES

The following section gives an example of how to use the cataloged procedures. The sample run described in this section creates an EIS master file, retrieves an answer file from it, lists the answer file and produces a summary report. Figure 7.2-1 illustrates the job control cards required to perform this run.

The first step creates an EIS master file named EIS.DATA.FTMSTRAA. Since the file is being newly created rather than updated, the DDNAME EISOLDMS is nullified with a DD DUMMY statement to indicate that no old master file exists. The file maintenance transactions must consist entirely of "Add" transactions. After the file has been created, it is cataloged by the JCL so that it may be referred to by succeeding steps without supplying specific location information.

The second step involves the retrieval language processor to read the queries and generate a retriever program. The program will be compiled with the parameters specified on the EXEC card rather than those in the procedure. An answer file named EIS.DATA.ANSWER will be produced and passed to later steps. It may be referred to by succeeding steps as if it has been cataloged. However, it will be deleted at the end of the job.

Step three invokes the file list program to list the answer file.

The final step merges the COBOL break control statements with the skeleton summary report program and compiles it. Again the parameters used during compilation will be overridden by the EXEC statement. The control cards defined by SUMMARY.INPUT will control the titling of the summary report.

```
//STEP1 EXEC EISFUPDT,
//
           NEWMSTR=FTMSTRAA
//UPDATE.EISOLDMS DD DUMMY
//UPDATE.INPUT DD *
      (EIS file maintenance transactions)
/*
//STEP2 EXEC EISRETVR
//COMPILE.INPUT DD *
      (EIS retrieval queries)
/*
//STEP3 EXEC EISPREPT
            MSTRFIL=ANSWER
//STEP4 EXEC EISSREPT,
//
            MSTRFIL=ANSWER
//COMPILE.INPUT DD *
      (COBOL break control statements)
/*
//SUMMARY.INPUT DD *
      (EIS summary report control cards)
/*
```

Sample EIS Job Stream

Figure 7.2-1

APPENDIX

This appendix presents sample system runs. In the samples the transactions, files, and tables are represented as residing on disk, tape and card and are shown changing media during and between runs. This is not a system requirement but is mearly to indicate the flexibility of external data storage. The following is not an exhaustive list of possible system program combinations but is a sample of possible uses.

Figure A-1 shows a system start up run. There are no existing files for the Emission Factor Table, or the Master File. The first step is to create an Emission Factor Table using program EXTBGN. The table can then be used to insert the new Emission Factors into EIS transactions. The NEDS Point Source Transactions are run through program CXNEDSCV to convert them to the EIS input transaction format. The NEDS transaction cards are put into a hold file.

The new EIS transactions can now be used as input to program EXEFIX which will use the Emission Factor Table to insert the emission factors into the transactions. These updated EIS transactions can then be used to create a master file using program FXFILMNT. Notice that there is no old master file being used in this run.

Figure A-2 shows the conversion of NEDS Area Source Transactions into EIS transactions using program CXASUMRY. The EIS transactions are then run through program EXEFIX. In this run, since the Emission Factor Table already exists, we use it to insert the emission factors into the EIS transactions.

The new transactions are now used to update the existing Master File using FXFILMNT. The old master file should be kept until the next update has been run. This will provide a backup file in case anything happens to the current master file. At this point the master file may be listed using program PXFILPRT. The formatted listing provides a further backup for the file. The entire file should be listed periodically to provide current file status checks.

Figure A-3 shows the retrieval program (RXCAMAIN1) being used to select the Area Source records from the master file. The File Print Program PXFILPRT is used to print a formatted listing of the Answer File. The program AXSNEDS used the Answer File and produces the NEDS Area Source Cards. The Area Source cards may be listed using program HXANREPT which produces a formatted list of the NEDS formats.

Figure A-4 shows the retrieval program RXCMAIN1 being used to select the Point Source records from the master file. The answer file from this retrieval is then listed using program PXFILPRT. The answer set is then used as input to program NXNEDSCV which converts it to NEDS Point Source Cards. The NEDS cards can then be used to file the quarterly NEDS report.

Figure A-5 shows the retrieval program RXCMAIN1 being used to select a set of data based on the requirements of the Request Cards. A formatted detail listing of the answer set is produced by program PXFILPRT. The information in the answer set is summarized by program EISSREPT to produce the EIS Summary Report.

Figures A-6 through A-8 are the EIS card input forms for point source data.




Figure A-1




Figure A-2




Figure A-3




Figure A-4




Figure A-5

12	
-	
00	
F	
7	
(D	
1	
T	
6	

Sta			Con	unty		١.	AGCF			Plan	t ID			Date	of Re	ecord	1
Эu	rie		,000	anty			MUC.	•		Nun	nber		Ye	ar		Day	
1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18

EMISSION INVENTORY SUBSYSTEM (EIS) COMPREHENSIVE DATA HANDLING SYSTEM (CDHS)

PLANT IDENTIFICATION (Segment 0) Input Form

	Conti	rol on	1	Loca	al troi							Ut	ser I	Plar	nt IC	0								(City				TM one	000				Co	onta	ct I	Pers	ona	ı										,					T	elep	hone									P	rinci	pal	Prod	duct					S	C 4	A	
19	20	21	1 2	22	23	24	25	:	26	27	2	8	29	3	0	31	33	2	33	34	3	5	36	37	30	8 :	39	40	41	4	2	43	44	4	5	46	47	48	49	5	0 !	51	57	53	5	4 !	55	56	57	58	59	6	0 6	1	62	63	64	65	5 6	6 6	57	68	69	70	7	1 7	2	73	74	75	76	5 7	77	78	79	80	,
		+	T	-			-	+			1			1			•	_			•	1							•		1														•	•						•	•	•				•	•	•	1			•	•								T	0	1		

															1	sta	blis	hme	ent	Nam	ne a	nd A	Addr	ess																																				Der G	ć .		,	Prop	erty	Area				5 + GE + 1	C	A 07 . 0	
19	20	21	2	2	23	24	2	5 2	26	27	28	1 2	9	30	31	3	12	33	34	4 3	35	36	37	38	3	19	40	41	42	43	3 4	4	45	46	47	48	3 4	19	50	51	5	2 5	3 9	54	55	56	57	58	59	60	0 6	1 6	12 (3 (64	65	66	67	68	69	70	71	72	7	3 7	4 7	75 7	76	77	78	79	80	1
			1					_	_		_		_		_	_	_	_	_	_	_		_	_		_	_			_	_	_	_		_	_	_	_	_		_	_	_	_	_		_	_	_	_	_		_	_	_	_		_	_				_					\perp	\Box	0	2	L	

										Es	table	shme	nt M	Aailın	g Ad	iress																																							c .	A
1	9 20 21	22	23	24	25 :	26 :	7 .	28	29 3	31 .	32 .	33	34 .	35	36 .	37	38	39	40 .	41	42 .	43	44 .	45 .	46 .	47 .	48	49	50	51	52 5	3 5	4 5	5 54	6 5	7 54	8 59	. 60	. 61	62	. 63	64	65 .	66	67 6	. 6	9 :	70 .	71 . 7	 73 7	4 75	76	77	78	79	80

State County AQCR			
	Number	Year	Day
1 2 3 4 5 6 7 8 9	10 11 12 13	14 - 15	16 17 18

EMISSION INVENTORY SUBSYSTEM (EIS) COMPREHENSIVE DATA HANDLING SYSTEM (CDHS)

POINT SOURCE (Segment 1) Input Form

Name of Person Completing Form	
Data	

Seg ID	. 1	NEDS		nt ID	ser	-		SIC			11	PP			Horu		- 1	f Coo		ates ertica	al .		D	eq	Latitu		Sec		Long	gitude	Min	1	Sec		Dec	1	Mar		hruput une	S	ept-	١.	No Ope	1	lw.			Boiler Design			% ! H	Space eat	-			9.9	c	A .	
19	\rightarrow	21 2	+	-	-	5 2	6	77	28	29	30	31	32	_	-	-	-	36	-		_	40	41	42		14	-	4	48	-	-	51		-	Feb 54 5	+	May 6 57	+	Aug	1	61	62	63	-	-	66	67	-	70	71	72	73 7	4 7	5 76	77	- 78	79	- BC	1
			1	1				+	-			-		+	+																					1												-					+			1	1		1

Seg 1	1							,	5	Stack I	Data			í									ts wi		c	5	Co		1			p Stat		1					Cont	rol Re	egulat	tions				1		9 8	c	6
ID	Height	t	Dian	n		Tem	ηp			F	low R	ate			1	eloci	ty		Plur	me He	nght		Stack			:	Yı .	Mo		Yr	N	Ao .	Day				Reg 1			Re	g 2			Reg :	3					
19 20	21 22 2	3 24	25 26	27	28	29	30	31 :	32 3	3 34	35	36	37 3	8 39	40	41	42	43	44 4	45 4	6 47	48	49	50 5	51 5	2 53	54	55 5	6 5	57 58	59	60	61 6	2 €	3 6	54 6	55 6	6 67	68	69	70	71	72	73 7	4 75	5 76	77	78	79	80
		-						1						1												1	•		1	•	1		7	1				-				1						1	2	

Seg 1			Polluta ID	ant			E	Co	ontro ment	ol Cos	t		1	Prin	ntro		C	ontr	lo		stim. Cont	rol				Emis									asur rssro					Allo	owab	ole ins			EU	1	T 64													C	1 :
19 2	0 21	22	2 23	24	25	26	27	28	29	30	31	32	33		34	35	36	37	38	39	40	41	4:	4:	3 4	4 4	5	16	47	48	49	50	51	52	53	54	55	56	57		59	60	61		63	64	65	66	67	68		70	71	72 7	3 7	4 75		77	78	79	80
	\top	1				-	_	_					T		•				:	1	•		1			•		•		1					,	•	1	•						•	1		1	1	•	+			***	-	+				1	3	
		1	T	1			-						1	•	•				•	1	•	7	1				•			1					,		1							•	1	1	1	1	•	+	1		-+	-	+	1	+	1	1	3	\Box
1	+	†	+	1		-	•	•				-	1	•	-				•			•	1		٠	٠	•	•		1						•	1		-	٠					1	1	1	1		+	+		+	+	+	+	1	1	1	3	H
1	-	+	+	+			-+						†	٠	- 1				•	1	•		1	•	*		٠			1	. '	: .					1	٠		•					1	1	t	t			+-			+	-	+	+	+-	1	3	H
1	+	+	+	1			-	-				*	+	-					•	1	٠	•	1			•	٠				٠.						1								t		1	1		٠	*		+		-	+	+	1	1	3	H
1	+	+	+	1		-	+			-		•	1		٠				٠	1		•	1			٠	٠			1							1								ł	1	†	1				٠			+		+	+	,	2	\vdash
1	+	+	+	+		+	-	-					+		- •					ł	٠	*	1	•	٠	٠		,		1				,			1				٠,				-	1	+	ł		٠	٠		•	•	- •		<u>-</u>	+-		3	H
+	+	+	+	+				+		4		*	+	٠						ŧ	٠	•	ł	٠						-							1									1	1	1					٠	4			-		H	3	\vdash
1	+	+	+	+	-			-+		. 4	۸.		ł	•			-			ł	٠	•	+							1							-								1	1	1	ł								+-	+		+	3	H
+	+	+	+-	+		-	-				٨	+-	+		+	-			٠	1		•	-							-															1	1	1	1							+		+		1	3	H
1	+	+	+-	+	-	-	-	+	- 1	- 4	٨.	+	+		+					1		•	1							-							- 1						. ,		1		1	ł		٠				-		-+-	-	-	1	3	\vdash
1	+	+	+	+	-				- 4				+							1		•	-			Det.	٠.			- 1							- 1					. ,	, ,		1	1	1	1		+					+	+	1	1	1	3	\sqcup
1	+	+	+	-	-	-	+	+	-				1				-			1		A	1							1	٠.						- [[1	1					+			-	+	-		1	3	
1	\perp	+	+	1				+					1									•	1							-							- 1										1	1						1					1	3	
	1	1	1	1			-+	+					1						ě	1		•	1							1							1										1	1							1.	1	1_		1	3	
	_	1							_ ;		٨.		1									•								-							1										1								_				1	3	
				1				!			_			_	_				_	L			L		_		-	-				_				_		_	_							!										i	1		1	3	

	ate		C-							Plan	nt ID			Date	of R	ecord	1
St	ate		Col	unty		l '	AQC	•		Nun	nber		Y	er		Day	
1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18

EMISSION INVENTORY SUBSYSTEM (EIS) COMPREHENSIVE DATA HANDLING SYSTEM (CDHS)

Machine - Process (Segment 2) Input Form

Name of Person Completing Form	
Data	

Seg	1	Seg	2	1	1		s	cc			IV		Nun	BE nber	c	ID		U			uel P Solid perati		te				M	exim _L	um Di Rate	esign				lfur ntent		Cor	sh			He																						
19	20	21	22	23	24	25	26	27	28	29	30	31	3	2 3	3 3	4 3	5 3	16 3	37 . 7	38 - 3	9 4	10	81	42	13	44	45	46	47	48	49 5	0 5	51 5	2 5	3 5	54 5	55 5	6	57 5	58 5	9 6	0 6	51	62	13	64	65 6	6 6	57 6	8 6	9	70 7	71	72	73	74 7	5 76	77	78	75	9 80	1
П	7		\neg							T		T		1	T	T	T	T			•		•	•	I		•	•			•				Ť	•	Ā.	T				7	1			-			1	T	1		T					T	2	1	T	1

Seg 1	Se	g 2 D	C 0 0 1 - 4	S 0 C 0 0 7 d c 0													Sor	urce	Desc	cripti	JON.												5																												Be	0	4 u v - 0 a	
19 20	21	22	23	24	25	26	27	2	8 2	29	30	31	32	3	3 3	14 :	35	36	37	38	39	40	41	42	43	3 4	4 4	5 4	16 4	47	48 4	49	50	51	52	53	54	- 55	56	57	58	59	60	61	62	63	64	65	66	67	68	69	70	71	72	73	74	75	76 7	77	78	79	80	
													1	I		I		1				_	•		•			•				1																												I	2	2		

	Seg 1	Seç	32			utant D					E	mışş	sion	Faci	tor				A C o	\$ " ·		-	Polls	utant D				E	miss	on F	ector					C 0 6	U			lutan ID	1				,	Emiss	sion l	Facto	,		1	C o d o	E " .							S	0	1 :
1	9 20	21	22	23	24	25 2	6 2	7 :	28 2	29	30	31	32	33	3 3	34	35	36	37	38	39		0 4	1 4	2 4	3	44	45	46	47	48	49	50	51 9	52	3 5	4	55 5	56	57	58	59	60 -	61	62	63	64	65	66	67	68	69	70	71	72	73	74	75 7	6 77	78	79	80
			\Box	1	1	1	1	1	1	1				1	T	1	1				1	-	-	-		İ			•	•				•	1	1	1	•	•	•		1					-			*	1	1	1	1				T	T	2	3	\Box
r	+		\neg	+	\top	\top	1	†	1	1				1	Ť	+	1			1	1	1				1	-					7		*	1	1	1					1	*								+	1	7	1		1	7	\top	+	2	3	
h	+		1	+	1	+	+	+	+	+	-	-		+ -	1	+	1			-	†-		•		-	1		•				*		•	+	+	1	•	•		*	1		•					-		+	+	+	_		+	+	+	+	2	3	+
t	+		\forall	$^{+}$	+	+	+	+	+	+		-	+	+	1	-+	+	-	-	+	t	+	*	•		t			•	•		•		*	t	1	t	*			•	1						- 4		+	+	+	-+	+		1	+	+	+	+-	3	+
ŀ	+		\forall	+	+	+	+	+	+	+		-	-	+-	*	•					t		*		+	t			,		*	*		+	+	+	t			•	•	1	• +				-			-+	+	+	+	+	-	+	+	+	+	+	3	+
H	+	\vdash	+	+	+	+	+	+	- 4-	+		-	+	+ -	*	+		: -	-		+-	†	٠			+			٠		+	*			ŧ	+	+	٠	•			ł	. +	-	-		ė		- +	-+	+	-+	-	-+	-	-	+	+	+	+-	3	+
H	+	\vdash	-	+	+	+	+	+		+	4		+	• -	•			-		-	1		•			1						•			ł	-	ŧ					ł						. 4	-	-+	+	\dashv		+	-	-+	+	+	+	+	3	+
H	+	\vdash	-+	-	-		- •	+		4										-	ł					1									1	ł	ł					ł						4		-	-	-	-		-	-	+	+	+	+	+	-
-	+	\vdash	-	-+	+	-+		+	-+	-4					•			. }		ł	1					+									+	+	ł				*	+						4			+	+	-	-+	-	-	+	+	+	+	3	+
1	+-	-	-		-			+	-	-+					*					1	-					1						4			+		+					4	+					-	ι,		+	+	-		-	-	-	+	+	+	3	-
1	+		-		-			+			4		٠							ļ	ļ					1						*			1	ł	1					1	+				-	-		-	+	4	-	-	_	-	-	+	+	+	3	+
-	_		-		+		-	4												1	1					-									1	1	-					1			0 0			. 4			. 1	_	_	_	_		1	1	+	+	3	-
L			1	-	-			1												1	1					1			,			4			1	1	1					1								_	_	_					1	1	1	2	3	\perp
1					-		1								•											1										1	1					1																	L	2	3	
						1			1											1						1									1	1	İ					1								1										2	3	
					1	1		T		1					Ā		ĺ						ì			I									1	I			1			I								1	T	1		1						2	3	
								T		1			1			,						_	•	•	-											1	Ī	1	•	•	•	Ī		i						•	T	1		-	1					2	3	