

SAI AIRSHED MODEL OPERATIONS MANUALS

Volume I -- User's Manual

ATMOSPHERIC SCIENCES RESEARCH LABORATORY
OFFICE OF RESEARCH AND DEVELOPMENT
U.S. ENVIRONMENTAL PROTECTION AGENCY
RESEARCH TRIANGLE PARK, NORTH CAROLINA 27711

SAI AIRSHED MODEL OPERATIONS MANUALS

Volume I -- User's Manual

by

J. Ames, T.C. Myers, L.E. Reid, D.C. Whitney,
S.H. Golding, S.R. Hayes, and S.D. Reynolds

Systems Applications, Incorporated
101 Lucas Valley Road
San Rafael, California 94903

Contract No. 68-02-2429

Project Officers

Kenneth L. Demerjian
Kenneth L. Schere
Meteorology and Assessment Division
Atmospheric Sciences Research Laboratory
Research Triangle Park, North Carolina 27711

ATMOSPHERIC SCIENCES RESEARCH LABORATORY
OFFICE OF RESEARCH AND DEVELOPMENT
U.S. ENVIRONMENTAL PROTECTION AGENCY
RESEARCH TRIANGLE PARK, NORTH CAROLINA 27711

NOTICE

The information in this document has been funded wholly or in part by the United States Environmental Protection Agency under Contract No. 68-02-2429 to Systems Applications, Inc. It has been subject to the Agency's peer and administrative review, and it has been approved for publication as an EPA document. Mention of trade names or commercial products does not constitute endorsement or recommendation for use.

ABSTRACT

This report presents a general view of the Systems Applications, Inc. (SAI) Airshed Model as well as detailed operating instructions for the user. Included are discussions of all the files needed to run the model, the data preparation programs that produce each file, the input formats and data preparation methods, samples of input and output, and information flow diagrams that illustrate the job stream control on any computer.

Chapter II presents a technical summary of the SAI Airshed Model; Chapter III contains an overview of the model as a system of computer programs, outlining the five main functions that must be performed by users and programs together. Chapter IV discusses some of the concepts and terms basic to an understanding of the system, followed in Chapter V by descriptions of the job control notations that will be used throughout this manual. Chapters VI through XI examine in detail the five main functions of the system, providing input and output definitions and examples, and job control diagrams for each program that must be exercised.

The Systems Manual, the companion to the User's Manual, describes the system from a programmer's point of view. Included are descriptions of all subroutines and how they fit together, run-time core allocation techniques, internal methods of segment handling using secondary storage, and detailed structure definitions of all files in the system. The Systems Manual also discusses procedures for implementing the programs on different computers, and the addition, removal, or replacement of computing algorithms and data preparation methods.

This report was submitted in fulfillment of Contract No. 68-02-2429 by Systems Applications, Inc. under the sponsorship of the U. S. Environmental Protection Agency. The report covers the period from 23 August 1976 to 15 September 1979; work was completed as of 15 September 1979.

ACKNOWLEDGMENTS

The appearance of this manual is the result of the efforts of the production staff at Systems Applications, Incorporated. The contributions of S. Bennett, N. Bubbs, M. Davis, L. Hill, J. Roark, and C. Smith to the typing, graphic arts, and assembly of this manual are gratefully acknowledged.

CONTENTS

ABSTRACT	iii
ACKNOWLEDGMENTS	iv
LIST OF FIGURES	x
LIST OF TABLES	xiii
LIST OF EXHIBITS	xvi
LIST OF ABBREVIATIONS	xix
I INTRODUCTION	I-1
II THE SAI AIRSHED MODEL	II-1
A. The Technical Features of the SAI Airshed Model	II-3
1. Treatment of Atmospheric Chemistry.	II-5
2. Treatment of Advective Pollutant Transport	II-6
3. Treatment of Turbulent Diffusion	II-6
4. Treatment of Other Microscale Phenomena	II-7
5. Treatment of Surface Removal Processes	II-8
6. Other Technical Features	II-8
B. Model Usage	II-9
C. Model Applications	II-16
III OVERVIEW OF THE SYSTEM	III-1
A. M.E.B. Data File Preparation	III-4
B. M.E.B. Data File Segmentation	III-7
C. Control Data Preparation	III-8
D. Airshed Simulation	III-10
E. Display and Analysis	III-10
IV DEFINITION OF SYSTEM CONCEPTS	IV-1
A. The Modeling Region (Grid)	IV-1
1. Horizontal Distribution of Grid Cells	IV-1
2. Vertical Distribution of Grid Cells	IV-6

CHAPTER IV (Continued)

B.	Chemical Species	IV-10
C.	Time	IV-10
D.	Segmentation	IV-11
E.	Time Slices and Integration Time Steps	IV-13
V	JOB CONTROL SPECIFICATIONS	V-1
A.	Information Flow Diagrams	V-1
B.	Program Worksheet	V-3
C.	File Characteristics	V-3
VI	PACKETS USED IN CREATING THE M.E.B. Files	VI-1
A.	Elements of Packet Construction	VI-1
1.	Rules for Card Format	VI-3
2.	The Reserved Word ALL	VI-4
3.	Persistence of Data	VI-5
4.	Units of Measure	VI-6
5.	Variables	VI-6
6.	Methods	VI-7
7.	Vertical Methods	VI-16
B.	Packet Rules and Formats	VI-23
1.	CONTROL Packet Rules	VI-23
2.	REGION Packet Rules	VI-32
3.	UNITS Packet Rules	VI-37
4.	STATIONS Packet Rules	VI-47
5.	POINT SOURCES Packet Rules	VI-50
6.	BOUNDARIES Packet Rules	VI-54
7.	TIME INTERVAL Packet Rules	VI-58
8.	SUBREGION Packet Rules	VI-61
9.	METHOD Packet Rules	VI-65
10.	VERTICAL METHOD Packet Rules	VI-69
11.	CONSTANTS Packet Rules	VI-73
12.	GRID VALUES Packet Rules	VI-76
13.	STATION READINGS Packet Rules	VI-79
14.	EMISSIONS VALUES Packet Rules	VI-82
15.	EMISSIONS FACTORS Packet Rules	VI-85
16.	BOUNDARY READINGS Packet Rules	VI-88
17.	SCALARS Packet Rules	VI-91
18.	VERTICAL PROFILES Packet Rules	VI-94

VII	M.E.B. FILE PREPARATION RULES AND EXAMPLES	VII-1
A.	AIRQUALITY	VII-3
1.	Variables	VII-3
2.	Methods	VII-3
3.	Time Variation	VII-5
4.	Packets	VII-6
5.	Additional Input Files	VII-10
6.	Examples	VII-11
B.	BOUNDARY.	VII-30
1.	Variables	VII-30
2.	Methods	VII-30
3.	Time Variations	VII-32
4.	Packets	VII-32
5.	Additional Input Files	VII-37
6.	Examples	VII-37
C.	DIFFBREAK	VII-56
1.	Variables	VII-56
2.	Methods	VII-56
3.	Time Variation	VII-58
4.	Packets	VII-58
5.	Additional Input Files	VII-62
6.	Examples	VII-63
D.	EMISSIONS	VII-69
1.	Variables	VII-69
2.	Methods	VII-69
3.	Time Variation	VII-71
4.	Packets	VII-71
5.	Additional Input Files	VII-71
E.	METSCALARS	VII-73
1.	Variables	VII-73
2.	Methods	VII-75
3.	Time Variations	VII-75
4.	Packets	VII-75
5.	Additional Input Files	VII-78
6.	Examples	VII-78
F.	PTSOURCE.	VII-82
1.	Variables	VII-82
2.	Methods	VII-84
3.	Time Variation	VII-84
4.	Packets	VII-85
5.	Additional Input Files	VII-89
6.	Examples	VII-89

G.	REGIONTOP	VII-100
	1. Variables	VII-100
	2. Methods	VII-100
	3. Time Variation	VII-102
	4. Packets	VII-102
	5. Additional Input Packets	VII-106
	6. Examples	VII-107
H.	ROADWAY.	VII-113
	1. Variables	VII-113
	2. Methods	VII-113
	3. Time Variation	VII-115
	4. Packets	VII-115
	5. Additional Input Files	VII-115
I.	TEMPERATURE	VII-117
	1. Variables	VII-117
	2. Methods	VII-117
	3. Time Variation	VII-119
	4. Packets	VII-119
	5. Additional Input Files	VII-123
	6. Examples	VII-123
J.	TERRAIN.	VII-131
	1. Variables	VII-131
	2. Methods	VII-131
	3. Time Variation	VII-133
	4. Packets	VII-133
	5. Additional Input Files	VII-137
	6. Examples	VII-137
K.	TOPCONC	VII-143
	1. Variables	VII-143
	2. Methods	VII-143
	3. Time Variation	VII-145
	4. Packets	VII-145
	5. Additional Input Files	VII-150
	6. Examples	VII-150
L.	WIND	VII-156
	1. Variables	VII-156
	2. Methods	VII-156
	3. Time Variation	VII-158
	4. Packets	VII-158
	5. Additional Input Files	VII-164
	6. Examples	VII-164

VIII	SEGMENTATION OF M.E.B. FILES	VIII-1
A.	Calculating Core Requirements	VIII-1
1.	Segment Table	VIII-2
2.	Local Table	VIII-2
3.	Boundary Table	VIII-4
4.	Segment Scratch Table	VIII-4
5.	A Sample Problem	VIII-5
B.	The File Segmentation Program	VIII-9
1.	The SEGMENTDEF Packet	VIII-14
2.	The SEGMENT FILE Packet	VIII-18
IX	PREPARATION OF CONTROL DATA	IX-1
A.	The Chemistry Parameters File	IX-1
1.	CONTROL Packet Rules for the CHEMPARAM File	IX-1
2.	SPECIES Packet Rules for the CHEMPARAM File	IX-5
3.	REACTIONS Packet Rules for the CHEMPARAM File	IX-12
4.	COEFFICIENTS Packet Rules for the CHEMPARAM File	IX-23
5.	CPREP Sample Input and Output	IX-28
B.	The Simulation Controls File	IX-36
1.	CONTROL Packet Rules for the SIMCONTROL File	IX-36
2.	SIMULATION Packet Rules for the SIMCONTROL File	IX-36
3.	SPREP Sample Input and Output	IX-49
X	AIRSHED SIMULATION	X-1
A.	Job Control	X-1
1.	Input Files	X-5
2.	Scratch Files	X-5
3.	Output Files	X-5
B.	Printed Output	X-6
C.	Error Conditions	X-31
XI	DISPLAY AND ANALYSIS	XI-1
A.	Capabilities of the Display Program	XI-1
B.	Input Required by the Display Program	XI-2
1.	Data File Input	XI-2
2.	Card Input	XI-4
C.	Output Produced by the Display Program	XI-11
	REFERENCES	R-1

ILLUSTRATIONS

<u>Number</u>		<u>Page</u>
II-1	Schematic Illustration of the Grid Used and Treatment of Atmospheric Processes in the SAI Airshed Model	II-4
II-2	Example of a Printed Map of Ground-Level Concentration Predictions	II-10
II-3	Example of Plots Illustrating Model Predictions and Actual Measured Concentrations	II-11
II-4	Example of a Plotted Contour Map of Ground-Level Concentration Predictions	II-12
II-5	Example of the Results of a Population Exposure Analysis: Denver	II-13
II-6	Sample Results of Phase III--Simulation of Emission Control Scenarios	II-15
II-7	Contour Plot Illustrating the Predicted Effect of a Control Strategy	II-17
III-1	Airshed Simulation Program with Input and Output Files	III-2
III-2	Information Flow in the SAI Airshed Model System	III-3
IV-1	Example of a Modeling Region That Includes the Required Boundary Cells	IV-3
IV-2	54 Mile by 54 Mile Modeling Region of Los Angeles Basin	IV-3
IV-3	Example of the Location of a Modeling Region with Respect to a Reference Origin	IV-4
IV-4	Conventional Method for Numbering Grid Cells	IV-5
IV-5	Various Vertical Cell Distributions That Can Be Employed in the SAI Airshed Model	IV-8
IV-6	Example of the Segmentation of a Region	IV-12
V-1	Example of an Information Flow Diagram for Use in Job Control	V-2
VI-1	Definition of Boundary Line Segments	VI-55

<u>Number</u>		<u>Page</u>
VII-1	Information Flow Diagram for the AIRQUALITY File	VII-4
VII-2	Input Card Deck Structure for Preparing the AIRQUALITY File.	VII-7
VII-3	Information Flow Diagram for the BOUNDARY File	VII-31
VII-4	Input Card Deck Structure for Preparing the BOUNDARY File. .	VII-33
VII-5	Information Flow Diagram for the DIFFBREAK File	VII-57
VII-6	Input Card Deck Structure for Preparing the DIFFBREAK File .	VII-59
VII-7	Information Flow Diagram for the EMISSIONS File	VII-70
VII-8	A Possible Input Card Deck Structure for Preparing the EMISSIONS File	VII-72
VII-9	Information Flow Diagram for the METSCALARS File	VII-74
VII-10	Input Card Deck Structure for Preparing the METSCALARS File	VII-76
VII-11	Information Flow Diagram for the PTSOURCE File	VII-83
VII-12	Input Card Deck Structure for Preparing the PTSOURCE File .	VII-86
VII-13	Information Flow Diagram for the REGIONTOP File	VII-101
VII-14	Input Card Deck Structure for Preparing the REGIONTOP File .	VII-103
VII-15	Information Flow Diagram for the ROADWAY File	VII-114
VII-16	A Possible Input Card Deck Structure for Preparing the ROADWAY File	VII-116
VII-17	Information Flow Diagram for the TEMPERATUR File	VII-118
VII-18	Input Card Deck Structure for Preparing the TEMPERATUR File	VII-120
VII-19	Information Flow Diagram for the TERRAIN File.	VII-132
VII-20	Input Card Deck Structure for Preparing the TERRAIN File . .	VII-134
VII-21	Information Flow Diagram for the TOPCONC File	VII-144
VII-22	Input Card Deck Structure for Preparing the TOPCONC File . .	VII-146
VII-23	Information Flow Diagram for the WIND File	VII-157
VII-24	Input Card Deck Structure for Preparing the WIND File . . .	VII-159

<u>Number</u>		<u>Page</u>
VIII-1	Sample Region--Unsegmented	VIII-6
VIII-2	Sample Region Divided into Two Segments	VIII-8
VIII-3	Sample Region Divided into Three Segments	VIII-11
VIII-4	Information Flow Diagram for the File Segmentation Program . .	VIII-13
IX-1	Information Flow Diagram for Use in Creation of the CHEMPARAM File	IX-2
IX-2	Information Flow Diagram for Use in Creation of the SIMCONTROL File	IX-37
X-1	Information Flow Diagram for the Airshed Simulation Program . .	X-2
XI-1	Information Flow Diagram for the Display Program	XI-3

TABLES

<u>Number</u>		<u>Page</u>
II-1	Applications of the SAI Airshed Model To Study Air Quality in Urban Areas	II-22
III-1	M.E.B. Data Files	III-5
III-2	Airshed Simulation Program Control Files.	III-9
V-1	Header Record Lengths for the SAI Airshed Model Data Files . .	V-6
V-2	Characteristics of the SAI Airshed Model Data Files	V-7
VI-1	Packets Used by the SAI Airshed Model Data Preparation Programs.	VI-2
VI-2	Standard Entries for Cards 4 Through 8 of the CONTROL Packet for M.E.B. Files	VI-24
VI-3	Control Packet for M.E.B. Files	VI-25
VI-4	REGION Packet for M.E.B. Files	VI-33
VI-5	Implicit Variable Names and Internal Units Used in the SAI Airshed Model	VI-38
VI-6	Standard Unit Conversions	VI-39
VI-7	Standard Species Names and Molecular Weights Used for Unit Conversion	VI-42
VI-8	UNITS Packet for M.E.B. Files	VI-44
VI-9	STATIONS Packet for M.E.B. Files	VI-48
VI-10	POINT SOURCES Packet for the PTSOURCE File	VI-51
VI-11	BOUNDARIES Packet for the BOUNDARY File	VI-56
VI-12	TIME INTERVAL Packet FOR M.E.B. Files	VI-59
VI-13	SUBREGION Packet for M.E.B. Files	VI-63
VI-14	METHOD Packet for M.E.B. Files	VI-66

<u>Number</u>		<u>Page</u>
VI-15	VERTICAL METHOD Packet for M.E.B. Files	VI-70
VI-16	CONSTANTS Packet for M.E.B. Files	VI-74
VI-17	GRID VALUES Packet for M.E.B. Files	VI-77
VI-18	STATION READINGS Packet for M.E.B. Files	VI-80
VI-19	EMISSIONS VALUES Packet for the PTSOURCE File	VI-83
VI-20	EMISSIONS FACTORS Packet for the PTSOURCE File	VI-86
VI-21	BOUNDARY READINGS Packet for the BOUNDARY File	VI-89
VI-22	SCALARS Packet for the METSCALARS File	VI-92
VI-23	VERTICAL PROFILES Packet for M.E.B. Files	VI-95
VII-1	CONTROL Packet Entries for the AIRQUALITY File	VII-8
VII-2	CONTROL Packet Entries for the BOUNDARY File	VII-34
VII-3	CONTROL Packet Entries for the DIFFBREAK File	VII-60
VII-4	CONTROL Packet Entries for the METSCALARS File	VII-77
VII-5	CONTROL Packet Entries for the PTSOURCE File	VII-87
VII-6	CONTROL Packet Entries for the REGIONTOP File	VII-104
VII-7	CONTROL Packet Entries for the TEMPERATURE File	VII-121
VII-8	CONTROL Packet Entries for the TERRAIN File	VII-135
VII-9	CONTROL Packet Entries for the TOPCONC File	VII-147
VII-10	CONTROL Packet Entries for the WIND File	VII-161
VIII-1	CONTROL Packet Entries for File Segmentation	VIII-15
VIII-2	Contents of SEGMENTDEF Packet Cards.	VIII-16
VIII-3	Contents of SEGMENT FILE Packet Cards	VIII-19
IX-1	CONTROL Packet for the CHEMPARAM File	IX-3
IX-2	SPECIES Packet for the CHEMPARAM File	IX-6
IX-3	REACTION Packet for the CHEMPARAM File	IX-13

<u>Number</u>		<u>Page</u>
IX-4	COEFFICIENTS Packet for the CHEMPARAM File	IX-24
IX-5	CONTROL Packet for the SIMCONTROL File	IX-38
IX-6	SIMULATION PACKET for the SIMCONTROL File	IX-40
X-1	Input File Assignments	X-3
X-2	Scratch File Assignments	X-4
X-3	Output File Assignments	X-4
X-4	Airshed Simulation Program Error Conditions	X-32
XI-1	Display Program Control Input Definition	XI-5

EXHIBITS

<u>Number</u>		<u>Page</u>
V-1	Sample SAI Airshed Model Program Worksheet for Use in Job Control	V-4
VI-1	CONTROL Packet Format	VI-31
VI-2	REGION Packet Format	VI-36
VI-3	UNITS Packet Format	VI-46
VI-4	STATIONS Packet Format	VI-49
VI-5	POINT SOURCES Packet Format	VI-53
VI-6	BOUNDARIES Packet Format	VI-57
VI-7	TIME INTERVAL Packet Format	VI-60
VI-8	SUBREGION Packet Format	VI-64
VI-9	METHOD Packet Format	VI-68
VI-10	VERTICAL METHOD Packet Format	VI-72
VI-11	CONSTANTS Packet Format	VI-75
VI-12	GRID VALUES Packet Format	VI-78
VI-13	STATION READINGS Packet Format	VI-81
VI-14	EMISSIONS VALUES Packet Format	VI-84
VI-15	EMISSIONS FACTORS Packet Format	VI-87
VI-16	BOUNDARY READINGS Packet Format	VI-90
VI-17	SCALARS Packet Format	VI-93
VI-18	VERTICAL PROFILES Packet Format	VI-97
VII-1	Sample Input Deck for the AIRQUL Program	VII-12
VII-2	Sample Output From the AIRQUL Program	VII-18
VII-3	Sample Input Deck for the BNDARY Program	VII-38

<u>Number</u>		<u>Page</u>
VII-4	Sample Output from BNDARY Program	VII-41
VII-5	Sample Input Deck for the DFNSBK Program	VII-64
VII-6	Sample Output from the DFNSBK Program	VII-66
VII-7	Sample Input Deck for the METSCL Program	VII-79
VII-8	Sample Output from the METSCL Program	VII-80
VII-9	Sample Input Deck for the PTSRCE Program	VII-90
VII-10	Sample Output from the PTSRCE Program	VII-93
VII-11	Sample Input Deck for the REGNTP Program	VII-108
VII-12	Sample Output from the REGNTP Program	VII-110
VII-13	Sample Input Deck for the TMPRTR Program	VII-124
VII-14	Sample Output from the TMPRTR Program	VII-128
VII-15	Sample Input Deck for the TERAIR Program	VII-138
VII-16	Sample Output from the TERAIR Program.	VII-140
VII-17	Sample Input Deck for the TPCONC Program	VII-151
VII-18	Sample Output from the TPCONC Program	VII-153
VII-19	Sample Input Deck for the WINDSET Program	VII-165
VII-20	Sample Output from the WINDSET Program	VII-170
VIII-1	Storage Requirements Worksheet.	VIII-3
VIII-2	Worksheet Filled Out for an Unsegmented Region	VIII-7
VIII-3	Worksheet Filled Out for a Two-Segment Region	VIII-10
VIII-4	Worksheet Filled Out for a Three-Segment Region	VIII-12
VIII-5	SEGMENTDEF Packet Format	VIII-17
VIII-6	SEGMENT FILE Packet Format	VIII-20
VIII-7	Sample Input to the File Segmentation Program	VIII-21
VIII-8	Sample Output from the File Segmentation Program	VIII-22

<u>Number</u>		<u>Page</u>
IX-1	CONTROL Packet Format for the CHEMPARAM File	IX-4
IX-2	SPECIES Packet Format for the CHEMPARAM File	IX-8
IX-3	SPECIES Definition Worksheet	IX-10
IX-4	REACTIONS Packet Format for the CHEMPARAM File	IX-15
IX-5	REACTIONS Definition Worksheet	IX-16
IX-6	COEFFICIENTS Packet Format for the CHEMPARAM File	IX-25
IX-7	COEFFICIENTS Definition Worksheet	IX-26
IX-8	Sample CPREP Input for the CHEMPARAM File	IX-29
IX-9	Sample CPREP Output for the CHEMPARAM File	IX-31
IX-10	CONTROL Packet Format for the SIMCONTROL File	IX-39
IX-11	SIMULATION Packet Format for the SIMCONTROL File	IX-48
IX-12	Sample SPREP Input for the SIMCONTROL File	IX-50
IX-13	Sample SPREP Output for the SIMCONTROL File	IX-51
X-1	Annotated Excerpt of Output from an Airshed Simulation Program Run	X-8
X-2	Sample Crash Output from the Airshed Simulation Program	X-27
XI-1	Sample Input for the Display Program	XI-10
XI-2	Standard Display Program Header Page	XI-12
XI-3	Sample Vertical Concentration Profile Output--Prediction Mode .	XI-13
XI-4	Sample Ambient Concentration Maps--Prediction Mode	XI-14

ABBREVIATIONS

act	activation
add	additive
b	boundary
bd	bound
beg	beginning
B.T.	Boundary Table
chem	chemistry
coeff	coefficient
col	column
conc	concentration
const	constant
crit	criterion
dark	darkness
diam	diameter
fact	factor
ht	height
i	initial
iter	iteration
LBL	Lawrence Berkeley Laboratory
loc	location
low	lower
L.T.	Local Table
max	maximum
M.E.B.	meteorology, emissions, and initial and boundary conditions
meth	method
min	minimum
molec	molecular
mult	multiplicative
num	numerical
param	parameter

pr	print
prof	profile
pt	point
srce	source
reac	reaction
ref	reference
rel	relative
resis	resistance
spec	species
S.S.T.	Segment Scratch Table
S.T.	Segment Table
stn	station
st-st	steady-state
subreg	subregion
surf	surface
temp	temperature
tol	tolerance
u-def	user-defined
up	upper
UTM	Universal Transverse Mercator
val	value
var	variable
vartn	variation
vel	velocity
vert	vertical
wt	weight

I INTRODUCTION

This report presents a general view of the Systems Applications, Inc. (SAI) Airshed Model as well as detailed operating instructions for the user. Included are discussions of all the files needed to run the model, the data preparation programs that produce each file, the input formats and data preparation methods, samples of input and output, and information flow diagrams that illustrate the job stream control on any computer.

Chapter II presents a technical summary of the SAI Airshed Model; Chapter III contains an overview of the model as a system of computer programs, outlining the five main functions that must be performed by users and programs together. Chapter IV discusses some of the concepts and terms basic to an understanding of the system, followed in Chapter V by descriptions of the job control notations that will be used throughout this manual. Chapters VI through XI examine in detail the five main functions of the system, providing input and output definitions and examples, and job control diagrams for each program that must be exercised.

The Systems Manual, the companion to the User's Manual, describes the system from a programmer's point of view. Included are descriptions of all subroutines and how they fit together, run-time core allocation techniques, internal methods of segment handling using secondary storage, and detailed structure definitions of all files in the system. The Systems Manual also discusses procedures for implementing the programs on different computers, and the addition, removal, or replacement of computing algorithms and data preparation methods.

II THE SAI AIRSHED MODEL

Systems Applications, Incorporated (SAI) designed its Airshed Model to calculate the concentrations of both reactive and inert air pollutants through simulation of the numerous physical and chemical processes that take place in the atmosphere. Much of the current interest in the model arises from the need to calculate ozone concentrations as a part of various environmental assessment studies (such as federally required State Implementation Plans and New Source Reviews). The results of recent evaluation and applications studies indicate that the SAI Airshed Model provides a sound, practical, and effective means for analyzing a variety of regional air quality problems.

Interactions among organic compounds (including pure and oxygenated hydrocarbons and other hydrocarbon derivatives) and nitrogen oxides (NO_x) are usually responsible for the relatively high ozone concentrations observed in and downwind of urban areas. Among the main factors affecting photochemical air quality in urban areas are:

- > The spatial and temporal distribution of emissions of NO_x and organic species.
- > The composition of the emitted organic species.
- > The spatial and temporal variations of the wind field.
- > The stability of the atmosphere and the associated dynamics of the mixing layer.
- > The chemical reactions involving organic species and NO_x .
- > The diurnal variations of ultraviolet radiation.
- > The loss of ozone and its precursors by surface uptake processes.
- > The ambient background concentrations of ozone, organic species, and NO_x immediately upwind of the urban area and within an elevated inversion layer.

Thus, development of an accurate ozone prediction relationship requires investigation of the relevant physical and chemical atmospheric phenomena that influence the magnitude and distribution of both ozone and its precursors.

To limit ozone concentrations, one must control all or part of the ozone formation process. Practically, man has the most influence on anthropogenic emissions. If ozone concentrations were proportional to emissions of organic compounds or NO_x , it would be simple to calculate the reduction in anthropogenic emissions necessary to achieve a desired reduction in ozone concentrations. But the relationship between ozone air quality and emissions of NO_x or organic species is complicated and nonlinear. Furthermore, the relationship changes with location and even with time at a given location because of variations in emissions, meteorology, and other factors.

To make available an appropriate quantitative treatment of this relationship, the U.S. Environmental Protection Agency (EPA) has, through a multiyear research effort, supported the development of the SAI Airshed Model. Initial model development efforts and applications (to the Los Angeles area) are fully described in a 15-volume series of reports by Roth et al. (1971) and Reynolds et al. (1973a). These reports are summarized in the three papers by Reynolds et al. (1973b, 1974) and Roth et al. (1974). Evaluation of the model's predictions and its components at that time showed that improved treatments of some physical and chemical processes were necessary. As a result, another series of research efforts was carried out to improve the model. These efforts are described in a 7-volume series of reports by Jerskey and Seinfeld (1976), Jerskey et al. (1976), Killus et al. (1977), Lamb (1976), Lamb et al. (1977), Liu et al. (1976a), and Reynolds et al. (1976), and in the papers by Lamb et al. (1975), Liu and Seinfeld (1975), Liu et al. (1976b), and Reynolds (1977). A summary of the technical features included in this model is given in the report by Reynolds et al. (1982).

A. THE TECHNICAL FEATURES OF THE SAI AIRSHED MODEL

The SAI Airshed Model can simulate the dynamic behavior of up to 20 pollutants. When photochemical simulations are carried out, 11 species must be included: nitric oxide (NO), nitrogen dioxide (NO₂), ozone (O₃), single-bonded carbon atoms (PAR), double-bonded carbon atoms except ethylenes (OLE), aromatic-bonded carbon atoms (ARO), carbonyl-bonded carbon atoms, ethylene, benzaldehyde (BZA), peroxyacetyl nitrate (PAN), and carbon monoxide (CO). In addition, the model can provide predictions of SO₂ and aerosol.* The user can exercise any of the following options with respect to the pollutants to be simulated:

- > Up to 20 unreactive pollutants.
- > Photochemical species, CO,[†] and up to 9 other unreactive pollutants.
- > Photochemical species, CO, SO₂, and up to 8 other unreactive pollutants.
- > Photochemical species, CO, SO₂, aerosol,[§] and up to 7 other unreactive pollutants.
- > Photochemical species, CO, aerosol,** and up to 8 other unreactive pollutants.


As illustrated in Figure II-1, simulations are performed on a three-dimensional grid selected by the user to cover the region of interest. Figure II-1 also shows the various atmospheric processes treated in each grid cell. The base of an elevated inversion layer is often selected as the top of the grid, but the model includes provisions to facilitate treatment of the inversion layer itself. The model's computer codes can handle any number of cells in the horizontal and vertical directions.

* The aerosol component includes emitted particulates and organic, nitrate, and sulfate aerosols formed in the atmosphere.


† Photochemical species include the first 10 pollutants cited above.

§ This aerosol consists of organic, nitrate, and sulfate components.


** This aerosol consists of only the organic and nitrate components.



(a) The Area To be Modeled



(b) Specification of the Grid



(c) Atmospheric Processes Treated in a Column of Grid Cells

Figure II-1. Schematic Illustration of the Grid Used and Treatment of Atmospheric Processes in the SAI Airshed Model

1. Treatment of Atmospheric Chemistry

Ozone is not emitted from sources; rather, it is formed by chemical reactions in the atmosphere. Consequently, to calculate ozone concentrations, a physicochemical model must contain a kinetic mechanism, that is, a group of chemical reactions and rate constants intended to represent the ozone formation process. Because of computing time limitations, it is not possible to include explicitly each chemical species of interest; thus, most of these kinetic mechanisms treat organic compounds in groups, often on the basis of the reactive functional groups they contain. For example, propylene, 1-butene, and 1-pentene, which each contain a carbon-carbon double bond, can be aggregated together as a single "lumped" species. Such a mechanism was used in the airshed model until 1976, when the Carbon-Bond Mechanism was developed.

Because of the association of reactions and reactivities with carbon bonds, the range of reactions and rate constants to be treated in a kinetic mechanism can be narrowed considerably when each carbon atom is treated according to its bond type. This concept is the basis for the Carbon-Bond II Mechanism, a 65-reaction mechanism developed at SAI and employed in the SAI Airshed Model (Whitten and Hogo, 1977; Whitten, Killus and Hogo, 1980). In this mechanism, the carbon atoms of each organic compound are assigned to one of the following groups: single-bonded carbon atoms, double-bonded carbon atoms except ethylene, ethylene, aromatic-bonded carbon atoms, carbonyl-bonded carbon atoms, and benzaldehyde. Further discussion of the definition and treatment of these groups is given in the final report on the application of the model to the Tulsa urban area (Reynolds et al., 1982). The user can add to the mechanism four reactions describing SO_2 oxidation and reaction expressions accounting for the formation of sulfate, organic, and nitrate aerosol products.* Simulations of smog chamber experiments indicate that the Carbon-Bond Mechanism performs significantly better than those previously employed in the airshed model (Whitten, Hogo, and Killus, 1980).

* The 69-reaction mechanism is shown in Chapter IX and is discussed in more detail in Reynolds et al. (1982).

2. Treatment of Advective Pollutant Transport

Pollutants are transported primarily by advection, that is, by the mean or bulk motion of the wind. A major difficulty in treating advection is wind shear, the variation of the wind with altitude. The wind speed near the ground typically increases with height, but the wind several hundred meters aloft may be faster or slower--and frequently from a different direction. In the original airshed model, wind shear was neglected, but later sensitivity studies indicated that inclusion of wind shear effects in the model could significantly alter NO_2 and ozone predictions (Reynolds et al., 1976). Consequently, the capabilities of the model were expanded to treat wind shear phenomena. Theoretical wind shear relationships were derived by Lamb (1976) using the predictions of a planetary boundary layer model developed by Deardorff (1972). These relationships are useful when wind measurements aloft are not available. When wind measurements are available both at the surface and aloft, one or more objective techniques are used to prepare appropriate three-dimensional wind inputs to the model. Two algorithms in the model are described by Liu et al. (1973) and Killus et al. (1977).

3. Treatment of Turbulent Diffusion

Pollutants are transported and dispersed largely by the action of the wind rather than by molecular diffusion. The treatment of advection discussed above does not represent pollutant transport completely because it ignores the influence of small-scale features of the wind, called eddies. Describing these microscale features of the wind deterministically is difficult because available data are insufficient to characterize winds on such a fine scale. Consequently, it is necessary to parameterize the microscale turbulent diffusion processes. In the SAI Airshed Model, and most other grid models as well, transport of a pollutant by turbulent diffusion is assumed to be proportional to the rate of change of concentration with position (i.e., concentration gradient). The

proportionality factor is termed the eddy diffusivity coefficient. These coefficients are sometimes treated as constants, but they can more accurately be treated as functions of atmospheric stability, surface roughness, and height above the ground.

Because of the empirical nature of the eddy diffusivity concept, it has heretofore been difficult to obtain precise measured or theoretical estimates for the diffusivity coefficients. At SAI, considerable effort has been devoted to the study of turbulent transport processes. As a result of these efforts, we have developed a novel procedure for estimating diffusivity coefficients. In this approach, control theory techniques are employed in conjunction with the results of a sophisticated planetary boundary layer model to generate "optimal" diffusivity values. For further details, the reader is referred to the reports by Lamb (1976) and Lamb et al. (1977).

4. Treatment of Other Microscale Phenomena

Several phenomena besides turbulent diffusion have characteristic spatial or temporal scales too small for explicit, deterministic resolution in urban and regional grid models. Two important examples are the rise of a hot, buoyant emissions plume from a large point source and the scavenging of ozone near roadways by NO emitted from vehicles. Studies of these phenomena and others at SAI resulted in the incorporation of an improved treatment of plume rise from point sources. In addition, a preliminary version of a module to treat the microscale effects of the emissions from a network of line sources (e.g., highways) in the lowest layer of grid cells has also been developed. In this layer, taken to be about 20 meters deep, NO emissions from vehicles on a roadway are allowed to react only with the ozone in the immediate vicinity of the roadway. More detailed descriptions of these algorithms and other microscale phenomena are given by Lamb (1976) and Lamb et al. (1977). Since the performance of the microscale module has not been thoroughly evaluated, we do not recommend that this optional model feature be exercised at this time.

5. Treatment of Surface Removal Processes

Many types of pollutants, including NO₂, ozone, and SO₂ in particular, can be removed from the atmosphere by chemical reaction, adsorption, or absorption at various surfaces found in urban areas. A methodology for calculating the removal of gaseous pollutants by surface sinks has been incorporated in the model. Surface removal is assumed to take place in two steps: transport to the surface followed by uptake by the surface. Parameterization of this two-step process is accomplished by defining a resistance to mass transport and a resistance to surface removal. The transport resistance is estimated from theoretical considerations of turbulent transfer in the atmospheric boundary layer, and the surface resistance is obtained from experimental data on the uptake of pollutants by various types of surfaces (Killus et al., 1977).

6. Other Technical Features

The numerical procedure used to solve the conservation-of-mass equations for each pollutant is an important component of a grid model. To minimize the propagation of numerical errors, techniques for treating horizontal (advective) pollutant transport--an element of the model particularly difficult to handle numerically--were examined. The results of these studies indicated that, of the techniques examined, the SHASTA integration scheme provided the best balance between accuracy of prediction and computational speed (Reynolds et al., 1976; Killus et al., 1977).

The SAI Airshed Model contains features designed to reduce cost by minimizing labor and computing expenses. For example, computerized data preparation programs are available for automating the conversion of various types of data into the proper input format. These features have no effect on the model's treatment of atmospheric processes, but they do aid the user in preparing the inputs required by the Airshed Model.

The model output consists of the predicted pollutant concentrations for every grid cell. These predictions are generally averaged over a period of one hour and are saved on a computer file for subsequent display and analysis. An example of the printed output produced by the display program is given in Figure II-2. If other computer graphics capabilities are available, then the results can be plotted as shown in Figures II-3 and II-4. Note, however, that the computer programs described in this manual produce only printed displays of the predicted concentrations. Gridded census data can be used in conjunction with the model predictions to estimate the dosages and exposures that are experienced by the human population within the modeling region. The results of an exposure analysis carried out for Denver are shown in Figure II-5. Of course, other displays and analyses can be prepared depending on the needs of the user.

B. MODEL USAGE

In general, studies that employ the SAI Airshed Model can be segmented into three phases: adaptation, evaluation of validity and performance, and application. The specifics of each phase depend on the region to be modeled and the intended application, but certain characteristics apply to each case.

The primary objective of Phase I is to adapt the model for application to a particular region. Efforts involved in this undertaking include:


- > Review of pertinent air quality studies of the region.
- > Examination and assessment of available emissions and aerometric data.
- > Specification of supplemental data (if any) needed for verification and application of the model.
- > Collection of supplemental data, if necessary, through intensive field monitoring studies.
- > Adaptation of existing, or development of new, input data preparation programs.

Upon completion of these tasks, the user is in a position to carry out photochemical simulations with the model.

1	8	5	4	8	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31	32	33	34	35	36	
24	18	14	12	10	8	6	7	7	7	6																									24	
20	28	20	17	18	15	12	12	12	12	12	10																									20
48	37	29	24	23	22	22	23	23	21	21	15																									48
48	47	41	37	34	32	32	32	30	28	26	25	21	18																							48
31	36	38	31	26	23	21	21	23	25	21	21	20	19	19	19	20	22	26	30	33	35	38	39	36	24	23	21	20	19	18	18	17	16	21		
20	7	9	8	7	4	5	5	4	5	8	10	11	12	13	14	15	16	17	19	21	25	30	36	37	35	31	27	24	22	21	21	20	19	18	16	20
19	5	2	1	1	1	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	19		
18	8	7	8	4	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	18	
17	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	17	
16	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	16	
15	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	15	
14	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	14	
13	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	13	
12	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	12	
11	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	11	
10	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	10	
9	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	9	
8	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	8	
7	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	7	
6	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	6	
5	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	5	
4	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	
3	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	3	
2	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	2	
1	7	7	7	5	5	5	5	5	5	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	4	1	


Source: Tesche and Burton (1978).

Figure II-2. Example of a Printed Map of Ground-Level Concentration Predictions. Average ground-level O_3 concentrations (pphm) are given for Los Angeles on 4 August 1975 between 1:00 and 2:00 p.m. PST.




Source: Anderson et al. (1977).

Figure II-3. Example of Plots Illustrating Model Predictions and Actual Measured Concentrations. Ozone concentrations measured at various stations in the Denver area on 28 July 1976 are compared with the corresponding predictions of the SAI Airshed Model as modified for Denver.



Source: Tesche and Burton (1978).

Figure II-4. Example of a Plotted Contour Map of Ground-Level Concentration Predictions. Average ground-level O₃ concentrations (pphm) are given for Los Angeles on 4 August 1975 between 1:00 and 2:00 p.m. PST.



Source: Anderson et al. (1977)

Figure II-5. Example of the Results of a Population Exposure Analysis:
 Denver

Phase II is devoted to assessing the performance of the model. First, the model is used to simulate the formation of photochemical smog on one or more days in the past chosen to represent typical or episodic meteorological conditions. Model predictions are then examined in light of actual observations in an effort to characterize model performance (see Figure II-3). Tasks in this phase include:


- > Selection of days for testing.
- > Preparation of model inputs for each day.
- > Performance of model simulations and analysis of results.
- > Collection of additional data, modification of the model or input data preparation programs, or both, as needed, until satisfactory model performance is obtained.

After the model has been demonstrated to perform adequately, further applications studies can be carried out with reasonable confidence.

The intent of the air quality modeling study is not fully realized until Phase III, when control issues are addressed. Applications of the model generally involve the following tasks:

- > Definition of the scenarios to be considered.
- > Specification of input conditions for each scenario (for example, adverse meteorological conditions, weekday emissions, and so on).
- > Performance of model simulations and analysis of results.

In evaluating the effects of some change in emissions, one compares the predictions for that case with those for a base case (see Figure II-6). The base case might, for example, represent conditions without the imposition of emissions controls. Several measures can be examined in assessing the effects of emissions alterations, including maximum one-hour-average concentrations, population dosages, and area-wide concentration changes. Of course, the model predictions can also be compared



Source: Anderson et al. (1977).

Figure II-6. Sample Results of Phase III--Simulation of Emission Control Scenarios. Ozone concentrations predicted by the SAI Airshed Model for the Denver area for 1976 emissions and a 30 percent emissions reduction are shown; note that reducing emissions of both NO_x and organic species by 30 percent reduced the maximum predicted ozone concentration by about 15 percent.


with air quality standards. As shown in Figures II-5 through II-7, various graphical techniques can be employed to display the model results.

C. MODEL APPLICATIONS

Many seemingly straightforward but inherently difficult issues arise in planning for the abatement and control of air pollution in an urban area. Some of these issues can best be addressed through the use of an airshed model; others can be addressed only in this way. This section discusses potential model applications and summarizes studies performed through June 1978 that employed the SAI Airshed Model.

Analyses that can be carried out with the SAI Airshed Model include:

- > Development of an emissions control policy. For example, the model can be applied to cities to ascertain the influence of various potential motor vehicle emissions standards on ambient CO, ozone, and NO₂ concentrations.
- > Evaluation of proposed emissions control strategies. The model would be particularly useful in helping to establish estimates of the relative emissions reductions of organic species and NO_x required to achieve the ozone and NO₂ air quality standards.
- > Selection of sites for future sources of air contaminants. Of particular interest here is the examination of alternative future source development scenarios that would minimize the possibility of subsequent violations of air quality standards.
- > Planning for the control of air pollution episodes. The model can be used to ascertain either the extent of intermittent controls required to relieve episodic conditions or the effectiveness of alternative control measures, such as emissions reductions in various portions of a region.



Source: Tesche and Burton (1978).

Figure II-7. Contour Plot Illustrating the Predicted Effect of a Control Strategy. This figure indicates the predicted effect on O₃ levels in the Los Angeles area of a 50 percent reduction in motor vehicle emissions of NO_x and organic species. The O₃ isopleths (pphm) represent the difference between the control strategy and base case predictions for the hours 1:00 to 2:00 p.m. PST.

- > Assessment of the contributions responsible for existing levels of air pollution. The model can be exercised both with and without particular sources included in the emissions inputs to examine their contributions to existing air quality.
- > Estimation of air quality in areas for which pollutant concentration data are unavailable. Model predictions can be used to locate regions experiencing high pollutant concentrations and thus aid in selecting additional monitoring sites.

In general, applications such as those cited above are carried out by altering any of four inputs to the model: the spatial distribution of emissions, the temporal distribution of emissions, the composition of organic compounds emitted from sources, and the initial and boundary pollutant concentrations. Control strategies that attempt to alter the reactivity of organic species emitted into the air, such as solvent substitution measures, can be handled in the model by altering the magnitude and composition of the emissions from the appropriate sources. In addition, emissions from one city may be responsible for increased background pollutant concentrations in a city downwind. The effects of alterations in background concentrations can be examined through changes in the initial and boundary pollutant concentrations used as input to the model.

Besides these applications, the SAI Airshed Model can be used in other photochemical air pollution analyses. Sensitivity studies, for example, can help assess the relative influences of various physical and chemical processes on pollutant concentrations in a particular region. Such information might be used as a basis for simplifying the treatments of various processes in the model or for reducing the amount of input data to be collected. Moreover, the model can serve as an educational tool by enhancing the existing understanding of the causes of photochemical air pollution in the region. The SAI Airshed Model can also be employed to test new theories, algorithms, and parameterizations of atmospheric processes. Thus, the model is useful in applications ranging from the evaluation of

emissions control strategies to the advancement of knowledge in atmospheric science.

Initially, most applications of the SAI Airshed Model were in research projects aimed at improving the model's components or in evaluative studies to ascertain its performance. However, several studies have been carried out that are illustrative of the applications cited earlier. We list below several of these investigations carried out through 1978 that the user can refer to for information on applying the model to suit specific needs.

- > An evaluation of four motor vehicle emissions control strategies for Los Angeles. The scenarios included (1) a 30 percent reduction in vehicle mileage, (2) a 100 percent reduction in vehicular emissions, (3) 79 percent, 73 percent, and 62 percent reductions in the emissions of organic species, NO_x and CO , respectively (strategy proposed by the Environmental Quality Laboratory at Caltech), and (4) a 90 percent reduction in vehicle mileage in the downtown Los Angeles area (Reynolds et al., 1973a).
- > An examination of a proposed State Implementation Plan for Los Angeles (June 1973). Three scenarios were considered in this study: (1) baseline 1969 conditions, (2) baseline 1977 conditions (with existing legislation in force), and (3) 1977 conditions with additional emission reductions resulting from gasoline rationing, carpooling, implementation of special bus lanes and parking restrictions, and limited control of stationary sources (Reynolds and Seinfeld, 1975).
- > An analysis of air quality for the Denver metropolitan region for the years 1976, 1985, and 2000. This study examined the impact on air quality of the urban growth associated with the construction of new wastewater treatment facilities. Model runs were also made to ascertain the sensitivity of the predictions to various land use scenarios that involved alterations to the spatial

- distribution of emissions (Anderson et al., 1977). Samples of the results are given in Figures II-3, II-5, and II-6.
- > A demonstration of the model's utility in selecting sites for aerometric monitoring. As part of a study sponsored by the EPA Environmental Monitoring and Support Laboratory in Las Vegas, the SAI model was applied to Las Vegas and the predictions were employed to estimate the best locations for CO monitors (Liu et al., 1977).
 - > An examination of the influence of highway location, design, and operation on photochemical smog formation. This study, sponsored by the Federal Highway Administration, is evaluating various transportation control strategies and will provide guidance to highway personnel in the use of photochemical models (Reynolds et al., 1979).
 - > An analysis of model sensitivity to ascertain the relationships between the quantity of data collected for use in estimating model inputs and the performance of the SAI Airshed Model. This information will be integrated into a larger study for the EPA Office of Air Quality Planning and Standards (OAQPS) aimed at examining means for employing the SAI model in evaluating the performance of simple oxidant relationships (Teschke et al., 1981).
 - > An examination of the capability of the SAI model to resolve the impact of emissions from major elevated point sources on regional air quality. Sponsored by the Southern California Edison Company, this study focused on the influence of NO_x and SO_2 emissions reductions on the expected incremental changes in NO_2 , ozone, and sulfate levels aloft and at the ground in the Los Angeles area (Teschke and Burton, 1978).
 - > An evaluation of alternative population growth scenarios for the Los Angeles metropolitan area. The purpose of this study is to help regional planners at the Southern California Association of Governments determine the extent to which future air quality levels in 1990 will be sensitive to the

manner in which the area is allowed to develop over the next 12 years.

Other ongoing studies that are not direct applications of the model but that do have some bearing on model usage include:

- > An investigation to establish guidelines for setting model performance measures and standards. This study for the OAQPS will yield information that will aid in evaluating the suitability of a model for use in a particular application (Hayes, 1978).
- > A study to establish guidelines for validation of air quality models. This effort will provide guidance to users in the examination of model performance. This study is also being carried out for OAQPS (Hillyer, Reynolds, and Roth, 1979).

In addition to these studies, versions of the SAI Airshed Model have been implemented for use in several cities, both in this country and in Europe. Table II-1 summarizes these applications.

TABLE II-1. USE OF THE SYSTEMS APPLICATIONS (SAI) AIRSHED MODEL
IN STUDIES OF AIR QUALITY IN URBAN AREAS.

User	Model Version	Study Site	Sponsor and Reference
Systems Appl., Inc.	1973	Los Angeles	EPA, Contracts CPA 70-148 and 68-02-0339 (Reynolds, 1973)
Systems Appl., Inc./ CAL TRANS/CARB	1973	Los Angeles	California Department of Transportation, Contract K-7319; California Air Resources Board, Contract ARB 4-250
Systems Appl., Inc.	1973	Los Angeles	Texaco
Systems Appl., Inc.	1973	Los Angeles	Western Oil and Gas Association
Systems Appl., Inc.	1977	Los Angeles	DOT, Contract DOT-FH-11-8529 (Reynolds et al., 1979)
Systems Appl., Inc.	1977	Los Angeles	Southern California Edison Company (Tesché and Burton, 1978)
Systems Appl., Inc.	1977	Los Angeles	Southern California Association of Governments (Reynolds et al., 1978)
Systems Appl., Inc.	1978	Los Angeles	Southern California Association of Governments and South Coast Air Quality Management District
Systems Appl., Inc.	1978	Los Angeles	NCAQ Contract (Souten, Tesché, and Oliver, 1981)
Systems Appl., Inc.	1982	Los Angeles	Western Oil and Gas Association (Roth et al., 1984)
Systems Appl., Inc.	1978	Tulsa	EPA Contract 68-02-3370 (Reynolds et al., 1982)
Systems Appl., Inc./ TNO	1978	The Netherlands	TNO (Bultjes et al., 1982)
Systems Appl., Inc./ Freie Universität Berlin/TNO	1978	Bonn/Cologne	Stern and Scherer (1982)
Systems Appl., Inc.	1978	California Central Valley	PG&E
Systems Appl., Inc.	1978	Los Angeles	EPA, Contract 68-02-2870 (Tesché et al., 1981)

Continued

TABLE II-1 (Concluded)

User	Model Version	Study Site	Sponsor and Reference
Systems Appl., Inc.	1978	Los Angeles	EPA, Contract RP-1375-1-2 (Seigneur et al., 1983)
Systems Appl., Inc./ State of Colorado	1973	Denver	Colorado Department of Highways, Contract 75-109
Systems Appl., Inc.	1976	Denver	EPA Region VIII, Contract 68-01-4341 (Anderson et al., 1977)
Systems Appl., Inc./ State of Colorado	1976	Denver	Colorado State Health Department and Department of Highways
Systems Appl., Inc.	1977	Denver	DOT, Contract DOT-FH-11-8529 (Reynolds et al., 1979)
Systems Appl., Inc.	1977	Denver	ERT/Colorado Interstate Pipeline Company
Systems Appl., Inc.	1973	Las Vegas	EPA, Contract 68-03-2174 (Liu et al., 1977)
Systems Appl., Inc./ British Leyland	1973	Turin, Italy	British Leyland
Systems Appl., Inc.	1977	Phoenix	EPA, Contract 68-03-2446
Systems Appl., Inc.	1977	Tampa	EPA, Contract 68-03-2446
Systems Appl., Inc.	1978	St. Louis	EPA, Contract 68-02-2429
Systems Appl., Inc.	1978	St. Louis	EPRI, Contract RF-1375-1-2 (Seigneur et al., 1983)
Systems Appl., Inc.	1978	Sacramento	DOT, Contract DOT-FH-11-8529 (Reynolds et al., 1979)
Systems Appl., Inc.	1982	Las Vegas	Southern California Edison Company (Tesche, Oliver, and Haney, 1982)
SRI, International	1982	Philadelphia	EPA, Contract 68-02-3538
Systems Appl., Inc.	1983	Philadelphia	EPA, Contract 68-02-3582 (Haney, Tesche, and Killus, 1983)


III OVERVIEW OF THE SYSTEM

The SAI Airshed Model System contains at its core the Airshed Simulation Program, the input data that consist of 10 to 14 files, depending on the program options chosen. Each file is created by a separate data preparation program. The output from the Airshed Simulation Program consists of three data results files and an execution trace report. The output data files can be further processed by the display and analysis programs and can also be used for restarting the simulation. Figure III-1 shows the Airshed Simulation Program and identifies its input and output files.

The SAI Airshed Model System can be described according to the five major tasks or functions that the user and the programs must perform:

- > M.E.B. (meteorology, emissions, and initial and boundary conditions) file preparation.
- > M.E.B. file segmentation.
- > Control data preparation.
- > Airshed simulation.
- > Display and analysis.

This classification of programs and tasks is used as the organizational basis for both this User's Manual and the companion Systems Manual. Each of the five major functions is represented by a rectangular box in Figure III-2, which illustrates the flow of information through the system and shows the position of each major function within the system. The following sections of this chapter briefly discuss each function in terms of the activities required of the user, and the remaining chapters of this report present the detailed information necessary for the completion of each task.



* Optional files.

** Optional file not recommended for usage at this time.

Figure III-1. Airshed Simulation Program with Input and Output Files




Figure III-2. Information Flow in the SAI Airshed Model System

A. M.E.B. DATA FILE PREPARATION

Of the 14 files input to the Airshed Simulation Program, two are classified as "control files" and are discussed separately. The preparation of the remaining 12 files, which contain meteorological, emissions, and initial and boundary conditions data (referred to in this report as the "M.E.B. files"), is discussed here. The Airshed Simulation Program requires appropriate meteorological, emissions, and initial conditions data for each cell of the region's rectangular grid. In addition, the concentration of each pollutant must be specified at each point on the boundary where the wind is flowing into the region. These data enter the program through the M.E.B. files. Table III-1 lists the 12 files, grouped by type; the 10-character code name as well as the descriptive name is given for each file. Also, the data items contained in each are listed and classified according to the nature of the variability (spatial, temporal, or pollutant) exhibited by each item.

For each file, there is a data preparation program that takes either observations or estimates at specific locations in the region, creates a fully gridded data field, and writes the data to the file in the appropriate format. The 12 M.E.B. data preparation programs are designed to be used together as a unified, user-oriented package. The input formats to all the programs are standardized and reasonably self-documenting. The interpolation methods are intended to accommodate input data of any complexity, from variables for which little or no data are available to those for which there are many observations and well-known interactions. Also, the units of measure are standardized, and a flexible unit conversion scheme is built into the programs.

The M.E.B. data preparation function consists of the following tasks for the user:

Table III-1. M.E.B. Data Files

File Description	Nature of Variability			
	Axes	Vertical Direction	Species	Time
<u>Meteorological Files</u>				
WIND--Wind				
$ u _{\max}^+$, $ v _{\max}^+$				t
Average wind speed along each boundary				t
u-velocity component	x y	z		t
v-velocity component	x y	z		t
DIFFBREAK--Diffusion Break				
Diffusion break	x y			t
REGIONTOP--Top of the Region				
Top of the modeling region	x y			t
*TEMPERATUR--Temperature				
Ground-level temperature	x y			t
METSCALARS--Meteorological Scalars				
Temperature gradient below diffusion break				t
Temperature gradient above diffusion break				t
Exposure index				t
Diurnal photolysis rate constant				t
Concentration of H ₂ O				t
Atmospheric pressure				t
<u>Emissions Files</u>				
EMISSIONS--Ground-Level Emissions				
Ground-level emissions (lumped mobile and nonpoint stationary sources)	x y		sp	t
*PTSOURCE--Point Source Emissions				
Location of source	(x,y)			
Effective plume height	(x,y)			t
Vertical cell index	(x,y)			t
Emissions rate	(x,y)	(z)	sp	t

Table III-1 (Concluded)

File Description	Nature of Variability			
	Axes	Vertical Direction	Species	Time
*ROADWAY--Roadway Microscale Parameters **				
Emissions from motor vehicles	x y		sp	t
Roadway microscale parameter	x y			t
Boundary Files				
*TERRAIN--Terrain Surface Parameters				
Surface roughness	x y			
Vegetation factor	x y			
BOUNDARY--Boundary Definition and Concentrations				
Boundary definition	(x,y)			
Boundary concentrations	(x,y)	z	sp	t
AIRQUALITY--Air Quality				
Initial concentrations	x y	z	sp	(t)s
TOPCONC--Concentrations at the Top of the Region				
Boundary concentrations at the top of the modeling region	x y		sp	t

x = east-west axis of grid.

y = north-south axis of grid.

z = vertical axis of grid.

sp = chemical species.

t = time.

() = data that vary spatially but are not present over the entire grid.

* = files that need not be present for a simulation run.

† u and v refer to the x and y components of the wind velocity, respectively.

s Concentrations must be present at least for the beginning time of the simulation.

** = The roadway microscale procedure is not recommended for usage at this time.

- > Determination of the appropriate files for a given simulation.
- > Detailed examination of the data requirements and optional methods for each file.*
- > Translation of available data into a form acceptable to the model.
- > Selection of the proper interpolation methods.*
- > Establishment of the size and location of the region.
- > Establishment of the vertical distribution of cells within the region.
- > Exercise of the data preparation programs, examination of the results, and modifications of the inputs or algorithms until a reasonable set of data is produced.

The preparation of the M.E.B. data files is certainly the most difficult and time-consuming task associated with using the SAI Airshed Model System. It is also the most important task, and careful, intelligent creation of the input is required to yield the best simulation results.

B. M.E.B. DATA FILE SEGMENTATION

The SAI Airshed Model System has been designed to enable simulation on a rectangular grid of any size and shape; that is, the dimensions of the region are not fixed within the programs, but are specified at run time. If a specified region does not fit within the core limitations of the host computer, that region can be divided into any number of contiguous subrectangles called "segments"; in this case, the size of each segment, rather than the size of the entire region, is limited by the amount of core available. The Airshed Simulation Program processes each segment in turn and information at the interfaces between segments is maintained.

* In some situations, the algorithms embedded in the data preparation programs may not be adequate for the intended model application; in these cases, the user will have to develop and interface the appropriate capability with the SAI Airshed Model System.

To enable simulation processing by segment, the user must create segmented data files from unsegmented files. The M.E.B. file segmentation function consists of the following tasks for the user.

- > Estimation of the size of the largest segment that will fit in core. This size will be determined by the number of species to be simulated, the number of vertical levels, the number of point sources, the program options selected, and the amount of core available on the host computer.
- > Definition of the size and arrangement of segments in the simulation region, and preparation of a segmentation control deck describing that layout.
- > Running the segmentation program on each of the spatially varying M.E.B. files.

C. CONTROL DATA PREPARATION

The Airshed Simulation Program requires two control files: the Chemistry Parameters file (CHEMPARAM), and the Simulation Controls file (SIMCONTROL), each created by its own data preparation program. Table III-2 summarizes the contents of the control files.

For the Chemistry Parameters file, all chemical species to be simulated are named and their properties specified. This list of species, rather than that appearing on any of the other data files, determines which species will be simulated. If there are any reactive species, the reaction rate constants and their other properties (such as the activation energy and reference temperature) are also specified. The user's tasks in making the Chemistry Parameters file are:

- > Preparation of a card deck describing the species and the chemical mechanism to be used.
- > Running the program that creates the Chemistry Parameters file.

TABLE III-2. Airshed Simulation Program Control Files

CHEMPARAM (Chemistry Parameters)

For each species

Name

Reactivity flag

Steady-state flags

Lower and upper concentration bounds

For each reaction

Rate constant

Photolysis and temperature-dependence flags

Activation energy and reference temperature

For each coefficient

Name

Value

SIMCONTROL (Simulation Controls)

Run identifier

Beginning and ending times

File options

Simulation options

Time slice controls

Minimum chemistry time step

Convergence criteria

Averaging interval

Instantaneous concentration output interval

Print options

Note: These files contain no spatially or temporally variable parameters.

The Simulation Controls file includes values for the simulation options, time span, integration controls, and output options, which are the data likely to be changed most frequently. The user's tasks in generating this file are:

- > Preparation of the card deck containing all the simulation control parameters.
- > Running the program that creates the Simulation Controls file.

Although the creation of the Simulation Controls file is described as a separate task among a number of tasks preliminary to running the simulation program, it can be performed just prior to a simulation program run within the same computer job.

D. AIRSHED SIMULATION

The Airshed Simulation Program reads the data files that were created in the three previously described steps and performs the simulation as specified by the control files. Its output consists of files containing instantaneous and time-averaged concentration predictions in segmented form, and a printed trace of the progress of the simulation. Concentration predictions are not printed by the simulation program except in a compact form for debugging purposes only. The selective printing of the simulation results is performed by the display and analysis function. The user's tasks in running the airshed simulation are:

- > Proper specification of all input files to be used.
- > Arranging to save the output files that the program creates.

E. DISPLAY AND ANALYSIS

The final function of the SAI Airshed Model System is the display and analysis of the simulation results. This function has been removed from the Airshed Simulation Program because often, no matter which output

options are selected for a simulation run, different options are needed at a later time. By writing the concentration predictions of all species in all dimensions to output files, one can select any available output mode at any later time.

The current display program capabilities include printout of either instantaneous or average concentration grid maps for selected species at selected vertical levels at selected times. Instantaneous or average vertical concentration profiles can also be printed at user-specified stations. The user's tasks in running the display program are:

- > Proper specification of all input files required (including the desired output file from the Airshed Simulation Program).
- > Preparation of an input deck containing parameters for the selection of times, species, and vertical levels to be printed, and station locations where vertical concentration profiles will be printed.

In addition, the design of the display program provides for the inclusion of additional analysis capabilities without extensive modification of the program. Specifically, the structure permits the comparison of two concentration data files. The two data files could be the output from two simulation runs (comparing different control strategies, for example), or one file could be simulation predictions and the other a gridded representation of station observation data.

IV DEFINITION OF SYSTEM CONCEPTS

This chapter discusses several important aspects of the Airshed Model System that must be understood before the model can be used. The concepts explained here include the subdivision of the modeling region into an array of three-dimensional grid cells, the pollutants treated by the model, and the handling of the time variability of various parameters in the model. Also, the segmentation of the entire modeling region into one or more sub-regions for performing the numerical integration process is examined. Finally, the treatment of time increments used in the Airshed Simulation Program is detailed.

A. THE MODELING REGION (GRID)

The modeling region is a three-dimensional volume subdivided into an array of three-dimensional grid cells. This section first describes the projection of this array onto the x-y, or horizontal, plane and then the method of determining the cell thicknesses in the z, or vertical, direction. Complete instructions for defining the location, size, shape, and resolution of the modeling region are given in Section VI.B.2, which discusses the REGION packet.

1. Horizontal Distribution of Grid Cells

Three pairs of values (which are further discussed below) define the horizontal modeling region:

- > The x- and y-coordinates, in meters, of its origin (the lower left-hand corner point) with respect to a reference origin.

- > The grid spacing (cell size), in meters, along each axis.
- > The number of grid cells along each axis.

In the horizontal plane, the region consists of a rectangular grid area with the x-axis parallel to the equator (east-west) and the y-axis perpendicular to the equator (north-south).^{*} This area is divided into rectangular grid cells of equal size. Although the spacing of cells may be different for one axis than for the other, yielding nonsquare cells, it must be uniform along each axis.

The region specified must include one cell at each boundary of the simulated area. Thus, if the area to be simulated is a 5 x 10 grid, the region specified must be at least 7 x 12, as shown in Figure IV-1. Also, portions of the inner rectangular area can be omitted from the simulation by defining the boundaries appropriately. Figure IV-2 shows a possible boundary for the Los Angeles region for which the prediction of concentrations in the areas over the Pacific Ocean and the San Gabriel Mountains would not be of interest. Boundaries of the simulated area are input to the simulation through the BOUNDARY file (see Section VI.A.6, which describes the method for defining the horizontal boundaries of the region).

The method for describing locations within the specified region has been standardized in the current version of the SAI Airshed Model. First, a "reference origin"--a point on the map defined by its Universal Transverse Mercator (UTM) coordinates--is designated. All other points in the region, including measuring stations, point sources, and the origin of the modeling region itself, are then described in terms of their distances in the x- and y-directions from the reference origin. The reference origin may coincide with the origin of the region, it may lie within the grid, or it may be completely outside the grid. Thus, the x- and y-coordinates of

^{*} This orientation of the horizontal grid is used for reference throughout the system. However, some other more useful or convenient grid orientation can be used, provided that point locations and wind vector components are carefully defined.




Figure IV-1. Example of a Modeling Region That Includes the Required Boundary Cells




Figure IV-2. 54 Mile by 54 Mile Modeling Region of Los Angeles Basin. Each grid square is 2 miles by 2 miles.

any point with respect to the reference origin may be positive or negative. In Figure IV-3, the reference origin is outside the modeling region. The x-coordinate of the region origin is positive and the y-coordinate is negative. The point sources and measuring stations appear both within the region and outside it. Using this method for locating points, the user can change the location, size, shape, or resolution of the modeling region without changing the coordinates of any of the other input data.




Figure IV-3. Example of the Location of a Modeling Region with Respect to a Reference Origin

It is sometimes necessary to describe the region in terms of its grid cells, generally when dealing with a whole cell (containing spatially averaged values) rather than a single point. Grid cell references instead of point locations are used to designate subregions and regional segments for the data preparation programs and to label printouts of grid values. Grid cells are numbered by their indices in the x- and y-directions, with Cell (1,1) referring to the cell in the lower left (southwest) corner of the grid, as illustrated in Figure IV-4.




Figure IV-4. Conventional Method for Numbering Grid Cells

2. Vertical Distribution of Grid Cells

Although the modeling region in the horizontal plane consists of rectangular cells of equal size, cells in the vertical direction are distributed differently. The vertical distribution of cells is described using the following definitions:


- > The diffusion break is the height above ground at which the diffusion characteristics (or eddy diffusivity) undergo a significant change. For example, when a mixed layer is capped by a stable inversion layer, the diffusion break occurs at the base of the inversion. If a ground-based stable layer is present, the diffusion break then occurs at the top of the inversion layer. Gridded values of the diffusion break are specified as a function of x, y, and time, and are input via the file DIFFBREAK.
- > The top of the region is the height above ground of the top of the simulation region. Gridded values are specified as a function of x, y, and time, and are contained in the file REGIONTOP. The top of the region may be located below, above, or at the same height as the diffusion break.
- > The space between the ground and the top of the region is divided into three layers:
 - The surface layer is one cell deep, and all surface layer cells maintain a constant height over space and time. Microscale calculations are performed in this layer using concentration predictions from the corresponding cell immediately above each surface layer cell. Ground-level emissions, surface deposition, and the reaction products of NO emissions from roadways and ambient ozone are combined to produce a flux of each pollutant into the cell above the surface layer cell. If the surface layer height is set to

zero, there is no surface layer and the microscale calculations are bypassed. Since the microscale prediction capabilities have not been fully tested, it is recommended that the surface layer height be set to zero.


- The lower layer, which must be at least one cell deep, includes the cells between the top of the surface layer (or those at ground level, if there is no surface layer) and the diffusion break.
- The upper layer includes the cells between the diffusion break and the top of the region. Calculations in this layer can be omitted by setting its number of cells to zero.

Figure IV-5 illustrates various "layer" configurations that can be employed in the model. Figure IV-5(a) shows surface, lower, and upper layers. Figure IV-5(b) omits the surface layer. Figure IV-5(c) contains surface and lower layers, but no upper layer; note that, in this case, the top of the region actually modeled is the diffusion break, not the region top parameter input. The user must specify the number of cells and the minimum cell height in the lower and upper layers. Figure IV-5(d) shows the region described in Figure IV-5(a) with two cells in the lower layer and two cells in the upper layer. The number of levels in the region, i.e., the number of cells in the vertical dimension of the concentration matrix, is equal to the number of cells in the lower layer plus the number of cells in the upper layer plus one, if there is a surface layer. The total number of levels is used to calculate the segment size limitation. For example, five levels are described in Figure IV-5(d).


If either the lower or upper layer cells (as defined above) are smaller than the minimum cell height specified, enough space is borrowed from the adjacent layer to make up that height. Such a situation occurs in cases in which the diffusion break is very low or it is higher than the top of the region. Figure IV-5(e) illustrates all possible vertical cell distributions for a region that embodies a surface layer, two cells in the lower layer, and two cells in the upper layer. The top of the region is assumed to be high enough to include the total number of cells




(a) Configuration of a Region into Surface, Lower, and Upper Layers



(b) Configuration of a Region into Lower and Upper Layers




(c) Configuration of a Region into Surface and Lower Layers



(d) The Region Described in Figure IV-5(a) Sectioned into Five Levels

Figure IV-5. Various Vertical Cell Distributions That Can Be Employed in the SAI Airshed Model



(e) All Possibilities for Vertical Cell Distribution of a Region That Contains a Surface Layer and Two Cells Each in the Upper and Lower Layers

G = Ground.

D = Diffusion break.

S = Height of the surface layer.

T = Top of the region.

===== Surface layer.

////// Lower layer.

\\\\\\\\ Upper layer.

Figure IV-5 (Concluded)

at the minimum height. For cases in which the minimum cell height is used to create a pseudo-lower layer or a pseudo-upper layer, the simulation program still uses the actual height of a cell with respect to the diffusion break rather than the cell number to calculate the vertical diffusivity. Instructions for specifying the vertical distribution of cells in the region are given in Section VI.B.2, which discusses the REGION packet.

B. CHEMICAL SPECIES

Each cell in the three-dimensional region previously described will carry a concentration value for each chemical species simulated. The Chemistry Parameters (CHEMPARAM) file indicates the species to be considered and their properties (Section IX.A). Initial concentrations of each pollutant are provided by the Air Quality (AIRQUALITY) file. The vertical column of concentrations at each boundary cell of the horizontal plane are provided by the Boundary (BOUNDARY) file. Boundary concentrations for each species at the top of the region are on the Top Concentrations (TOPCONC) file. Instructions for creating these three files are given in Chapter VII.


C. TIME

Concentrations of each species in each cell are moved ahead from a beginning time to an ending time in increments called "time slices". The beginning time, ending time, and the size of time slice are specified on the Simulation Controls (SIMCONTROL) file (Section IX.B). The time intervals for concentration averaging and for the output of the four-dimensional concentration fields are also specified on this file. A further discussion of the treatment of time is given in Section E of this chapter.


D. SEGMENTATION

The segmentation process involves dividing the user-defined modeling region into one or more rectangular segments in the horizontal plane, thereby allowing the Airshed Simulation Program to retain in core the data for the entire area it is processing, and providing flexibility as to the choice of the number and size of grid cells. The maximum horizontal dimensions for each segment are determined by the amount of core storage available on a particular computer, the number of vertical levels and chemical species to be simulated, and the simulation options to be used. Although the data arrays for all segments are maintained in secondary storage, all of the data arrays for a single segment reside in core during the period that the segment is being processed.


Each segment must be constructed as if it were an independent region being simulated, with its own set of input data and boundary conditions. To provide adequate information at the segment interfaces, adjacent segments must be constructed with a four cell overlap, as illustrated in Figures IV-6(a) through IV-6(c). Figure IV-6(a) shows a 7 x 12 cell region, consisting of a 5 x 10 area to be simulated plus a one-cell boundary on all edges. If the data covering this area do not fit in core, the area can be divided into two segments as shown in Figure IV-6(b). However, since each segment must include two boundary cells from the adjacent segment, the length of each segment is increased by two cells at the interface boundary. Figure IV-6(c) shows the layout of the original region, segmented into two 7 x 8 regions, each with a 5 x 5 simulation area. The two southernmost simulated rows of Segment 1 are the north boundary cells for Segment 2, and the two northernmost simulated rows of Segment 2 are the south boundary cells of Segment 1. Instructions for calculating maximum segment size and defining the regional segment layout are given in Chapter VIII.



(a) A 5 x 10 Cell Region with a One-Cell Boundary on All Edges



(b) Division of the 5 x 10 Cell Region into Two 5 x 5 Cell Segments



(c) Layout of a Region Showing the Interface of Boundary Cells for Two Segments

Figure IV-6. Example of the Segmentation of a Region

E. TIME SLICES AND INTEGRATION TIME STEPS

The "time slice" is the amount of simulation time during which the integration for any segment will proceed without updating the boundary conditions or any other time-varying data. At the beginning of a time slice, new data from the files are read if necessary, and the concentrations at the segment interfaces are updated (Chapter VII of the Systems Manual details the method of maintaining segment interface concentrations). Then, each segment in turn is entirely processed for one time slice. Because all data for a given segment are in core at once, this scheme reduces the number of I/O transfers.

To describe how the time slice is determined, another time increment--the integration time step--must be defined. The integration time step is the increment over which the numerical integration of the governing equations in a segment actually takes place. The numerical integration procedure consists of four sequential steps:

- > Horizontal advection and diffusion (Steps 1 and 2).
- > Vertical advection and diffusion, including the treatment of emissions, surface deposition, and the surface layer microscale effects (Step 3).
- > Chemistry (Step 4).

The maximum time step allowable for the horizontal transport calculations in a segment is determined by the simulation program on the basis of the maximum wind velocity component over the segment and by the horizontal grid cell size:

$$\Delta t_{\max} = \min \left(\frac{.5\Delta x}{|u|_{\max}}, \frac{.5\Delta y}{|v|_{\max}} \right),$$

where

$\Delta t_{\max}$ = maximum allowable time step for the segment,
 Δx = size of the grid cell in the x-direction,
 Δy = size of the grid cell in the y-direction,
 $|u|_{\max}$ = maximum absolute value of the wind velocity
 component in the x-direction over the entire
 segment for all vertical levels,
 $|v|_{\max}$ = maximum absolute value of the wind velocity
 component in the y-direction over the entire
 segment for all vertical levels.

The size of the time slice is determined in the following way:

- > First, the time slice is set to the maximum size input by the user on the SIMCONTROL file.
- > If necessary, the time slice is reduced to avoid exceeding the time interval for which the data on any input file apply.
- > Also, if necessary, it is further reduced to avoid exceeding the next output time (instantaneous or average).
- > Finally, it is reduced if necessary on the basis of the smallest maximum time step that is allowed in any segment.*

* The user sets the maximum number of time steps that can be taken in any slice. Thus, the time slice used can be no larger than

$$n(\Delta t_{\max})_{\min} ,$$

where n = maximum number of steps in a slice (input on the SIMCONTROL file), and $(\Delta t_{\max})_{\min}$ = the smallest maximum allowable time step calculated for any segment. In general, if n is set large, the time slice used will be limited by the maximum time slice input. If n is small, the time slice used will be limited by the smallest allowable time step for any segment.

After the size of the time slice has been determined, the overall integration time step to be used for each segment is calculated. If the maximum time step for the segment is shorter than the calculated time slice, the slice is divided into the smallest number of equal time steps such that each is less than or equal to the maximum time step. Thus, if the time slice is 0.25 hour, and the maximum time step is 0.10 hour, the time slice is divided into three equal time steps of 0.08 1/3 hours each. If the maximum time step is greater than the time slice, the overall time step used will be equal to the time slice.

The overall time step described above (limited by the maximum wind speed and time slice size) may still be too large to allow completion of the chemistry step (Step 4). If the time step used for advection is too large to allow convergence in the chemistry calculations for any given cell, the time step is cut in half only for the chemistry step for that cell. This "chemistry time step" is successively halved until the chemistry calculations converge, and a sufficient number of these steps are taken for that cell to fill out the overall time step. If the chemistry time step for any cell must be decreased to less than the minimum chemistry time step specified by the user (on SIMCONTROL), the simulation will stop and values of all arrays will be printed in the neighborhood of the cell.

V JOB CONTROL SPECIFICATIONS

This manual does not present specific job control examples because they vary greatly depending not only on the computer system used but also on the intentions and the style of the individual user. Instead, Chapters VII through XI contain diagrams illustrating the flow of information (card decks, binary files, and printed output) among the various computer programs. This chapter discusses a typical information flow diagram, suggests a worksheet for keeping track of programs, and provides a summary of file characteristics to aid in the preparation of job control statements.

A. INFORMATION FLOW DIAGRAMS

Each information flow diagram provides the following details, which are specified for each program being described:

- > The names of the files associated with the program
- > The FORTRAN unit number assigned to each file
- > The program name
- > Any necessary subroutine libraries
- > Any optional flow patterns.

Figure V-1 is an example of such a diagram. The input is a card deck read on Unit 5 (the standard read unit), and a binary file named BINARY, read on Unit 3. An optional input file--BIN2--if present, is read on Unit 2. The program to be executed--PROGM--requires subroutines that are stored in SUBLIB. The output from the program is another binary file called BINOUT, written on Unit 4, and a printout of results on Unit 6, the standard print unit.




Figure V-1. Example of an Information Flow Diagram for Use in Job Control

B. PROGRAM WORKSHEET

This manual assumes that the programs have already been compiled and that they exist in an executable form. Exhibit V-1(a) is a worksheet that can be used to locate and identify each program in the system; Exhibit V-1(b) shows that worksheet filled out for use on the Lawrence Berkeley Laboratory (LBL) system. To use a different system, users who implement the programs must provide the information necessary to run them, including link/loading information, storage requirements, and the location of predefined procedures.

C. FILE CHARACTERISTICS

The 17 data files associated with the SAI Airshed Model are described in detail in Chapter IX of the Systems Manual. This section simply tabulates the essential features of each file to aid in the preparation of job control statements.

With the exception of the card-image input files and the output print files, all files in the SAI Airshed Model are binary (unformatted) files of variable record lengths. Each file contains one to four standard header records followed by data records specific to the particular file. The following terms are used to express the number of records on a file and the maximum record length:

- sg = number of segments,
- sp = number of species,
- $x_{\max}$ = largest number of cells in the x or y dimension
for any segment,
- $xy_{\max}$ = largest number of grid cells in the horizontal
plane for any segment,
- z = number of vertical levels,
- $pt_{\max}$ = largest number of point sources in any segment.

Program	Source	Object	Libraries	Scratch Vector	Size	Other Information
AIRQUL						
BNDARY						
DIFFBK						
EMISSN						
METSCL						
PTSRCE						
REGNTP						
ROADWY						
TMPRTR						
TERAIN						
TOPCON						
WINDSET						
UTILITY						
FILUTIL						
SEGDEF						
CPREP						
SPREP						
AIRSIM						
DISPLAY						

(a) Format

Exhibit V-1. Sample SAI Airshed Model Program Worksheet for Use in Job Control

Program	Source	Object	Libraries	Scratch Vector	Size	Other Information
AIRQUL	AIRQULU	AIRQUAL	C, F (~~~~~)	14,500	170,000 ₈	
BNDARY	BNDARYU	BOUNDARY		17,000		
DIFFBK	DIFFBKU	DIFFBK		26,500		
EMISSN	EMISSNU	EMISSN		20,000		
METSCL	METSCLU	METSCL		40,000		
PTSRCE	PTSRCEU	PSOURCE		23,500		
REGNTP	REGNTPU	REGNTP		22,500		
ROADWY	ROADWYU	ROADWAY		20,000		
TMPRTU	TMPRTU	TEMPRTUR		26,500		
TERRAIN	TERRAINU	TERRAIN		27,000		
TOPCON	TOPCONU	TOPCONC		20,000		
WINDSET	WINDSETU	WINDSET		11,900		
UTILITY	UTILITYU	UTILITY		—	—	
FILUTIL	FILUTLU	FILUTIL		—	—	
SEGDEF	SEGTOFU	SEGTOEF		—	—	
CPREP	JCPREP	JCPREP	—	—	32,000 ₈	Overlay form -- requires AUTOLAY control deck
SPREP	JSPREP	JSPRLPR	—	—	27,000 ₈	
AIRSIM	JSIMU	JSIMR	—	30,000	170,000 ₈	
DISPLAY	DISPLAU		—	—	134,000 ₈	

(b) Worksheet Filled Out for Use on the LBL System

Exhibit V-1 (Concluded)

Table V-1 shows the number of words in each of the four header records. Table V-2 lists the 17 files, indicates the number of records appearing on each one, and gives the maximum length of a nonheader record. If this length is smaller for the largest segment than that of the longest header record, then the longest header determines the maximum record length for the whole file. In addition to the 17 data files shown in Table V-2, some temporary scratch files might be used by a particular program, depending on the implementation and the size of the region to be modeled. Chapter IX of the Systems Manual explicitly defines these files.

Table V-1. Header Record Lengths for the
SAI Airshed Model Data Files

<u>Record Name</u>	<u>Length (decimal words)</u>
File description header record	76
Region description header record	15
Segment description header record	4 sg
Species description header record	10 sp

Table V-2. Characteristics of the SAI Airshed Model Data Files

Name of File	Header Records				Number of Time-Invariant Records	Number of Records per time Interval	Maximum Data Record Length (decimal words)
	File	Region	Segment	Species			
AIRQUALITY	✓	✓	✓	✓	--	1 + sg*sp*z	11 + xy _{max}
BOUNDARY	✓	✓	✓	✓	4sg	1 + 4*sg*sp	12 + x _{max} *z
DIFFBREAK	✓	✓	✓		--	1 + sg	11 + xy _{max}
EMISSIONS	✓	✓	✓	✓	--	1 + sg*sp	11 + xy _{max}
METSCALARS	✓	✓			--	2	66
PTSOURCE	✓	✓	✓	✓	2sg	1 + sg*(2 + sp)	6*pt 11 + pt
REGIONTOP	✓	✓	✓		--	1 + sg	11 + xy _{max}
ROADWAY						1 + sg*(1 + sp)	11 + xy _{max}
TEMPERATUR	✓	✓	✓		--	1 + sg	11 + xy _{max}
TERRAIN	✓	✓	✓		2sg	--	11 + xy _{max}
TOPCONC	✓	✓	✓	✓	--	1 + sg*sp	11 + xy _{max}
WIND	✓	✓	✓		--	1 + 2sg*z	11 + xy _{max}
CHEMPARAM	✓			✓	2-4	--	62 18 sp 5*reactions 11*coefficients
SIMCONTROL	✓				1	--	36
AVERAGE	✓	✓	✓	✓	--	1 + sg*sp*z	11 + xy _{max}
INSTANT	✓	✓	✓	✓	--	1 + sg*sp*z	11 + xy _{max}
VARIATION	✓	✓	✓	✓	--	1 + sg*sp	11 + xy _{max}

VI PACKETS USED IN CREATING THE M.E.B. FILES

As many as 12 different data preparation programs are required for constructing the M.E.B. files--one program for each file. This chapter discusses the data modules--packets--that are used by the data preparation programs. All input data are divided into packets; each packet contains a specific type of information necessary to some aspect of data preparation. The following sections first present general rules that apply to the preparation of all the packets, and then explicit rules and formats for each one. Chapter VII contains rules for the preparation of the data files using these packets, and examples of the output from the programs.

A. ELEMENTS OF PACKET CONSTRUCTION

The ordering and internal structure of the data packets have been designed for consistency of formats, flexibility of use, and ease of visual analysis. Each packet begins with a header card identifying the packet and ends with a termination/trailer card that reads END or ENDTIME. The packet names, their classifications, and their proper ordering are shown in Table VI-1.

Of the time-invariant data, the CONTROL and REGION packets are mandatory, and they are entered first and second, respectively, in the input deck. The CONTROL packet defines input and output options and maximum variable counters used by the program to set internal array dimensions. The REGION packet defines the location, size, and resolution of the modeling region. If present, the UNITS packet follows the REGION packet. The UNITS packet names user-defined variables and specifies unit conversions.

Table VI-1. Packets Used by the SAI Airshed Model
Data Preparation Programs

Time-Invariant Packets

CONTROL
REGION
UNITS
STATIONS
POINT SOURCES
BOUNDARIES

Time-Varying Packets

TIME INTERVAL
SUBREGIONS
METHOD
VERTICAL METHOD
CONSTANTS
GRID VALUES
STATION READINGS
EMISSIONS VALUES
EMISSIONS FACTORS
BOUNDARY READINGS
SCALARS
VERTICAL PROFILES

The remaining time-invariant packets, STATIONS, BOUNDARIES, and POINT SOURCES, which define fixed locations in the region, are optional depending on the file being created and the method used.

The TIME INTERVAL packets appear next. Each TIME INTERVAL packet contains the other time-varying packets to be used during the interval specified and ends with an ENDTIME card. The time intervals used must cover the time span specified in CONTROL with no gaps or overlaps. The time-varying packets included within each TIME INTERVAL packet define the data preparation methods to be used and supply the time-varying data.

Different interpolation methods can be used for different variables in different areas of the region. The SUBREGION packet defines the areas, and the METHOD packet defines the method to be used for each variable in each subregion. The VERTICAL METHOD packet describes the method to be used for calculating values for variables that vary vertically. Although any of these packets can be changed in subsequent time intervals, for most runs the subregions and methods supplied in the first time interval will be used for the entire duration of the run. The other time-varying packets define the values for the input variables. The particular packets used for any given run depend on the file being created and the methods selected. After the first TIME INTERVAL packet has defined the information to be written on the file, this information will persist into succeeding time intervals as described in Section A.3 of this chapter.

1. Rules for Card Format

Each data card is divided into two sections: Columns 1 to 60 contain input data; Columns 61 to 80 are reserved for any desired user identification information. All input fields are 10 columns wide except packet headers and file identifiers, which can occupy the entire width available for input, i.e., Columns 1 to 60.

Integers are input in Format I10 and must be right justified. Floating point variables are input as F10.0. Alphanumeric information can occupy any of the columns available for input of that data as long as it is correctly ordered and no extraneous or erroneous symbols are included. Thus, for example, `_C_ON__TROL___` would be recognized as "CONTROL"; `CNOTROL` and `CONTROLZ` would not. The 60-column file identifier is not subject to validation and, therefore, can contain any information the user desires.

2. The Reserved Word ALL

The word ALL is a special designation that is reserved to enable the user to specify information globally; therefore, it should not be used to indicate a specific alphanumeric entity, such as a variable, subregion, station, point source, or boundary name. When used in the input field usually associated with an alphanumeric name, ALL means that the subsequent information applies to all the names that could occupy that input field. ALL can generally be used wherever it makes sense. The following examples illustrate both the proper and improper usages of this command:

- > Proper usages of ALL.
 - A card in the METHOD packet:

```
|ALL _____|__WX_____|GRIDVALUE|    .
```

This card specifies that in all subregions the values of the variable WX will be input by the GRID VALUE method. If ALL also occurred in place of WX, e.g.,

```
|ALL _____|ALL _____|GRIDVALUE|    ,
```

the values of all input variables in all subregions would also be input by the GRID VALUE method.

- A card in the STATION READINGS packet:

```
|WEST_____|_ALL_____|-9.0_____|    .
```

This information indicates that the values of all variables reported by Station WEST are to be set to -9.0 (a value that implies data are missing).

- > Improper usage of ALL. A card in the UNITS packet:

```
|ALL_____|KG/D_____|a          |b          |c          |    ,
```

where a, b, and c are numbers. This card says that all input variables will have values input in kg/day, to which the conversion parameters a and b and the molecular weight c are to be applied. It is improper because different species have different molecular weights.

3. Persistence of Data

As previously mentioned, the information provided in any TIME INTERVAL packet remains in effect until it is replaced. This persistence rule applies to all time-varying data, including subregion and method definitions and input values. For example, METHODS for computing each variable in each subregion need be specified only in the first TIME INTERVAL. They can be changed in a later TIME INTERVAL if desired, but in most cases only one definition is required.

If no data are available for a given station over a certain time interval, the user can omit that station in that time interval, and the data previously input will be used. However, if the data are actually to be treated as missing, the station must be included and must be assigned values that are interpreted by the program as "missing data." In general,

missing integer and real values are represented by -9 and -9.0, respectively. Although the use of this device can save considerable duplication of effort, it places on the user the burden of ensuring that all changes in status are specified.

4. Units of Measure

The Airshed Simulation Program assumes a standard and consistent set of units for all of its computations, and the files input to the program must contain data expressed in these "internal" units. The data input to the file preparation programs, however, may be in other than internal units. To accommodate such data, the programs contain a set of standard alternative unit designations for use in directing automatic conversion of input units to internal units. Additionally, the user can specify the use of nonstandard conversion factors. Section B.3 of this chapter discusses the internal units for each variable, alternative units and their associated conversion factors, and the method for specifying non-standard unit conversions.

5. Variables

Each program has a set of output variables. For files that vary by species, the output variables are the species names listed in the CONTROL packet. For files that do not vary by species, the output variables are names built into the corresponding data preparation program; the implicit output variable names for each file are presented in the appropriate section of Chapter VII. Values input to the program may be for the output variables themselves, or they may be for variables that will be acted on in some way to produce the output variables. For example, concentrations of total hydrocarbon may be input to the AIRQUALITY program, whereas its output consists of concentrations in each of several carbon-bond classes.

Whenever the input variables are different from the output species or implicit output variables, they are referred to as "user-defined variables," and must be named in the UNITS packet. Designation of the user-defined variables in this way allows the program to allocate space for them internally.

6. Methods

This section explains the methods for calculating the ground-level values of each variable within each subregion. (Section B.8 of this chapter gives instructions on dividing the modeling region into subregions.) These methods are designated in the METHOD packet, which is discussed in Section B.9 of this chapter. The first eight methods (a through h) can be used by any of several data preparation programs; the remaining methods (i through r) are each specific to a single program.

a. CONSTANT

A single value is to be used for this variable in every ground-level cell in this subregion. The value must be defined in a CONSTANTS packet and the program will convert it to internal units if necessary. The CONSTANT method requires no other parameters.

b. GRID VALUE

A value for this variable will be input for each ground-level grid cell in the subregion. The values will be defined in a GRID VALUES packet and the program will convert them to internal units if necessary. The GRID VALUE method requires no other parameters.

c. STATINTERP (Station Interpolation)

The value for this variable at each ground-level grid cell in the subregion is calculated by the program as the weighted average of values at selected measuring stations. Station locations will be defined in a STATIONS packet; values for the variable at each station will be input in the STATION READINGS packet and the program will convert them to internal units if necessary. To calculate the value at a given grid cell, the program weights each station value by the inverse of the distance of the station from the center of the cell. The following four parameters must be specified to control the selection of the measuring stations to be included in the average:

- > EXTENT--This number determines the acceptability of a station on the basis of the subregion it is in. If EXTENT = 0.0, a station within the radius of influence will be included in the average regardless of the subregion it occupies. If EXTENT $\neq$ 0.0, only stations within the same subregion will be accepted. If this number is omitted, it will be assumed to be zero.
- > INITRADIUS--initial radius of influence. All stations within this distance of the cell for which values are being calculated will be used. This number is assumed to be in grid units. If this number is set very large, all stations will be included. Omission of this number constitutes an error.
- > RADIUSINCR--If no measuring stations with values are encountered within the initial radius of influence, the radius will be incremented by this amount until at least one station is included. This number is assumed to be

in grid units. When this number is small, the values generated will be distributed more smoothly over the region, but the cost in computing time could be great. Conversely, when this number is large, computing time might be reduced, but at the expense of irregularities in the computed grid values. If this number is omitted, only the initial radius will be used, and the failure to find a valid station constitutes an error.

- > MAXRADIUS--maximum radius of influence. This number is assumed to be in grid units. Failure to find valid station data within this radius constitutes an error. If this number is omitted, the entire modeling region may be used.

d. POISSON

The value for this variable at each ground level grid cell in the sub-region is calculated by the program using the Poisson smoothing method [see Killus et al. (1977), Chapter IV, pp. 135-142]. Values for the variable at selected measuring stations must be input in the STATION READINGS packet. The POISSON method requires three parameters:

- > MAXITER--the maximum number of iterations; the suggested number is ≤ 200 .
- > ERRORTOL--error tolerance. This parameter is expressed in internal units of the variable; the suggested value = $0.01 * \text{expected value}$.
- > OMEGA--weighting factor to aid convergence; the suggested value = 1.4.

e. SPLIT/COMB (Split or Combine)

Any variable to be output can be formed by splitting or combining input variables (typically, these are species):

$$\text{var}_{\text{out}} = \sum_{i=1}^N \text{var}_i * \text{factor}_i \quad .$$

This method requires N parameter cards; on Card i the parameter name is the name of variable_i and the value is factor_i. If the parameter (variable) name is left blank, the corresponding factor is treated as a constant (i.e., var_i = 1). All values for input variables will already have been converted to internal units when this computation is done, so the factors specified should not include unit conversions.

f. E-W INTERP (East-West Interpolation)

For each row of grid cells within a subregion, a linear interpolation will be carried out between values in the bordering cells in the east and west edges of the row. This subregion must not lie on an edge (i.e., it must be bounded on east and west by other subregions) and values for the bordering subregions must be calculated by a noninterpolative method. The E-W INTERP method requires no other parameters.

g. N-S INTERP (North-South Interpolation)

For each column of grid cells within a subregion, a linear interpolation will be carried out between values in the bordering cells on the north and south edges of the column. This subregion must not lie on an edge (i.e., it must be bounded on north and south by other subregions), and values for the bordering subregions must be calculated by a noninterpolative method. The N-S INTERP method requires no other parameters.

h. USER (User-Supplied Algorithm)

Each data preparation program is designed to call a user-supplied subroutine for any variable for which the method USER has been selected. All available data are passed to the subroutine as arguments. At present, all user subroutines are dummies; as new methods are developed, they can be inserted in user subroutines, and parameter values can be read and passed as for any of the standard methods.

i. BOUNDVALUE

This method is used only for creation of the BOUNDARY file. It specifies that concentration values will be input for each boundary line segment through the BOUNDARY READINGS packet. BOUNDVALUE requires no parameters.

The following two methods are used only for creating the PTSOURCE file.

j. EMVALUES

This method name indicates that point source emissions will be entered for this species for this point source type (the "subregion" field) by means of the EMISSIONS VALUES packet. EMVALUES requires no parameters.

k. EMFACTORS

This method name indicates that for this species and point source type, the emissions values and flow rate previously entered will be modified by factors supplied by means of an EMISSIONS FACTORS packet. This method requires no parameters.

The following two methods are used only for the REGIONTOP file. Both require that the DIFFBREAK file be input and that the vertical definition of the region be included in the REGION packet. Both use NZUPPR (the number of cells in the upper layer) as defined in the REGION packet.

l. FIXDHEIGHT

The REGIONTOP is defined such that there will be NZUPPR cells of a fixed height above the diffusion break, subject to the maximum height indicated on the method card. REGIONTOP can be defined as being equal to the diffusion break, subject to the maximum height indicated on the method card, by specifying NZUPPR = 0. This method requires one parameter: UPCELLHT-- the cell height in the upper layer (above the diffusion break). If NZUPPR > 0, this number must be specified and must be greater than the minimum height of upper layer cells.

m. SAMEHEIGHT

The REGIONTOP is defined such that there will be NZUPPR cells above the diffusion break of the same height as the NZLOWR cells between the top of the surface layer and the diffusion break, subject to the maximum height indicated on the method card. No other parameters are required.

The following two methods are used only for the TOPCONC file. Both require that vertical concentration profiles be input by means of a VERTICAL PROFILES packet; i.e., they require that for each species in each subregion, a number of height-concentration pairs be provided. Both methods require the REGIONTOP file. The method RELTOPCONC requires the DIFFBREAK file as well.

n. ABSTOPCONC

The concentration at the top of the region will be calculated from the profile based on the height of the top of the region. The vertical profile

input describes the vertical distribution of concentration values. The height of the top of the region above ground is compared with the height of each profile point to determine the value to be used. The profile is input as a set of pairs (H_i, F_i) , where H is height and F is some profile value. Since it is assumed that the pair (H_1, F_1) corresponds to ground level, the following transformation is applied to all heights:

$$H'_i = H_i - H_1 \quad .$$

The profile is thus considered to be the set of pairs (H'_i, F_i) ordered by increasing H' .

The profile is used for a particular grid cell in the following way: For a cell at a given (x,y) location on the grid, find the height T of the top of the region. Then, the concentration, C , at the top is defined as follows:

$$C = \begin{cases} F_n, & \text{if } T > H'_n \quad ; \\ F_{i-1} + \frac{T - H'_{i-1}}{H'_i - H'_{i-1}}(F_i - F_{i-1}), & \text{if } H'_{i-1} \leq T \leq H'_i \quad . \end{cases}$$

o. RELTOPCONC

The concentration at the top of the region will be calculated from the profile based on the height of the top of the region relative to the height of the diffusion break. The vertical profile input describes the vertical distribution of concentration values. The height of the top of the region relative to the height of the diffusion break is compared to the height of each profile point relative to its diffusion break to determine the value to be used. The profile is input as a set of pairs (H_i, F_i) , where H is height and F is some profile value. Since it is assumed that the pair (H_1, F_1) corresponds to ground level, the following transformation is applied to all pairs: For all i ,

$$H'_i = (H_i - H_1)/DB_p \quad ,$$

where DB_p = diffusion break at the profile location. The profile is thus considered to be the set of pairs (H'_i, F_i) ordered by increasing H' .

The profile is used for a particular grid cell in the following way. For a cell at a given (x,y) location on the grid, find the height of the top of the region. Then, convert the absolute height T to the height of the top relative to the diffusion break at that location:

$$T' = \frac{T}{DB} \quad .$$

Then, the concentration, C , at the top is defined as follows:

$$C = \begin{cases} F_n & , \text{ if } T' > H'_i & ; \\ F_{i-1} + \frac{T' - H'_{i-1}}{H'_i - H'_{i-1}} (F_i - F_{i-1}) & , \text{ if } H'_{i-1} \leq T' \leq H'_i & . \end{cases}$$

The following three methods are used only in the WIND program. In this program there are four implicit variables: SPEED and DIRECTION, the variables ordinarily input to the program; and WINDX and WINDY, the x- and y-components of the wind that are written to the WIND file. Further discussion of the specification of these variables appears in Chapter VII.

p. DIVERGENCE

The DIVERGENCE method uses the algorithms developed by Anderson and Durran and reported in Killus et al. (1977) to calculate a three-dimensional wind field. The method is unique in that it calculates the values for the two output variables (WINDX and WINDY) simultaneously and computes the values for all cells at all levels. DIVERGENCE is, therefore, also a vertical method and must be explicitly named in the VERTICAL METHOD packet

as well. Use of this method requires that station readings and vertical profiles for SPEED and DIRECTION be specified and that the ground-level temperature field (TEMPERATUR data file) be available. Since this method internally performs a Poisson interpolation, it requires the same three parameters as the POISSON method (previously discussed). These parameters should be specified for the first variable (WINDX or WINDY) that appears using the DIVERGENCE method. The other variable (WINDY or WINDX) should also use the DIVERGENCE method, but no parameter need be included. The vertical method for both of these variables should also be DIVERGENCE. This method cannot be specified for SPEED or DIRECTION. The DIVERGENCE method requires that the files DIFFBREAK, REGIONTOP, and TEMPERATUR be attached to the run.

The methods VECTORIZE and POLARIZE are used only to calculate the three-dimensional arrays. Necessary conversion of station values and profile values are handled automatically.

q. POLARIZE

This method can only be specified for the variables SPEED and DIRECTION. The values of SPEED and DIRECTION will be calculated from the vector components WINDX and WINDY. This method should be used if printouts of gridded SPEED and DIRECTION are desired. Some method other than VECTORIZE (discussed next) should be specified for WINDX and WINDY if POLARIZE is used. No parameters are required.

r. VECTORIZE

This method is used to convert SPEED and DIRECTION to WINDX and WINDY. This method should be used to calculate the output variables WINDX and WINDY if gridded SPEED and DIRECTION values are given or calculated by the program. POLARIZE should not be the method used for SPEED and DIRECTION if VECTORIZE is used for WINDX and WINDY.

7. Vertical Methods

The vertical methods are used to define values of the output variables at each vertical cell, given the values at ground level. Each method assumes that ground-level values already exist and are in internal units. These methods are designated in the VERTICAL METHOD packet, which is discussed in Section B.10 of this chapter. The first eight vertical methods (a through h) can be used by any of several data preparation programs; the remaining methods (i through k) are each specific to a single program.

a. CONSTANT

Values in each vertical cell are equal to the ground-level value. This method requires no additional parameters.

There are four vertical methods that require the input of a vertical profile to describe the shape of the vertical distribution of values. These vertical methods require that the DIFFBREAK and REGIONTOP files be attached. For two of these methods, ABSPROFILE and RELPROFILE, the ground-level value only is used in calculating vertical distribution. For the other two, ABSPROFRAT and RELPROFRAT, the value for the variable at the top of the region is required in addition to the ground-level value, and the profile defines the shape of the interpolation between them. These two ratio methods also require the TOPCONC file.

Each of these general vertical profile methods can be used in either the "absolute" or "relative" mode. In the absolute mode, the heights provided with each profile point are directly used to calculate the variable value at a cell of a given height. That is, the absolute height of the cell above ground is used to determine the profile value. In the relative mode, the heights provided with each profile point are used as heights relative to the diffusion break or top of region at the specified location of the profile.

b. ABSPROFILE

The vertical profile input describes the shape of the vertical distribution of values using the ground-level value. The height of each cell above ground is compared with the height of each profile point to determine the scaling factor to be used. The profile is input as a set of pairs (H_i, F_i) , where H is height and F is some profile value. Since it is assumed that the pair (H_1, F_1) corresponds to ground level, the following transformation is applied to all pairs:

$$H'_i = H_i - H_1 \quad ,$$

$$F'_i = F_i / F_1 \quad .$$

The profile is thus considered to be the set of pairs (H'_i, F'_i) ordered by increasing H' .

The profile is used for a particular grid cell in the following way: For a cell at a given (x,y) location on the grid, find the average height (A_k) of each vertical cell (k) as a function of the diffusion break and top of the region. If the ground-level value at that location is V_1 , then

$$V_k = \text{factor}_k * V_1 \quad ,$$

where

$$\text{factor}_k = \begin{cases} F'_n & , \text{ if } A_k > H'_n \\ F'_{i-1} + \frac{A_k - H'_{i-1}}{H'_i - H'_{i-1}} (F'_i - F'_{i-1}) & , \text{ if } H'_{i-1} \leq A_k \leq H'_i \end{cases} .$$

c. RELPROFILE

The vertical profile input describes the shape of the vertical distribution of values using the ground-level value. The height of each cell relative to the height of the diffusion break is compared to the height of each profile point relative to its diffusion break to determine the scaling factor to be used. The profile is input as a set of pairs (H_i, F_i) , where H is height and F is some profile value. Since it is assumed that the pair (H_1, F_1) corresponds to ground level, the following transformation is applied to all pairs: For all i ,

$$H'_i = (H_i - H_1)/DB_p \quad ,$$

$$F'_i = F_i/F_1 \quad ,$$

where DB_p = diffusion break at profile location. The profile is thus considered to be the set of pairs (H'_i, F'_i) ordered by increasing H' .

The profile is used for a particular grid cell in the following way. For a cell at a given (x,y) location on the grid, find the average height A_k of each vertical cell k as a function of the diffusion break and top of the region. Then convert the absolute height A_k to the height of the cell relative to the diffusion break at that location:

$$A'_k = \frac{A_k}{DB} \quad .$$

If the ground-level value at that location is V_1 , then

$$V_k = \text{factor}_k * V_1 \quad ,$$

where

$$\text{factor}_k = \begin{cases} F'_n & , \text{ if } A'_k > H'_n \\ F'_{i-1} + \frac{A'_k - H'_{i-1}}{H'_i - H'_{i-1}} (F'_i - F'_{i-1}) & , \text{ if } H'_{i-1} \leq A'_k \leq H'_i \end{cases} \quad .$$

d. ABSPROFRAT

The vertical profile input describes the shape of the vertical distribution of values expressed as the relative contribution (weighting) of the ground-level value and another value (which may be the value at the top of the region). The height of each cell above ground is compared with the height of each profile point to determine the contribution factor to be used. The profile is input as a set of pairs (H_i, F_i) , where H is height and F is a profile value $0 \leq F \leq 1$. $F = 0$ means that the ground-level value only should be used. $F = 1$ means that the other (top) value only should be used. (The exact formula is shown below.) Since it is assumed that the pair (H_1, F_1) corresponds to ground level, the following transformation is applied to all heights: For all i ,

$$H'_i = H_i - H_1 \quad .$$

The profile is thus considered to be the set of pairs (H'_i, F_i) ordered by increasing H' .

The profile is used for a particular grid cell in the following way. For a cell at a given (x,y) location on the grid, find the average height A_k of each vertical cell k as a function of the diffusion break and top of the region. If the ground-level value at that location is V_g and the other (top) value is V_t , then

$$V_k = V_g + \text{factor}_k (V_t - V_g) \quad ,$$

where

$$\text{factor}_k = \begin{cases} 1.0 , & \text{if } A'_k > H'_n \quad ; \\ F'_{i-1} + \frac{A'_k - H'_{i-1}}{H'_i - H'_{i-1}} (F'_i - F'_{i-1}) , & \text{if } H'_{i-1} \leq A'_k \leq H'_i \quad . \end{cases}$$

e. RELPROFRAT

The vertical profile input describes the shape of the vertical distribution of values expressed as the relative contribution (weighting) of the ground-level value and another value (which could be the value at the top of the region). The height of each cell relative to the diffusion break is compared to the height of each profile point relative to its diffusion break in order to determine the contribution factor to be used. The profile is input as a set of pairs (H_i, F_i) , where H is height and F is a profile value, $0 \leq F \leq 1$. $F = 0$ means that the ground-level value only should be used. $F = 1$ means that the other (top) value only should be used. (The exact formula is presented below.) Since it is assumed that the pair (H_1, F_1) corresponds to ground level, the following transformation is applied to all heights: For all i ,

$$H'_i = (H_i - H_1)/DBp \quad ,$$

where DBp = diffusion break at profile location. The profile is now considered to be the set of pairs (H'_i, F_i) ordered by increasing H' .

The profile is used for a particular grid cell in the following way. For a cell at a given (x,y) location on the grid, find the average height A_k of each vertical cell k as a function of the diffusion break and top of the region. Then convert the absolute height A_k to the height of the cell relative to the diffusion break at that location:

$$A'_k = \frac{A_k}{DB} \quad .$$

If the ground-level value at that location is V_g and the other (top) value is V_t , then

$$V_k = V_g + \text{factor}_k (V_t - V_g) \quad ,$$

where

$$\text{factor}_k = \begin{cases} 1.0, & \text{if } A'_k > H'_n ; \\ F'_{i-1} + \frac{A'_k - H'_{i-1}}{H'_i - H'_{i-1}} (F'_i - F'_{i-1}), & \text{if } H'_{i-1} \leq A'_k \leq H'_i . \end{cases}$$

f. E-W INTERP (East-West Interpolation)

For each row a linear interpolation will be carried out between values in the bordering cells in the east and west edges of the row. This subregion must not lie on an edge (i.e., it must be bounded on east and west by other subregions), and values for the bordering subregions must be calculated by a noninterpolative method. The E-W INTERP method requires no other parameters.

g. N-S INTERP (North-South Interpolation)

For each column a linear interpolation will be carried out between values in the bordering cells on the north and south edges of the column. This subregion must not lie on an edge (i.e., it must be bounded on north and south by other subregions), and values for the bordering subregions must be calculated by a noninterpolative method. The N-S INTERP method requires no other parameters.

h. VERTUSER (User-Supplied Algorithm)

For each file containing vertically varying data, the file preparation program is designed to call a user-supplied subroutine for any variable for which the vertical method VERTUSER has been selected. All available data are passed to the subroutine as arguments. At present, all vertical user subroutines are dummies; as new methods are developed, they can be inserted in user subroutines, and parameter values can be read and passed as for any of the standard vertical methods.

To create the PTSOURCE file, a vertical method must be chosen for determining the height at which the emissions from each point source enter the modeling region. Two vertical methods have been provided: STACKHGT and PLUMERISE, described below. Each of these vertical methods requires that the DIFFBREAK and REGIONTOP files be attached to the run.

i. STACKHGT

The emissions enter the region in the vertical cell that contains the top of the stack. No additional parameters are required.

j. PLUMERISE

Plume rise is calculated by the Briggs formulae [see Briggs (1975)]. For this vertical method the TEMPERATUR, METSCALARS, and WIND files must also be attached to the run. PLUMERISE requires no other parameters.

k. DIVERGENCE

The vertical method DIVERGENCE is used only for the WIND file. If DIVERGENCE has been specified in the METHOD packet for WINDX and WINDY, it must also be specified in the VERTICAL METHOD packet for those variables. No other parameters are required.

B. PACKET RULES AND FORMATS

This section presents the following information for each packet:

- > Instructions as to where the packet is used.
- > Special information about the contents.
- > A table outlining the definition of each field on the cards.
- > An exhibit showing the appearance (format) of the packet as a whole.

1. CONTROL Packet Rules

The CONTROL packet must always be the first packet input. The first three cards are the packet header, and the name and identifier of the file to be created. The next five cards contain counters for dimensioning arrays, and input and output option specifications; the standard entries are listed in Table VI-2. These control parameters are used in different combinations for different programs; each file preparation description in Chapter VII includes a table of the specific control parameters required for each file. For some files, some control parameters do not apply; these parameters are listed as "Spare" and any values are ignored. Following the control cards are those containing species names, if any, and the time span of the file. The contents of each card in the CONTROL packet are described in Table VI-3, and the format is shown in Exhibit VI-1.

Table VI-2. Standard Entries for Cards 4 Through 8 of the CONTROL Packet for M.E.B. Files

<u>Card Number</u>	<u>Entries</u>
4	Number of species Number of user-defined variables Number of stations Number of subregions Number of parameters Spare
5	Output file number Print input cards Print output grid Spare Spare Spare
6	Print units table Print station locations table Print regional grid Print methods table Print station values table Spare
7	Number of vertical parameters Number of heights in profile Print vertical methods table Print vertical profile tables Spare Spare
8	DIFFBREAK file number REGIONTOP file number TOPCONC file number TEMPERATUR file number METSCALARS file number WIND file number

Table VI-3. CONTROL Packet for M.E.B. Files

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	60A1	--	Must be CONTROL, left adjusted
2 File Name	File name 1-10	10A1	--	Must be the name (type) of the file to be created; misspellings will not be tolerated
3 File Identifier	Identifier 1-10	60A1	--	Can be any alphanumeric sequence; it will not be validated, but will be written on the file and used in printed page headings exactly as given
4-8 Control Counters	Number of species 1-10	I10	--	These cards contain integer-format control information; all five cards must be included for all programs even though a given program does not require all the control information
				For files that vary by species, this is the number of species output to the file; for files that do not vary by species, this number should be zero; in either case, this parameter controls the number of species names read from Cards 9+ in this packet; for files that do not vary by species, the species names are ignored

Table VI-3 (Continued)

<u>Card Number and Name</u>	<u>Item and Columns</u>	<u>Format</u>	<u>Units</u>	<u>Comments</u>
	Number of user- defined variables 11-20	I10	--	If species are input that do not appear in the output list, their number must be provided here; they must also be named in the UNITS packet; for files that do not vary by species, there is no need for user-defined variables by any of the current methods; if a user-defined method requires other than the standard variables, however, the additional variables can be enumerated here and named in the UNITS packet, and values can be supplied in the time-varying data packets
	Number of stations (or boundary lines or point sources) 21-30	I10	--	Defines the maximum number of fixed locations in the region that are to be specified in time-invariant packets
	Number of sub- regions 31-40	I10	--	Maximum number of different subregions that will be named in all SUBREGION packets; must be at least one
	Number of para- meters 41-50	I10	--	Maximum number of parameters that are defined or implied for all methods in all subregion-variable pairs; to obtain this value, multiply the number of parameters required for each method by the number of subregion-variable pairs that use the method (ALL counts not as 1, but as the total number); each time a parameter is redefined, it must be counted as a separate entry; add 3 to the maximum number of entries to ensure that enough space is allocated

Table VI-3 (Continued)

<u>Card Number and Name</u>	<u>Item and Columns</u>	<u>Format</u>	<u>Units</u>	<u>Comments</u>
5 Output Controls	Output file unit number 1-10	I10	--	Depending on the implementation, a specific number may be required for each output file
	Input print option 11-20	I10	--	= 0--don't print cards; = 1--do print input cards
	Output print option 21-30	I10	--	= 0--don't print all output data; = 1--do print all output data
6 Print Options	Print units table 1-10	I10	--	For all options specified on this card, the value 0 means "don't print it" and the value 1 means "do print it"
	Print station locations (or boundaries or point sources) 11-20	I10	--	
	Print region 21-30	I10	--	
	Print methods table 31-40	I10	--	
	Print station values (or boundary values or point source emissions) 41-50	I10	--	

Table VI-3 (Continued)

Card Number and Name	Item and Columns	Format	Units	Comments
7 Vertical Controls	Number of vertical parameters 1-10	I10	--	Meaningful only for files that vary vertically; for other files, this card should be blank
	Number of profile heights 11-20	I10	--	Maximum number of parameters that are defined or implied for all vertical methods for all subregion-variable pairs; this value is computed in the same manner as the number of parameters (defined on Card 4)
	Print vertical methods table 21-30	I10	--	Maximum number of height-value pairs that will be input for any single profile = 0--don't print it; = 1--do print it
	Print vertical profiles table 31-40	I10	--	= 0--don't print it; = 1--do print it
8 File Unit Assignment			--	Contains FORTRAN unit numbers for files that might be required as input to a particular data preparation program; if any of these files is <u>not</u> to be read in a run, its field <u>should</u> be left blank or set to zero; for consistency, the same unit number should be assigned to a given file for every data prepar- ation program using that file

Table IV-3 (Continued)

<u>Card Number and Name</u>	<u>Item and Columns</u>	<u>Format</u>	<u>Units</u>	<u>Comments</u>
	DIFFBREAK unit number 1-10	I10	--	Suggested value = 11, if required
	REGIONTOP unit number 11-20	I10	--	Suggested value = 12, if required
	TOPCONC unit number 21-30	I10	--	Suggested value = 13, if required
	TEMPERATUR unit number 31-40	I10	--	Suggested value = 14, if required
	METSCALARS unit number 41-50	I10	--	Suggested value = 15, if required
	WIND unit number 51-60	I10	--	Suggested value = 16, if required
9+ Species Names	Species 1-10	10A1	--	One species name per card; the number of species cards to be included here is defined on Card 4

Table VI-3 (Concluded)

Card Number and Name	Item and Columns	Format	Units	Comments
¹⁰ Time Span				Defines the time span for which the file contains data; this card must be present
	Beginning date 1-10	I10	Julian date (yyddd)	yy is the last two digits of the year and ddd is the three-digit Julian date
	Beginning time 11-20	I10	Military time (hhmm)	hh is hours and mm is minutes--this time will be internally converted to hours and fraction
	End date 21-30	I10	Julian date (yyddd)	Same format as that for beginning date
	End time 31-40	I10	Military time (hhmm)	Same format as that for beginning time
¹¹ Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTAN Format
		1-10	11-20	21-30	31-40	41-50	51-60
1	Packet Header	CONTROL					
2	File Name	File name					
3	File Identifier	# species	# u-def var	# stn	# subreg	# param	spare
4	Control Counters	output file	pr input	pr output	spare	spare	spare
5	Output Controls	pr units	pr stn loc	pr region	pr meth	pr stn val	spare
6	Print Options	#vert param	# heights	pr vert meth	pr vert prof	spare	spare
7	Vertical Controls	DIFFBREAK unit #	REGIONTOP unit #	TOPCONC unit #	TEMPERATUR unit #	METSCALARS unit #	WIND unit #
8	File Unit Assignments	spec name	beg time	end date	end time		
9+	Species Names	beg date					
10	Time Span	END					
11	Packet Terminator						

Exhibit VI-1. CONTROL Packet Format

2. REGION Packet Rules

The REGION packet must follow the CONTROL packet. It contains a complete definition of the location, size, and resolution of the modeling region. The same REGION packet values should be used to prepare all M.E.B. files for a given region. The contents of each card in the REGION packet are described in Table VI-4 and the format is shown in Exhibit VI-2.

Table VI-4. REGION Packet for M.E.B. Files

<u>Card Number and Name</u>	<u>Item and Columns</u>	<u>Format</u>	<u>Units</u>	<u>Comments</u>
1 Packet Header	Header 1-10	60A1	--	Must be REGION, left adjusted
2 Reference Origin (UTM)				The origin (in UTM coordinates) used to locate the modeling region and all other fixed points (stations, point sources, boundary lines); these numbers are not used for computation but are compared to the reference origins on other files for consistency
	x-location 1-10	F10.0	m	x-coordinate
	y-location 11-20	F10.0	m	y-coordinate
	Zone 21-30	I10	--	UTM zone
3 Origin of Grid				The location of the lower left-hand corner of the grid with respect to the reference origin; this point is used to place the grid on the map; the grid is assumed to be rectangular and is oriented with the x-direction increasing to the east and the y-direction increasing to the north; the grid origin may be the same as the reference origin, in which case the coordinates are 0.0, 0.0
	x-location 1-10	F10.0	m	x-coordinate
	y-location 11-20	F10.0	m	y-coordinate

Table VI-4 (Continued)

Card Number and Name	Item and Columns	Format	Units	Comments
4 Grid Cell Size	x-size 1-10	F10.0	m	The grid consists of a matrix of rectangular cells of the same size and shape; this card defines the length of the cell along each axis x-length y-length
	y-size 11-20	F10.0	m	
5 Grid Size	Number of cells in x-direction 1-10	I10	--	Defines the size of the grid in terms of the number of cells in each horizontal direction and the number of cells in the vertical direction Must be > 0 Must be > 0 Should be equal to the number of cells in the lower layer, plus the number of cells in the upper layer, plus one if there is a surface layer of nonzero height (see Card 6); for files that do not vary vertically, this number can be set to 0
	Number of cells in y-direction 11-20	I10	--	
	Number of cells in z-direction 21-30	I10	--	
6 Vertical Definition				Contains the parameters required to define the vertical distribution of cells within the region; (see Section IV.A.2 for a detailed discussion of vertical distribution parameters); if the number of z cells = 0, this card must be present, but the values will be ignored

Table VI-4 (Concluded)

Card Number and Name	Item and Columns	Format	Units	Comments
	Number of cells in lower layer 1-10	I10	--	Must be ≥ 1
	Number of cells in upper layer 11-20	I10	--	Must be ≥ 0
	Surface layer 21-30	F10.0	m	Height of surface layer; must be 0.0 if no surface layer is to be simulated (since microscale features have not been fully tested, set to 0.0)
	Lower layer 31-40	F10.0	m	Minimum height of cells in lower layer
	Upper layer 41-50	F10.0	m	Minimum height of cells in upper layer
7 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTTRAN Format
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2	Reference Origin (UTM)	REGION x-loc	y-loc	zone	.		
3	Origin of Grid	x-loc	y-loc				
4	Grid Cell Size	x-size	y-size				
5	Grid Size	# x	# y	# z			
6	Vertical Definition	# z low	# z up	ht surf layer	min cell low	min cell ht up	ht
7	Packet Terminator	END					

Exhibit VI-2. REGION Packet Format

3. UNITS Packet Rules

The UNITS packet must be used whenever values for any species or implicit variable are input in other than internal units. Additionally, all user-defined variables must be named in this packet, even if they are already in internal units. When it appears, this packet should follow the REGION packet and precede all the others, since it can modify coordinates specified in other time-invariant packets.

Table VI-5 shows the internal units for all variables used by the SAI Airshed Model. Table VI-6 shows other standard units that can be used and the associated conversion factors for each variable. Table VI-7 shows the standard molecular weights for certain species. In addition to internal units or built-in standard units, the user can specify his own input units, conversion factors, and molecular weights. The following specific rules apply to this packet:

- > If a species or an implicit variable is not defined in this packet, it is assumed to be already in the appropriate internal units.
- > If the unit name for a variable is left blank, the program will provide space for that variable and no unit conversions will be performed.
- > If the variable is in one of the standard alternate units shown in Table VI-6, the units should be named and the factor fields left blank; the built-in conversion factors will then be used.
- > If the variable will be input in nonstandard units, the unit name should be nonblank and scaling factors provided; conversion will be made using the following formula:

$$\text{var}_{\text{internal}} = a * \text{var}_{\text{input}} + b$$

Table VI-5. Implicit Variable Names and Internal Units
Used in the SAI Airshed Model

Variable Name	Internal Units	Code
Time	hr	*
HEIGHT	m	M
COORD	m	M
DIFFBREAK	m	M
REGIONTOP	m	M
ROUGHNESS	m	M
DIAMETER	m	M
SPEED	m/hr	M/HR
WINDX	m/hr	M/HR
WINDY	m/hr	M/HR
CARM	m/hr	M/HR
STACKVEL	m/hr	M/HR
FLOWRATE	m ³ /hr	M3/HR
DIRECTION	radians (from N = 0)	RADN=0
TEMPERATUR	°K	DEGK
STACKTEMP	°K	DEGK
TGRADBELOW	°K/m	DEGK/M
TGRADABOVE	°K/m	DEGK/M
ATMOSPRESS	atm	ATMOSPHERE
EXPCLASS	unitless	*
VEGFACTOR	unitless	*
RADFACTOR	min ⁻¹	*
Concentrations	ppm ($\mu\text{g}/\text{m}^3$ for AEROSOLS)	PPM MICROG/M3
CONCWATER	ppm	PPM
Point source emissions	g-mol/hr (g/hr for AEROSOLS)	GM/HR G/HR

* The units for these variables can not be changed by the UNITS packet.

Table VI-6. Standard Unit Conversions

Variable	Standard Units	Standard Unit Code	a*	b
TEMPERATUR	°K [†]	DEGK	-9.0	-9.0
	°C	DEGC	-9.0	273.15
	°F	DEGF	0.5555556	255.38
	°R	DEGR	0.5555556	-9.0
HEIGHT	m [†]	M	-9.0	-9.0
COORD	cm	CM	0.01	-9.0
ROUGHNESS	km	KM	1000.0	-9.0
DIFFBREAK	in	IN	0.0254	-9.0
REGIONTOP	ft	FT	0.3048	-9.0
DIAMETER	mi	MI	1609.344	-9.0
SPEED	m/hr [†]	M/HR	-9.0	-9.0
WINDX	km/hr	KM/HR	1000.0	-9.0
WINDY	mi/hr	MI/HR	1609.344	-9.0
CARM	m/min	M/MIN	60.0	-9.0
STACKVEL	ft/min	FT/MIN	18.288	-9.0
	m/sec	M/S	3600.0	-9.0
	ft/sec	FT/S	1097.28	-9.0
	knots	KNOTS	1852.0	-9.0
DIRECTION	radians (from N = 0) [†]	RADN=0	-9.0	-9.0
	radians (from S = 0)	RADS=0	-9.0	3.141593
	degrees (from N = 0)	DEGN=0	0.01745329	-9.0
	degrees (from S = 0)	DEGS=0	0.01745329	3.141593
	16-point (from S = 1)	16PTS=1	0.392699	2.748893
	16-point (from S = 16)	16PTS=16	0.392699	3.141593
	36-point (from S = 1)	36PTS=1	0.1745329	2.967059
	36-point (from S = 36)	36PTS=36	0.1745329	3.141593

Table VI-6 (Continued)

Variable	Standard Units	Standard Unit Code	a*	b
TGRADUPPER	$^{\circ}\text{K}/\text{m}^{\dagger}$	DEGK/M	-9.0	-9.0
TGRADLOWER	$^{\circ}\text{K}/\text{km}$	DEGK/KM	0.001	-9.0
	$^{\circ}\text{C}/\text{m}$	DEGC/M	-9.0	-9.0
	$^{\circ}\text{C}/\text{km}$	DEGC/KM	0.001	-9.0
	$^{\circ}\text{F}/\text{ft}$	DEGF/FT	1.822689	-9.0
	$^{\circ}\text{F}/\text{mi}$	DEGF/MI	0.0003452	-9.0
	$^{\circ}\text{R}/\text{ft}$	DEGR/FT	1.822689	-9.0
	$^{\circ}\text{R}/\text{mi}$	DEGR/MI	0.0003452	-9.0
ATMPRESS	$\text{atm}^{\dagger}$	ATMOSPHERE	-9.0	-9.0
	Bars	BARS	0.986923	-9.0
	mm of Hg	MMHG	0.0013158	-9.0
	ft of H_2O	FTH2O	0.029499	-9.0
	kg/cm^2	KG/CM2	0.967841	-9.0
	in of Hg	INHG	0.0334211	-9.0
	lb/in^2	LB/IN2	0.068046	-9.0
	psi	PSI	0.068046	-9.0
	millibars	MILLIBARS	0.0009869	-9.0
	in of H_2O	INH2O	0.0024582	-9.0
Concentrations	$\text{ppm}^{\dagger}$	PPM	-9.0	-9.0
CONCWATER	pptm	PPTM	0.1	-9.0
	pphm	PPHM	0.01	-9.0
	ppb	PPB	0.001	-9.0
	$\text{g mol}/\text{m}^3$	GM/M3	.24400	-9.0
	$\text{lb mol}/\text{ft}^3$	LBM/FT3	3.876×10^{-4}	-9.0
	$\mu\text{g}/\text{m}^3$	MICROG/M3	-0.0244	-9.0
	g/m^3	G/M3	-24400	-9.0
	lb/ft^3	LB/FT3	-3.876×10^{-4}	-9.0

Table VI-6 (Concluded)

<u>Variable</u>	<u>Standard Units</u>	<u>Standard Unit Code</u>	<u>a*</u>	<u>b</u>
Point source emissions	g-mol/hr [†]	GM/HR	-9.0	-9.0
	g-mol/day	GM/D	0.0416667	-9.0
	lb-mol/hr	LBM/HR	453.592	-9.0
	lb-mol/day	LBM/D	18.89967	-9.0
	kg/hr	KG/HR	-1000.0	-9.0
	kg/day	KG/D	-41.6667	-9.0
	lb/hr	LB/HR	-453.592	-9.0
	lb/day	LB/D	-18.89967	-9.0
	ton/hr	TON/HR	-907184.0	-9.0
	ton/day	TON/D	-37799.3	-9.0
	ton/year	TON/YR	-103.6	-9.0

* When the multiplicative factor (a) is negative, but not -9., the molecular weight is used in the denominator, and the absolute value of a is used as the multiplier.

† Internal units.

Table VI-7. Standard Species Names and Molecular Weights Used for Unit Conversion

<u>Species</u>	<u>Molecular Weight</u>
NO	30.
NO2	46.
CO	28.
O3	48.
H2O2	34.
SO2	64.
HNO2	47.
H2O	18.
O2	32.
CO2	44.
SO4	96.
PAN	121.
PAR	16.
OLE	32.
ETH	32.
ARO	96.
AEROSOLS	1.
CH4	16.
TOTAL HC	16.
SOX	64.
NOX	46.
OXIDANT	48.

- > If the variable is a species and the input values will be in mass units rather than mole units, the following formula will be used:

$$\text{var}_{\text{internal}} = (a * \text{var}_{\text{input}} + b) / \text{mol wt} \quad .$$

- > If both a standard unit name and scaling factors are specified, a warning message will be printed and the user's scaling factors will be used.
- > A designation of -9.0 indicates that the conversion factor is not to be applied.
- > If the factor fields are not blank or zero, a molecular weight must be entered on the card. If the variable does not have a molecular weight, e.g., as in TEMPERATUR, either a -9.0 or a +1.0 should be entered in the molecular weight field.

The contents of each card in the UNITS packet are shown in Table VI-8 and the format is given in Exhibit VI-3.

Table VI-8. UNITS Packet for M.E.B. Files

<u>Card Number and Name</u>	<u>Item and Columns</u>	<u>Format</u>	<u>Units</u>	<u>Comments</u>
1 Packet Header	Header 1-10	60A1	--	Must be UNITS, left adjusted
2 Unit Definition	Variable name 1-10	10A1	--	Can be a species name, implicit variable, user-defined variable, or either of two special names: > COORD--for station, point source, boundary, and vertical profile coordinates; > HEIGHT--for station height, point source, stack height, and vertical profile heights (note that this name does not apply to the height of the diffusion break or top of the region); conversions specified apply to values input in all subsequent packets
	Unit name 11-20	10A1	--	If field is left blank, no unit conversion will be performed; if this is one of the standard unit names listed in Table VI-6, the corresponding conversion factors will be used; if it is any other unit name, conversion factors must be input

Table VI-8 (Concluded)

Card Number and Name	Item and Columns	Format	Units	Comments
	Multiplicative factor (a) 21-30	F10.0	--	Can be left blank if standard conversion factors are to be used
	Additive factor (b) 31-40	F10.0	--	Can be left blank if standard conversions are to be used
	Molecular weight (c) 41-50	F10.0	--	Can be left blank if standard molecular weights are to be used; if the unit name does not belong to the standard set, this number should be set to 1., even for nonspecies variables
3 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTTRAN Format
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2+	Unit Definition	UNITS var name	unit name	mult fact	add fact	molec wt	60A1 2(10A1), 3F10.0 10A1
3	Packet Terminator	END					

Exhibit VI-3. UNITS Packet Format

4. STATIONS Packet Rules

The STATIONS packet must be included if the methods STATINTERP, POISSON, or DIVERGENCE are used for any variable. The STATIONS packet, if present, must appear before the first time interval; it must include all stations for which values may appear at any time within the span of the file. The number of station cards must not exceed the maximum number of stations specified in the CONTROL packet. Duplication of station names is considered an error resulting in termination of the run. The contents of each card in the STATIONS packet are shown in Table VI-9 and the format is given in Exhibit VI-4.

Table VI-9. STATIONS Packet for M.E.B. Files

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	60A1	--	Must be STATIONS, left adjusted
	Station Name and Location			
	Station name 1-10	10A1	--	Can be any name except the same as that for another station, or blank, or ALL
	x-location 11-20	F10.0	m, unless COORD was specified in UNITS packet	x-coordinate of the station; this number must be specified
	y-location 21-30	F10.0	m, unless COORD was specified in UNITS packet	y-coordinate of the station; this number must be specified
3 Packet Terminator	z- location 31-40	F10.0	m, unless HEIGHT was specified in UNITS packet	Height of the station above ground; if omitted, this number is assumed to be 0; for files that do not vary vertically, this number is ignored
	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTTRAN Format
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2+	Station Name and Location	STATIONS stn name	x-loc	y-loc	z-loc		60A1 10A1, 3F10.0 10A1
3	Packet Terminator	END					

Exhibit VI-4. STATIONS Packet Format

5. POINT SOURCES Packet Rules

The POINT SOURCES packet is used for preparing the PTSOURCE file; it must appear before the first time interval and include all point sources for which values may appear at any time within the span of the file. There are two cards (a pair) required for each point source, and the number of pairs must equal the number of point sources specified on Card 4 of the CONTROL packet. Duplication of point source names is considered an error, resulting in termination of the run. The contents of each card in the POINT SOURCES packet are shown in Table VI-10 and the format is given in Exhibit VI-5.

Table VI-10. POINT SOURCES Packet for the PTSOURCE File

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	60A1	--	Must be POINT SOURCES, left adjusted
2+ Point Source Name and Location	Point source name 1-10	10A1	--	Can be any alphanumeric sequence except the same as that of another point source or type of source, or blank, or ALL
	Type 11-20	10A1	--	Can be any alphanumeric sequence except a point source name, or blank, or ALL; point sources of the same type are treated as a group when specifying the method for calculating emissions and when specifying the vertical method; they can also be treated as a group when specifying emissions or emission factors
	x-location 21-30	F10.1	m, unless COORD was specified in UNITS packet	x-coordinate of the point source with respect to the reference origin; this number must be specified
	y-location 31-40	F10.1	m, unless COORD was specified in UNITS packet	y-coordinate of the point source with respect to the reference origin; this number must be specified

Table VI-10 (Concluded)

Card Number and Name	Item and Columns	Format	Units	Comments
3+ Point Source Properties	Stack height 1-10	F10.0	m, unless HEIGHT was specified in UNITS packet	Height of the top of the stack above the ground; this number must be greater than zero
	Stack exit diameter* 11-20	F10.0	m, unless DIAMETER was speci- fied in UNITS packet	Must be specified if it is to be used to calculate the flow rate for the PLUMERISE method
	Stack exit temperature 21-30	F10.0	°K, unless STACKTEMP was spe- cified in UNITS packet	Used to calculate heat flux for the PLUMERISE method
	Stack exit velocity* 31-40	F10.0	m/hr, unless STACKVEL was speci- fied in UNITS packet	Used with stack exit diameter to calcu- late flow rate for the PLUMERISE method
4 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

* If the vertical method PLUMERISE is to be used to calculate the height at which the emissions enter the modeling region, either both the stack exit diameter and stack exit velocity or the stack flow rate alone must be specified. Flow rate is specified in the EMISSIONS VALUES packet.

Card Number	Card Identifier	Column Number					FORTTRAN Format
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2+	Point Source Name and Location	POINT SOURCES pt srce nam	type	x-loc	y-loc		
3+	Point Source Properties	stack ht	stack diam	stack temp	stack vel		
4	Packet Terminator	END					

60A1
2(10A1),
2F10.0
4F10.0
10A1

Exhibit VI-5. POINT SOURCES Packet Format

6. BOUNDARIES Packet Rules

The BOUNDARIES packet, used for preparing the BOUNDARY file, must appear before the first time interval. It contains a set of line segments that define the boundary of the simulated area; each line segment is defined by two coordinate pairs that represent its end points. The line segments can appear in any order and, within each one, the end points can appear in any order, but the complete set must represent a closed figure (i.e., every end point must be identical to one, and only one, end point of another line segment). In addition, the figure represented must be nonconcave along each axis; that is, within a single row or column, any two cells within the simulated area must not have any nonsimulated cells between them.

The boundary line segments outline the edge cells within the inner area to be simulated. Figure VI-1 shows a 17 x 22 cell region in which the inner 15 x 20 area is to be simulated. In the figure, the boundary line segments are indicated by dotted lines. To ensure that the program succeeds in matching the end points of touching line segments, each end point should be defined to be in the center of the cell in which it lies. The number of boundary line segments input must not exceed the maximum number specified on Card 4 of the CONTROL packet. Duplication of line segment names is considered an error resulting in termination of the run.

The contents of each card in the BOUNDARIES packet are shown in Table VI-11 and the format is given in Exhibit VI-6.




Figure VI-1. Definition of Boundary Line Segments

Table VI-11. BOUNDARIES Packet for the BOUNDARY File

<u>Card Number and Name</u>	<u>Item and Columns</u>	<u>Format</u>	<u>Units</u>	<u>Comments</u>
¹ Packet Header	Header 1-10	60A1	--	Must be BOUNDARIES, left adjusted
²⁺ Boundary Definition	Line segment name 1-10	10A1	--	Any alphanumeric sequence except the same as that for another line segment name, blank, or ALL
	x-beginning 11-20	F10.0	m, unless COORD was specified in UNITS packet	x-coordinate of the first end point with respect to the reference origin; the end point should lie in the center of a cell
	y-beginning 21-30	F10.0	m, unless COORD was specified in UNITS packet	y-coordinate of the first end point with respect to the reference origin
	x-end 31-40	F10.0	m, unless COORD was specified in UNITS packet	x-coordinate of the second end point with respect to the reference origin
	y-end 41-50	F10.0	m, unless COORD was specified in UNITS packet	y-coordinate of the second end point with respect to the reference origin
³ Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	1-10	11-20	21-30	31-40	41-50	51-60	FORTRAN Format
1	Packet Header	BOUNDARIES	x-beg	y-beg	x-end	y-end		60A1
2+	Boundary Definition	line name						10A1, 4F10.0
3	Packet Terminator	END						10A1

Exhibit VI-6. BOUNDARIES Packet Format

7. TIME INTERVAL Packet Rules

A series of TIME INTERVAL packets follows the time-invariant data. The time intervals must be contiguous, must go forward, and must cover the entire time span of the file as specified in the CONTROL packet. If any time interval extends beyond the time span specified in the CONTROL packet, that time interval will be reset by the program to lie exactly within the time span of the file.

TIME INTERVAL packets contain other time-varying packets that define regional divisions, calculation methods, and time-varying data values. Each TIME INTERVAL packet consists of a header card, a time interval card, other packets as desired, and a terminator card. The contents of each card in the TIME INTERVAL packet is shown in Table VI-12 and the format is given in Exhibit VI-7. The other time-varying packets that can be included within the TIME INTERVAL packet for a given file are shown in the appropriate section of Chapter VII; their formats and rules are described in the remainder of this chapter.

Table VI-12. TIME INTERVAL Packet for M.E.B. Files

Card Number and Name	Item and Columns	Format	Units	Comments
¹ Packet Header	Header 1-10	60A1	--	Must be TIME INTERVAL, left adjusted
² Time Interval	Beginning date 1-10	I10	Julian date (yyddd)	yy is the last two digits of the year and ddd is the three-digit Julian date
	Beginning time 11-20	I10	Military time (hhmm)	hh is hours and mm is minutes; this time will be internally converted to hours and fraction
	End date 21-30	I10	Julian date (yyddd)	Same format as beginning date
	End time 31-40	I10	Military time (hhmm)	Same format as beginning time
^{3 +} Other Packets				Chapter VII lists the packets allowed here for each data file
⁴ Packet Terminator	Terminator 1-3	10A1	--	Must be ENDTIME, left adjusted

Card Number	Card Identifier	Column Number					FORTTRAN Format
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2	Time Interval	TIME INTERVAL beg date	beg time	end date	end time		60A1 4110
3+	Other Packets						
4	Packet Terminator	ENDTIME					10A1

Exhibit VI-7. TIME INTERVAL Packet Format

8. SUBREGION Packet Rules

The entire modeling region can be divided into subregions for data preparation purposes. Different data preparation methods or other parameters can be associated with each subregion. (These subregions should not be confused with "segments," which are divisions of the region for simulation purposes.) The subregion definitions may likely be different for the preparation of different types of data files; in fact, a subregion definition can be changed within the time span of a given file depending on the availability of or assumptions about the data.

A subregion name must be assigned to each grid square in the modeling region. The maximum number of subregion names that may be assigned is specified in the CONTROL packet. If this number = 1, the entire region is considered to be one subregion; nevertheless, the SUBREGION packet must be included and must appear at the beginning of the first TIME INTERVAL packet. In subsequent time intervals, the SUBREGION packet can be used to change subregion assignments. Only those portions of the region to be changed need be specified. New subregion names can be added provided that the maximum number allowed is not exceeded.

Subregion names are assigned by row. A typical subregion definition card contains a subregion name and a row in which it appears. For that row, a column number and cell count, n , are specified. Beginning at that column, the subregion name will be repeated for n columns along the row. The following conditions constitute errors resulting in termination of the program:

- > The cell count extends the column count beyond the edge of the region.
- > Any grid cell is unassigned.
- > The number of subregion names exceeds the maximum number specified in the CONTROL packet.

If the entire region is to be treated as one subregion, the SUBREGION packet should contain the following information:

SUBREGION

A-----|-----1|-----1|-----1|

END ,

where A (or some other simple name) is the subregion name. This name (or ALL) must then be used in the subregion field of all subsequent input cards.

The contents of each card in the SUBREGION packet are shown in Table VI-13 and the format is given in Exhibit VI-8.

Table VI-13. SUBREGION Packet for M.E.B. Files

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	60A1	--	Must be SUBREGION, left adjusted
2+ Subregion Definition	Subregion name 1-10	10A1	--	Any alphanumeric sequence except blank or ALL
	Row number 11-20	I10	--	Must be ≥ 1 , and $\leq$ number of rows (cells in y-direction) in region
	Beginning column number 21-30	I10	--	Must be ≥ 1 , and $\leq$ number of columns (cells in x-direction) in region
	Cell count 31-40	I10	--	Must not exceed [(number of columns) - (column number) + 1]; if omitted, this value is assumed to be = rest of row; if negative, this value is assumed to be = rest of modeling region
3 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

<u>Card Number</u>	<u>Card Identifier</u>	<u>Column Number</u>					<u>FORTTRAN Format</u>
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2+	Subregion Definition	SUBREGION subreg name row #		beg col #	# cells		
3	Packet Terminator	END					

60A1
10A1,
3I10
10A1

Exhibit VI-8. SUBREGION Packet Format

9. METHOD Packet Rules

The METHOD packet is used to define the calculation method to be used for ground-level values of each variable in each subregion; it is required for all of the M.E.B. files except METSCALARS. The METHOD packet must appear in the first time interval, and it must directly follow the SUBREGION packet. In subsequent time intervals, the methods previously defined will persist unless they are respecified. If new subregions are defined in later time intervals, methods must also be defined for them. The contents of each card in the METHOD packet are shown in Table VI-14 and the format is given in Exhibit VI-9. Within the METHOD packet, each Method Definition card must be followed by its Parameter cards, if any. All of the calculation methods and the parameters required by each one are defined in Section VI.A.6. Chapter VII lists the particular methods that can be used for each file.

Table VI-14. METHOD Packet for M.E.B. Files

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	60A1	--	Must be METHOD, left adjusted
2+ Method Definition				
	Subregion name 1-10	10A1	--	Must match a name in the subregion packet; if the name = ALL, this method will apply to this variable in all subregions
	Variable name 11-20	10A1	--	Must be an output species, implicit vari- able name, or user-defined variable name from the UNITS packet; if the variable name = ALL, this method will be used for all variables in this subregion
	Method 21-30	10A1	--	See Section VI.A.6 for standard method names
	Minimum value 31-40	F10.0	Internal units assumed, unless otherwise specified in UNITS packet	Lower bound for variable; if the variable name = ALL, this value will be converted according to unit specifications for the first variable; care should be taken in setting limits for ALL variables, espe- cially when species (requiring different molecular weights for conversion) are involved; if the value calculated for the variable is less than this number, that value will be set equal to this number; if the field is left blank, it is assumed to be zero; if it is set to -9.0, no lower limit test will be performed

Table VI-14 (Concluded)

Card Number and Name	Item and Columns	Format	Units	Comments
	Maximum value 41-50	F10.0	Internal units assumed, unless otherwise speci- fied in UNITS packet	Upper bound for variable; if the vari- able name = ALL, this value will be converted as described above; if the value calculated for this variable is greater than the number, that value will be set equal to this number; if the field is left blank, it is assumed to be zero; if it is set to -9.0, no upper limit test will be performed
	Number of parameters 51-60	I10	--	Defines the number of parameter cards that follow (Card 3 below); must be ≥ 0; Section VI.A.6 gives the number of parameters associated with each method
3+ Parameters	Parameter name 1-10	10A1	--	Standard parameter names and values are defined in Section VI.A.6; the number of parameter cards for a given method must equal the number specified on Card 2
	Parameter value 11-20	F10.0	--	
4 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTTRAN Format
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2+	Method Definition	METHOD subreg name	var name	method	min value	max value	# params
3+	Parameters	param name	value				
4	Packet Terminator	END					

60A1
3(10A1),
2F10.0,
I10
10A1,F10.0
10A1

Exhibit VI-9. METHOD Packet Format

10. VERTICAL METHOD Packet Rules

In general, where it is necessary to determine the values of variables in grid cells above ground level, a VERTICAL METHOD packet is required. The VERTICAL METHOD packet is used to define the calculation method to be used for obtaining values of each variable above ground level in each sub-region. The VERTICAL METHOD packet must appear in the first time interval; it must follow the METHOD packet and precede the VERTICAL PROFILES packet (if any). In subsequent time intervals, the vertical methods previously defined will persist unless they are respecified. If new subregions are defined in later time intervals, vertical methods must also be defined for them. Within the VERTICAL METHOD packet, each vertical method definition card must be followed by its parameter cards, if any. All of the vertical calculation methods and the parameters required by each one are defined in Section VI.A.7. Chapter VII lists the particular vertical methods that can be used for each file. The contents of each card in the VERTICAL METHOD packet is shown in Table VI-15, and the format is given in Exhibit VI-10.

Table VI-15. VERTICAL METHOD Packet for M.E.B. Files

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	60A1	--	Must be VERTICAL METHOD, left adjusted
2+ Vertical Method Definition	Subregion name 1-10	10A1	--	Must match a name in the subregion packet; if the name = ALL, this vertical method will apply to this variable in all subregions
	Variable name 11-20	10A1	--	Must be an output species, implicit variable name, or user-defined variable name from the UNITS packet; if the variable name = ALL, this vertical method will be used for all variables in this subregion
	Method 21-30	10A1	--	See Section VI.A.7 for standard vertical method names
	Minimum value 31-40	F10.0	Internal units, unless otherwise specified in UNITS packet	Lower bound for variable; as in the METHOD packet, if the variable name = ALL, this value will be converted according to unit specifications for the first variable; if the value calculated for the variable is less than this number, that value will be set equal to this number; if the field is left blank, it is assumed to be zero; if it is set to -9.0, no lower limit test will be performed

Table VI-15 (Concluded)

Card Number and Name	Item and Columns	Format	Units	Comments
	Maximum value 41-50	F10.0	Internal units, unless otherwise speci- fied in UNITS packet	Upper bound for variable; if the varia- ble name = ALL, this value will be con- verted as described above; if the value calculated for this variable is greater than this number, that value will be set equal to this number; if the field is left blank, it is assumed to be zero; if it is set to -9.0, no upper limit test will be performed
3+ Parameters	Number of parameters 51-60	I10	--	Defines the number of parameter cards that follow (Card 3 below); must be ≥ 0; Section VI.A.7 gives the number of parameters associated with each verti- cal method
	Parameter name 1-10	10A1	--	Standard parameter names and values are defined in Section VI.A.7; the number of parameter cards for a given vertical method must equal the number specified on Card 2
	Parameter value 11-21	F10.0	--	
4 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTTRAN Format
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2+	Vertical Method Definition	VERTICAL METHOD subreg name	var name	method	min value	max value	# param
3+	Parameters	param name	value				
4	Packet Terminator	END					

60A1
3(10A1),
2F10.0
I10
10A1, F10.0
10A1

Exhibit VI-10. VERTICAL METHOD Packet Format

11. CONSTANTS Packet Rules

The CONSTANTS packet is required in the first time interval if the method for any variable in any subregion has been specified as CONSTANT. All constant values can be included in one packet or, if desired, they can be grouped in several packets. In either case, all constant values must be specified in the initial time interval and will persist in subsequent time intervals unless they are explicitly changed. The contents of each card in the CONSTANTS packet are shown in Table VI-16 and the format is given in Exhibit VI-11.

Table VI-16. CONSTANTS Packet for M.E.B. Files

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	60A1	--	Must be CONSTANTS, left adjusted
2+ Constants	Subregion name 1-10	10A1	--	Must be identical to a previously named subregion, or ALL; if ALL is specified, all subregions that use the CONSTANT method for this varia- ble will be assigned this value
	Variable name 11-20	10A1	--	Must be a variable named on a method card that specifies CONSTANT; if ALL is specified, all variables that require CONSTANT for this subregion will be assigned this value
	Value 21-30	F10.0	Internal units, unless otherwise speci- fied in UNITS packet	If the variable name = ALL, this value will be converted according to unit specifications for the first variable; care should be taken in specifying values for ALL variables, especially when species (requiring different molecular weights for conversion) are involved
3 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTRAN Format
		1-10	11-20	21-30	31-40	41-50	
1	Packet Header	CONSTANTS					60A1
2+	Constants	subreg name	var name	value			2(10A1), F10.0
3	Packet Terminator	END					10A1

Exhibit VI-11. CONSTANTS Packet Format

12. GRID VALUES Packet Rules

The GRID VALUES packet must be included in the first time interval if the method for any variable in any subregion has been specified as GRID VALUE. All grid values can be included in one packet or, if desired, they can be grouped in several packets. In either case, all grid values must be specified in the initial time interval and will persist in subsequent time intervals unless they are explicitly changed. The contents of each card in the GRID VALUES packet are shown in Table VI-17 and the format is shown in Exhibit VI-12.

Table VI-17. GRID VALUES Packet for M.E.B. Files

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	60A1	--	Must be GRID VALUES, left adjusted
2+ Grid Values	Subregion name 1-10	10A1	--	Must be identical to a previously named subregion; GRID VALUES must be specified as the method for this variable
	Variable name 11-20	10A1	--	Must be a variable named or implied (by means of ALL) on a method card for this subregion
	Column number 21-30	I10	--	y-index on grid, counting from bottom (SOUTH) row = 1
	Row number 31-40	I10	--	x-index on grid, counting from left (WEST) column = 1
	Value 41-50	F10.0	Internal units, unless otherwise specified in UNITS packet	If the variable name = ALL, this value will be converted according to unit specifications for the first variables; care should be taken in specifying values for ALL variables especially when species (requiring different molecular weights for conversion) are involved.
3 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTTRAN Format
		1-10	11-20	21-30	31-40	41-50	51-60
1	Packet Header	GRID VALUES					
2+	Grid Values	subreg name	var name	col #	row #	value	60A1 2(10A1), 2I10, F10.0 10A1
3	Packet Terminator	END					

Exhibit VI-12. GRID VALUES Packet Format

13. STATION READINGS Packet Rules

The STATION READINGS packet must appear in the first time interval when the method for any variable in any subregion has been specified as STATINTERP, POISSON, or DIVERGENCE. A value that does not appear in the first time interval for a station-variable pair is recognized as "missing", and the station will not be included in the calculation. In subsequent time intervals, the STATION READINGS packet can be used to modify existing data in the following ways:

- > An existing reading can be changed by substituting a new value.
- > An existing reading can be nullified (i.e., changed to "missing") by supplying a value of -9.0.
- > A "missing" reading can be changed to "nonmissing" by supplying a value.

For any station-variable pair not supplied, the previous values, "missing" or not, will persist. The contents of each card in the STATION READINGS packet is shown in Table VI-18 and the format is given in Exhibit VI-13.

Table VI-18. STATION READINGS Packet for M.E.B. Files

Card Number and Name	Item and Columns	Format	Units	Comments
¹ Packet Header	Header 1-10	60A1	--	Must be STATION READINGS, left adjusted
²⁺ Station Readings	Station name 1-10	10A1	--	Must be identical to a name specified in the STATIONS packet
	Variable name 11-20	10A1	--	Must be a species name, or an implicit or user-defined variable
	Value 21-30	F10.0	Internal units, unless otherwise speci- fied	A blank is treated as zero; -9.0 is considered "missing"
³ Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTTRAN Format
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2	Station Readings	STATION READINGS stn name	var name	value			60A1 2(10A1), F10.0 10A1
3	Packet Terminator	END					

Exhibit VI-13. STATION READINGS Packet Format

14. EMISSIONS VALUES Packet Rules

The EMISSIONS VALUES packet is used to create the PTSOURCE file. It provides emissions values for those variables for which the method EMVALUES was specified. The EMISSIONS VALUES packet must be included in the first time interval (unless all emissions are zero); any value not appearing in the first time interval for a point source-species pair will be assumed to be zero. In subsequent time intervals, existing data will persist unless explicitly changed. If all point sources of a given type have the same emissions values, the type can be specified instead of individual point source names.

If the vertical method PLUMERISE has been specified for a point source type, the variable FLOWRATE must be either input in the EMISSIONS VALUES packet or calculated. If it is not input, it will be calculated from the stack diameter and exit velocity input in the POINT SOURCES packet.

The contents of each card in the EMISSIONS VALUES packet are shown in Table VI-19 and the format is given in Exhibit VI-14.

Table VI-19. EMISSIONS VALUES Packet for the PTSOURCE File

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	60A1	--	Must be EMISSIONS VALUES, left adjusted
2+ Point Source Emissions	Point source or type 1-10	10A1	--	Must be one of the following: > a name appearing in the POINT SOURCES packet, > ALL--meaning all point sources, > a type appearing in the POINT SOURCES packet, meaning all point sources of a given type Must be an output species or a user- defined input variable, or FLOWRATE Emissions of the variable from the point source; if the variable is FLOWRATE, the units are m ³ /hr, unless otherwise speci- fied in the UNITS packet
3 Packet Terminator	Variable name 11-20 Value 21-30 Terminator 1-3	10A1 F10.0 10A1	-- gm-mo1/hr (gm/hr for AEROSOLS), unless otherwise spe- cified in UNITS packet --	Must be END, left adjusted

Card Number	Card Identifier	1-10	11-20	21-30	31-40	41-50	51-60	FORTAN Format
1	Packet Header	EMISSIONS VALUES						60A1
2+	Point Source Emissions	pt srce or type	var name	value				2(10A1), F10.0
3	Packet Terminator	END						10A1

Exhibit VI-14. EMISSIONS VALUES Packet Format

15. EMISSIONS FACTORS Packet Rules

The EMISSIONS FACTORS packet can be input for a given time interval to scale the emissions values previously input. The factors are used only if the method EMFACTORS was specified for the variable and point source type. The following formula will be used:

$$\text{output emissions (source, species)} = \text{factor (source, species)} \\ \times \text{emissions (source, species)} \quad .$$

The factor is always applied to the last emissions value input in an EMISSIONS VALUES packet, not the last one calculated by a previous emissions factor. If factors are not input, they are assumed to be 1.0 (or the previous value specified). Emissions factors are applied to numbers in internal units--they are thus to be used to describe temporal variation rather than unit conversion. The contents of each card in the EMISSIONS FACTORS packet are shown in Table VI-20 and the format is given in Exhibit VI-15.

Table VI-20. EMISSIONS FACTORS Packet for the PTSOURCE File

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	60A1	--	Must be EMISSIONS FACTORS, left adjusted
2+ Emissions Factors	Point source or type 1-10	10A1	--	Must be one of the following: > a name appearing in the POINT SOURCES packet, > ALL--meaning all point sources, > a type appearing in the POINT SOURCES packet, meaning all point sources of a given type
	Variable name 11-20	10A1	--	Must be an output species or a user-defined input variable; if the name = ALL, this factor will apply to all species and to FLOWRATE
	Factor 21-30	F10.0	--	Emission factors apply to FLOWRATE as well as to species; when the variable = ALL, these factors are automatically applied; when factors are being provided for individual species, the factor for the flow rate, if it changes, must also be specified
3 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTAN Format
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2+	Emissions Factors	EMISSIONS pt srce or type END	FACTORS var name	factor			60A1 2(10A1), F10.0 10A1
3	Packet Terminator						

Exhibit VI-15. EMISSIONS FACTORS Packet Format

16. BOUNDARY READINGS Packet Rules

The BOUNDARY READINGS packet is used to create the BOUNDARY file; it provides values for those variables for which the method BOUNDVALUE was specified. The packet must be input for the first time interval. Concentration values at ground level are specified for each species for each boundary line segment; missing values are considered an error. In subsequent time intervals, only the data to be changed need be specified. The contents of each card in the BOUNDARY READINGS packet is shown in Table VI-21, and the format is given in Exhibit VI-16.

Table VI-21. BOUNDARY READINGS Packet for the BOUNDARY File

Card Number and Name	Item and Columns	Format	Units	Comments
¹ Packet Header	Header 1-10	60A1	--	Must be BOUNDARY READINGS, leftadjusted
²⁺ Boundary Values	Line segment name 1-10	10A1	--	Must be a name specified in the BOUNDARY packet, or ALL
	Variable name 11-20	10A1	--	Must be an output species, a user-defined variable, or ALL
	Value 21-30	F10.0	ppm ($\mu\text{g}/\text{m}^3$ for AEROSOLS), unless otherwise specified in UNITS packet	Ground-level concentration of the variable along the line segment
³ Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTTRAN Format
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2+	Boundary Values	BOUNDARY READINGS line name	var name	value			
3	Packet Terminator	END					

60A1
2(10A1),
F10.0
10A1

Exhibit VI-16. BOUNDARY READINGS Packet Format

17. SCALARS Packet Rules

The SCALARS packet must be input for the first time interval for the METSCALARS file. For this time interval, all six meteorological scalars (TGRADBELOW, TGRADABOVE, EXPCLASS, RADFACTOR, CONCWATER, and ATMOSPRESS) must be assigned values. Missing values are considered errors. In subsequent time intervals, only the data to be changed need be specified. The contents of each card in the SCALARS packet is shown in Table VI-22 and the format is given in Exhibit VI-17.

Table VI-22. SCALARS Packet for the METSCALARS File

Card Number and Name	Item and Columns	Format	Units	Comments
¹ Packet Header	Header 1-10	60A1	--	Must be SCALARS, left adjusted
²⁺ Meteorological Scalars	Scalar name 1-10	10A1	--	Must match the standard spelling of the scalars (see Chapter VII for instruc- tions on preparing the METSCALARS file)
	Value 11-20	F10.0	Internal units, unless otherwise speci- fied in UNITS packet	
³ Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTTRAN Format
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2+	Scalars	SCALARS scalar name	value				60A1 10A1, F10.0 10A1
3	Packet Terminator	END					

Exhibit VI-17. SCALARS Packet Format

18. VERTICAL PROFILES Packet Rules

For some vertical methods, a profile is required (see Section VI.A.7 for details). The VERTICAL PROFILES packet must contain a profile for each subregion-variable pair requiring one. Each profile must contain at least two points, which must be entered in order of increasing height. The first point always represents ground level. There can be only one vertical profile specified for a given subregion and variable. Each profile consists of a description card followed by a set of height/value pairs. The contents of each card in the VERTICAL PROFILES packet is shown in Table VI-23 and the format is given in Exhibit VI-18.

Table VI-23. VERTICAL PROFILES Packet for M.E.B. Files

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	60A1	--	Must be VERTICAL PROFILES, left adjusted
2+ Profile Description	Subregion name 1-10	10A1	--	Must be identical to a previously named subregion, or boundary line segment, or ALL; if ALL is specified, all subregions that require a vertical profile for this variable will use these values
	Variable name 11-20	10A1	--	Must be a variable that requires a vertical profile for this subregion; if name = ALL, this profile will be used for all variables in this subregion
	x-location 21-30	F10.0	m, unless COORD was specified in UNITS packet	x-coordinate of the profile with respect to the reference origin; this number will be ignored if a "relative" method is not being used
	y-location 31-40	F10.0	m, unless COORD was specified in UNITS packet	y-coordinate of the profile with respect to the reference origin; this number will be ignored if a "relative" method is not being used
	Number of points 41-50	I10	--	Number of profile points that follow; must be ≥ 2 (or = -9 to clear all profile points)

Table VI-23 (Concluded)

Card Number and Name	Item and Columns	Format	Units	Comments
3+ Profile Points	Height 1-10	F10.0	m, unless HEIGHT was specified in UNITS packet	Must be in increasing order; the first is assumed to be ground level and will be subtracted from all others to obtain each height relative to the ground
	Value 11-20	F10.0	--	See the appropriate vertical method description in Section VI.A.7
	Terminator	10A1	--	Must be END, left adjusted
4 Packet Terminator				

Card Number	Card Identifier	Column Number					FORTTRAN Format
1	Packet Header	1-10	11-20	21-30	31-40	41-50	51-60
2+	Profile Description	VERTICAL PROFILES subreg name	var name	x-loc	y-loc	# pts	60A1 2(10A1), 2F10.0, I10 2F10.0 10A1
3+	Profile	height	value				
4	Packet Terminator	END					

Exhibit VI-18. VERTICAL PROFILES Packet Rules

VII M.E.B. FILE PREPARATION RULES AND EXAMPLES

Chapter VI presented the data preparation packets--the building blocks used to generate the M.E.B. data files. This chapter presents detailed instructions for the creation of each file, using the packets described above.

The preparation of some data files may require that other files be input, depending on the method used. In general, vertically varying files may require information from DIFFBREAK and REGIONTOP to define the vertical distribution of grid cells. The following is a suggested order of file preparation, assuming methods requiring the greatest file dependency. This order may be varied, depending on the requirements of the actual methods used.

- > DIFFBREAK.
- > EMISSIONS.
- > METSCALARS.
- > TEMPERATUR.
- > TERRAIN.
- > REGIONTOP (requiring DIFFBREAK).
- > TOPCONC (requiring DIFFBREAK and REGIONTOP).
- > AIRQUALITY (requiring DIFFBREAK, REGIONTOP, and TOPCONC).
- > BOUNDARY (requiring DIFFBREAK, REGIONTOP, and TOPCONC).
- > WIND (requiring DIFFBREAK, REGIONTOP, and TEMPERATUR).
- > PTSOURCE (requiring DIFFBREAK, REGIONTOP, METSCALARS, TEMPERATUR, and WIND).

The output from each program can include a printout of the input a title page, tables of methods, vertical methods, vertical profiles, a subregion grid, and grids of output variable values. In this manual,

a sample of each type of output is shown only for the AIRQUALITY file (Exhibit VII-2). For the other M.E.B. files, only the title page, methods tables, and an output grid sample are shown.

The data file preparation instructions are presented alphabetically by file name; each section includes:

- > A short description of the file.
- > The variables required and their units.
- > The computation methods that can be used.
- > The time variation represented.
- > The arrangement of packets in the input deck and special instructions for each one.
- > Additional input files required.
- > Sample input and output from a file generation run.

A. AIRQUALITY

The AIRQUALITY file contains a three-dimensional matrix of concentrations for any number of chemical species. Its primary purpose is to provide the set of initial conditions for the beginning of the modeling period; however, it can also be used to prepare a three-dimensional distribution of measured data in any time interval for use in comparison studies. The program AIRQUL is used to create the AIRQUALITY file. AIRQUL requires subroutines from the libraries UTILITY and FILUTIL. Figure VII-1 is an information flow diagram illustrating the job control to be used. The following sections discuss the input to the AIRQUL program.

1. Variables

The output variables for the AIRQUALITY file are the species named in the CONTROL packet. Additional user-defined input variables (e.g., "reactive hydrocarbons") can be specified in the UNITS packet. The internal units for the concentrations of all species except AEROSOLS are parts per million (ppm); for AEROSOLS, the units are micrograms per cubic meter ($\mu\text{g}/\text{m}^3$). The standard names for reactive species currently recognized by the Airshed Simulation Program are listed in Section IX.A. If any of these species does not appear on the AIRQUALITY file, the initial concentrations will default to a value defined in the CHEMPARAM file. If any additional species appear on AIRQUALITY, they will be ignored.

2. Methods

The methods that can be used to generate the AIRQUALITY file are:

- > CONSTANT
- > GRID VALUE
- > STATINTERP
- > POISSON




Figure VII-1. Information Flow Diagram for the AIRQUALITY File

- > SPLIT/COMB
- > E-WINTERP
- > N-SINTERP
- > USER.

These methods are discussed in detail in Section VI.A.6.

Since the AIRQUALITY file varies in the vertical direction, a vertical method must also be specified for each output variable in each sub-region. The vertical methods that can be used are:

- > CONSTANT
- > ABSPROFILE
- > RELPROFILE
- > ABSPROFRAT
- > RELPROFRAT
- > E-WINTERP
- > N-SINTERP
- > VERTUSER.

These vertical methods are discussed in detail in Section VI.A.7.

3. Time Variation

The concentrations on the AIRQUALITY file are used as initial conditions for the Airshed Simulation Program. The time span of the file must therefore include the beginning simulation time. Furthermore, the time interval containing the data to be used must begin at or before the simulation starting time and must end after the simulation starting time. In the example in Exhibit VII-1 in this chapter, the time interval for the initial concentrations is 0500 to 0501.

4. Packets

Figure VII-2 shows the input deck structure in terms of the packets to be used. Each of these packets is described in detail in Section VI.B. Following are special input packet considerations for the file:

> CONTROL

- The file name on Card 2 must be AIRQUALITY.
- The control variables to be specified on Cards 4 to 8 for AIRQUALITY are shown in Table VII-1.
- The number of species must be greater than zero.
- If there are input variables that do not appear as output variables, their number must appear as the number of user-defined variables. All such variables must also be named.
- If data from measuring stations are to be used (methods STATINTERP or POISSON), the maximum number of such stations must be given.
- The number of subregions must be at least one.
- The maximum number of parameters must be sufficient to include all specifications of all parameters.
- The vertical controls card (No. 7) must include maximum vertical parameter and profile entries as applicable.
- The file unit assignment card (No. 8) must provide entries for the DIFFBREAK, REGIONTOP, and TOPCONC files if, and only if, these files are required by the vertical methods selected.
- The beginning and ending dates and times should reflect the time variation considerations discussed in Section 3 above.
- A set of output species names is required; their number must be the same as the entry in the first control parameter on Card 4. If either the ABSPROFRAT or RELPROFRAT vertical method is selected for any variable, the output species names specified here must match the species names on the TOPCONC file.




Figure VII-2. Input Card Deck Structure for Preparing the AIRQUALITY File

Table VII-1. CONTROL Packet Entries for
the AIRQUALITY File

<u>Card Number</u>	<u>Entry</u>
4	Number of species Number of user-defined variables Number of stations Number of subregions Number of parameters Spare
5	Output file number Print input cards Print output grid Spare Spare Spare
6	Print units table Print station locations table Print regional grid Print methods table Print station values table Spare
7	Number of vertical parameters Number of heights in profile Print vertical methods table Print vertical profile tables Spare Spare
8	DIFFBREAK file number REGIONTOP file number TOPCONC file number Spare Spare Spare

- > REGION. This packet must follow the CONTROL packet. The vertical parameters must be provided for the AIRQUALITY file.
- > UNITS. This packet, if present, must follow the REGION packet. The UNITS packet must be provided if:
 - Any input variable will be input in other than internal units.
 - Any user-defined variables are specified.
 - COORD or HEIGHT unit conversions are to be used.
 The number of user-defined variables must not exceed the maximum specified in the CONTROL packet.
- > STATIONS. This packet is required if either of the methods STATINTERP or POISSON is specified. The number of stations listed must not exceed the maximum specified in the CONTROL packet.
- > TIME INTERVAL. One or more TIME INTERVAL packets must be present. The first time interval must begin at or before the beginning of the time span specified on Card 10 of the CONTROL packet. All time intervals must be contiguous and of nonzero length. Each TIME INTERVAL packet contains one or more of the following packets and ends with an ENDTIME card. Following the first time interval, only those data that are to be changed need be specified.
- > SUBREGION. The first time interval must contain a SUBREGION packet; the inclusion of this packet in other time intervals is optional. The number of subregions must not exceed the maximum specified in the CONTROL packet.
- > METHOD. A method must be provided for every variable--including user-defined variables--in every subregion in the first time interval. Methods can be changed in subsequent TIME INTERVAL packets if desired. Note that each parameter entry contributes to the overall parameter count; the total number of parameters must not exceed the maximum specified in the CONTROL packet.

- > VERTICAL METHOD. A vertical method must be provided for every variable--including user-defined variables--in every subregion in the first time interval. Vertical methods can be changed in subsequent TIME INTERVAL packets if desired. Note that each vertical parameter entry contributes to the overall vertical parameter count; the total must not exceed the maximum specified in the CONTROL packet.
- > CONSTANTS. If the method CONSTANT is assigned to any variable in the METHOD packet, the first time interval must contain a CONSTANTS packet. More than one CONSTANTS packet can appear in any time interval.
- > GRID VALUES. If the method GRID VALUE is assigned to any variable in the METHOD packet, the first time interval must contain a GRID VALUES packet. More than one GRID VALUES packet can appear in any time interval.
- > STATION READINGS. If either the POISSON or STATINTERP method is assigned to any species in the METHOD packet, the first time interval must contain a STATION READINGS packet. More than one STATION READINGS packet can appear in any time interval.
- > VERTICAL PROFILES. If any of the profile methods are assigned to any species in the VERTICAL METHOD packet, the first time interval must contain a VERTICAL PROFILES packet. There must be a vertical profile defined (or implied using ALL) for every variable in every subregion for which a profile method was specified. The number of height-value pairs in any single profile must not exceed the maximum specified in the CONTROL packet. More than one VERTICAL PROFILES packet can appear in any time interval.

5. Additional Input Files

If any vertical method besides CONSTANT was selected, the DIFFBREAK and REGIONTOP files must be input to AIRQUL. In addition, if either of

the vertical methods ABSPROFRAT or RELPROFRAT was selected, the TOPCONC file must also be input.

6. Examples

Exhibit VII-1 shows a sample input deck for AIRQUALITY file generation. The output from an AIRQUL run using that input deck is shown in Exhibit VII-2.

CONTINUL								
AIR QUALITY								
INITIAL POLLUTANT CONCENTRATIONS								
11	1	25	1	30	76195			5
21	1	1						
5	5	1	1					
11	12	13						
NO								
NO2								
O3								
ETH								
OLE								
PAR								
CARB								
ARO								
BZA								
PAN								
CO								
76195	500	76195	501					
END								
REGION								
725000.	4252000.	15						
-19000.	-16000.							
4000.	4000.							
17	22	4						
2	2	0.	50.0	200.				
END								

Exhibit VII-1. Sample Input Deck for the AIRQUL Program

STATIONS

101	19183.	27862.	10.
102	17510.	34045.	10.
103	22598.	30467.	10.
104	22312.	25304.	10.
105	18706.	24453.	10.
106	13660.	25566.	10.
107	15179.	30610.	10.
108	23407.	39102.	10.
109	30802.	27886.	10.
110	22209.	20826.	10.
111	13812.	20479.	10.
112	8938.	28913.	10.
113	12738.	37820.	10.
114	19320.	45456.	10.
115	32111.	45799.	10.
116	37777.	38083.	10.
117	35560.	20818.	10.
118	18065.	11256.	10.
119	4759.	18547.	10.
120	-1921.	33909.	10.
121	7414.	50376.	10.
122	16631.	77223.	10.
123	52320.	34378.	10.
124	24275.	-15463.	10.

END	125	-27555.	30240.	10.
TIME INTERVAL				
	76195	500	76195	501
SUBREGION				
A		1	1	-1
END				

Exhibit VII-1 (Continued)

METHOD	NO	POISSON	.00100	1.00	3
A					
MAXITER	100				
ERRORTOL	.001000				
OMEGA	1.4				
A					
MAXITER	100	POISSON	.00100	1.00	3
ERRORTOL	.001000				
OMEGA	1.4				
A					
MAXITER	100	POISSON	.00100	1.00	3
ERRORTOL	.001000				
OMEGA	1.4				
A					
MAXITER	100	POISSON	.05000	4.00	3
ERRORTOL	.050000				
OMEGA	1.4				
A					
ETH		SPLIT/COMB	.00100	4.00	1
RHC	.0217				
A		SPLIT/COMB	.00100	4.00	1
RHC	.0440				
A		SPLIT/COMB	.01000	4.00	1
RHC	.6665				
A		SPLIT/COMB	.00100	4.00	1
RHC	.0810				
A		SPLIT/COMB	.00010	4.00	1
RHC	.0240				
A		SPLIT/COMB	.00000	4.00	1
RHC	.0001				
A		CONSTANT	.00001	.10	0
CO		POISSON	.10000	20.00	3
MAXITER	100				
ERRORTOL	.100000				
OMEGA	1.4				
END					
VERTICAL METHOD					
ALL	ALL	RELPROFRAT	.0000	100.0	
END					
CONSTANTS					
A	PAN	.000010			
END					

Exhibit VII-1 (Continued)

STATION READINGS

INITIAL COND 500

101	03	.024
102	03	-.9.000
103	03	.027
104	03	-.9.000
105	03	.002
106	03	.022
107	03	.030
108	03	.027
109	03	.038
110	03	.035
111	03	-.9.000
112	03	.028
113	03	.034
114	03	.036
115	03	-.9.000
116	03	.035
117	03	.036
118	03	-.9.000
119	03	.029
120	03	.019
121	03	.002
122	03	.043
123	03	-.9.000
124	03	.024
125	03	.003
101	CO	.254
102	CO	.050
103	CO	.174
104	CO	-.9.000
105	CO	.050
106	CO	.185
107	CO	.226
108	CO	.055
109	CO	.050
110	CO	-.9.000
111	CO	.059
112	CO	.267
113	CO	.209
114	CO	.109
115	CO	.050
116	CO	-.9.000
117	CO	.148
118	CO	.050
119	CO	.320
120	CO	.239
121	CO	.108
122	CO	.050

123	CO	.175
124	CO	.256
125	CO	.077
101	RHC	-9.000
102	RHC	.131
103	RHC	.086
104	RHC	.178
105	RHC	-9.000
106	RHC	.196
107	RHC	.146
108	RHC	.060
109	RHC	-9.000
110	RHC	-9.000
111	RHC	.082
112	RHC	.117
113	RHC	.050
114	RHC	-9.000
115	RHC	-9.000
116	RHC	-9.000
117	RHC	-9.000
118	RHC	-9.000
119	RHC	.050
120	RHC	.474
121	RHC	-9.000
122	RHC	-9.000
123	RHC	-9.000
124	RHC	-9.000
125	RHC	-9.000
101	NO	.002
102	NO	.002
103	NO	.003
104	NO	.002
105	NO	-9.000
106	NO	.002
107	NO	.003
108	NO	.005
109	NO	.002
110	NO	.002
111	NO	.002
112	NO	.002
113	NO	.003
114	NO	.002
115	NO	.002
116	NO	.002
117	NO	.002

Exhibit VII-1 (Continued)

118	NO	.002
119	NO	.002
120	NO	.003
121	NO	.002
122	NO	.002
123	NO	.002
124	NO	.002
125	NO	.002
101	NO2	.020
102	NO2	.004
103	NO2	.010
104	NO2	-9.000
105	NO2	-9.000
106	NO2	.002
107	NO2	.011
108	NO2	.010
109	NO2	.002
110	NO2	.005
111	NO2	.018
112	NO2	.016
113	NO2	.010
114	NO2	.008
115	NO2	.002
116	NO2	.002
117	NO2	.002
118	NO2	.003
119	NO2	.011
120	NO2	.022
121	NO2	.005
122	NO2	.002
123	NO2	.002
124	NO2	.003
125	NO2	.002

END	VERTICAL PROFILE	35296.	5038.	4
A	ALL	0.		
	0.	0.		
	100.	0.		
	120.	1.		
	500.	1.		
END	ENDTIME			

PROCESSING OF INPUT DATA FOR THE PREPARATION OF FILE AIRQUALITY

INITIAL POLLUTANT CONCENTRATIONS ST LOUIS 500 76195

NUMBER OF USER-DEFINED VARIABLES =	1	
NUMBER OF STATIONS =	25	
NUMBER OF SUBREGIONS =	1	
NUMBER OF METHOD PARAMETERS =	30	
NUMBER OF VERTICAL METHOD PARAMETERS =	5	
NUMBER OF VERTICAL PROFILE HEIGHTS =	5	
PROGRAM OUTPUT WILL BE PLACED ON FILE NUMBER	21	
INPUT DATA FOR DIFFUSION BREAK WILL BE OBTAINED FROM FILE NUMBER	11	
INPUT DATA FOR REGION TOP WILL BE OBTAINED FROM FILE NUMBER	12	
INPUT DATA FOR TOP CONCENTRATIONS WILL BE OBTAINED FROM FILE NUMBER	13	
INPUT CARDS WILL BE PRINTED		
OUTPUT GRID WILL BE PRINTED		
UNIT TABLE WILL NOT BE PRINTED		
STATION LOCATIONS WILL NOT BE PRINTED		
SUBREGION GRID WILL NOT BE PRINTED		
METHOD TABLE WILL BE PRINTED		
STATION VALUES WILL NOT BE PRINTED		
VERTICAL METHOD TABLE WILL BE PRINTED		
VERTICAL PROFILE VALUES WILL NOT BE PRINTED		
BEGINNING DATE OF FILE	76195	BEGINNING TIME OF FILE 5.00
ENDING DATE OF FILE	76195	ENDING TIME OF FILE 5.02

Exhibit VII-2. Sample Output From the AIRQUL Program

A TOTAL OF 11 SPECIES NAMES WERE READ, THE SPECIES NAMES ARE --

NO			
NO2			
O3			
ETH			
OLE			
PAR			
CARB			
ARO			
BZA			
PAI			
CO			
REGION	15		
	72500.	425200.	
	-19000.	-16000.	
	4000.00	4000.00	
	17	22	
	2	2	
	.00	50.00	200.00
END			

Exhibit VII-2 (Continued)

REGIONAL DEFINITION

UTM ORIGIN X-COORDINATE	725000.
UTM ORIGIN Y-COORDINATE	4252000.
UTM ORIGIN ZONE NUMBER	15
REGION ORIGIN X-COORDINATE	-19000.
REGION ORIGIN Y-COORDINATE	-16000.
CELL LENGTH IN X-DIRECTION	4000.00
CELL LENGTH IN Y-DIRECTION	4000.00
NUMBER OF CELLS IN X-DIRECTION	17
NUMBER OF CELLS IN Y-DIRECTION	22
NUMBER OF CELLS IN Z-DIRECTION	4
NUMBER OF CELLS IN LOWER VERTICAL LAYER .	2
NUMBER OF CELLS IN UPPER VERTICAL LAYER	2
HEIGHT OF SURFACE LAYER	.00
MINIMUM CELL HEIGHT IN LOWER LAYER	50.00
MINIMUM CELL HEIGHT IN UPPER LAYER	200.00
UNITS	
RHC	PPH 1.0000 .0000 .0000
END	.0000 .0000 .0000

Exhibit VII-2 (Continued)

STATIONS			
101	19183.	27862.	10.00
102	17518.	34045.	10.00
103	22588.	30467.	10.00
104	22312.	25304.	10.00
105	18706.	24453.	10.00
106	13660.	25566.	10.00
107	15179.	30610.	10.00
108	23407.	39102.	10.00
109	30802.	27886.	10.00
110	22209.	20826.	10.00
111	13812.	20479.	10.00
112	8938.	28913.	10.00
113	12738.	37820.	10.00
114	19320.	45456.	10.00
115	32111.	45799.	10.00
116	37777.	38083.	10.00
117	35560.	20818.	10.00
118	18065.	11256.	10.00
119	4759.	18547.	10.00
120	-1921.	33909.	10.00
121	7414.	50376.	10.00
122	16631.	77223.	10.00
123	52320.	34378.	10.00
124	24275.	-15463.	10.00
125	-27555.	30240.	10.00
END	0.	0.	.00

Exhibit VII-2 (Continued)

TIME INTERVAL	500	76195	501
SUBREGION	1	1	-1
A	0	0	0
END			
METHOD			
A	NO	POISSON	.0010
MAXITER	1000.0000		
ERRORTOL	.0010		
OMEGA	1.4000		
A	NO2	POISSON	.0010
MAXITER	1000.0000		
ERRORTOL	.0010		
OMEGA	1.4000		
A	O3	POISSON	.0010
MAXITER	1000.0000		
ERRORTOL	.0010		
OMEGA	1.4000		
A	RHC	POISSON	.0500
MAXITER	1000.0000		
ERRORTOL	.0500		
OMEGA	1.4000		
A	E7H	SPLIT/COMB	.0010
RHC	.0217		
A	OLE	SPLIT/COMB	.0010
RHC	.0440		
A	PAR	SPLIT/COMB	.0100
RHC	.6665		
A	CARB	SPLIT/COMB	.0010
RHC	.0810		
A	ARO	SPLIT/COMB	.0001
RHC	.0248		
A	BZA	SPLIT/COMB	.0000
RHC	.0001		
A	PAN	CONSTANT	.0000
A	CO	POISSON	.1000
MAXITER	1000.0000		
ERRORTOL	.1000		
OMEGA	1.4000		
END			

Exhibit VII-2 (Continued)

METHODS TABLE

SUBREGION	VARIABLE	METHOD	MIN. VALUE	MAX. VALUE	PARAMETER	PAR. VALUE
A	NO	POISSON	.0010	1.0000	MAXITER ERRORTOL OMEGA	1000.0000 .0010 1.4000
A	NO2	POISSON	.0010	1.0000	MAXITER ERRORTOL OMEGA	1000.0000 .0010 1.4000
A	O3	POISSON	.0010	1.0000	MAXITER ERRORTOL OMEGA	1000.0000 .0010 1.4000
A	ETH	SPLIT/COMB	.0010	4.0000	RHC	.0217
A	OLE	SPLIT/COMB	.0010	4.0000	RHC	.0440
A	PAR	SPLIT/COMB	.0100	4.0000	RHC	.6665
A	CARB	SPLIT/COMB	.0010	4.0000	RHC	.0810
A	ARO	SPLIT/COMB	.0001	4.0000	RHC	.0248
A	BZA	SPLIT/COMB	.0000	4.0000	RHC	.0001
A	PAN	CONSTANT	.0000	.1000		
A	CO	POISSON	.1000	20.0000		
A	RHC	POISSON	.0500	4.0000	MAXITER ERRORTOL OMEGA	1000.0000 .1000 1.4000
VERTICAL METHOD					MAXITER ERRORTOL OMEGA	1000.0000 .0500 1.4000
ALL	RELPROFRAT	.0000	100.0000	0		
END		.0000	.0000	0		

Exhibit VII-2 (Continued)

METHODS TABLE						
SUBREGION	VARIABLE	METHOD	MIN. VALUE	MAX. VALUE	PARAMETER	PAR. VALUE
A	NO	RELPROFRAT	.0000	100.0000		
A	NO2	RELPROFRAT	.0000	100.0000		
A	O3	RELPROFRAT	.0000	100.0000		
A	ETH	RELPROFRAT	.0000	100.0000		
A	OLE	RELPROFRAT	.0000	100.0000		
A	PAR	RELPROFRAT	.0000	100.0000		
A	CARB	RELPROFRAT	.0000	100.0000		
A	ARO	RELPROFRAT	.0000	100.0000		
A	BZA	RELPROFRAT	.0000	100.0000		
A	PAN	RELPROFRAT	.0000	100.0000		
A	CO	RELPROFRAT	.0000	100.0000		
A	RHC	RELPROFRAT	.0000	100.0000		
CONSTANTS						
A	PAN		.0000			
END			.0000			

Exhibit VII-2 (Continued)

STATION READINGS

INITIAL COND 500

101	03	.0240
102	03	-9.0300
103	03	.0270
104	03	-9.0000
105	03	.0020
106	03	.0220
107	03	.0300
108	03	.0270
109	03	.0380
110	03	.0350
111	03	-9.0000
112	03	.0280
113	03	.0340
114	03	.0360
115	03	-9.0000
116	03	.0350
117	03	.0360
118	03	-9.0000
119	03	.0290
120	03	.0190
121	03	.0020
122	03	.0430
123	03	-9.0000
124	03	.0240
125	03	.0030
101	CO	.2540
102	CO	.0500
103	CO	.1740
104	CO	-9.0000
105	CO	.0500
106	CO	.1850
107	CO	.2260
108	CO	.0550
109	CO	.0500
110	CO	-9.0000
111	CO	.0590
112	CO	.2670
113	CO	.2090
114	CO	.1090
115	CO	.0500
116	CO	-9.0000
117	CO	.1480
118	CO	.0500
119	CO	.3200
120	CO	.2390
121	CO	.1080
122	CO	.0500
123	CO	.1750
124	CO	.2560
125	CO	.0770

101	RHC	-9.0000
102	RHC	.1310
103	RHC	.0860
104	RHC	.1780
105	RHC	-9.0000
106	RHC	.1960
107	RHC	.1460
108	RHC	.0600
109	RHC	-9.0000
110	RHC	-9.0000
111	RHC	.0820
112	RHC	.1170
113	RHC	.0500
114	RHC	-9.0000
115	RHC	-9.0000
116	RHC	-9.0000
117	RHC	-9.0000
118	RHC	-9.0000
119	RHC	.0500
120	RHC	.4740
121	RHC	-9.0000
122	RHC	-9.0000
123	RHC	-9.0000
124	RHC	-9.0000
125	RHC	-9.0000
101	NO	.0020
102	NO	.0020
103	NO	.0030
104	NO	.0020
105	NO	-9.0000
106	NO	.0020
107	NO	.0030
108	NO	.0050
109	NO	.0020
110	NO	.0020
111	NO	.0020
112	NO	.0020
113	NO	.0030
114	NO	.0020
115	NO	.0020
116	NO	.0020
117	NO	.0020
118	NO	.0020

119	NO	.0020	
120	NO	.0030	
121	NO	.0020	
122	NO	.0020	
123	NO	.0020	
124	NO	.0020	
125	NO	.0020	
101	NO2	.0200	
102	NO2	.0040	
103	NO2	.0100	
104	NO2	-9.0000	
105	NO2	-9.0000	
106	NO2	.0020	
107	NO2	.0110	
108	NO2	.0100	
109	NO2	.0020	
110	NO2	.0050	
111	NO2	.0160	
112	NO2	.0100	
113	NO2	.0080	
114	NO2	.0020	
115	NO2	.0020	
116	NO2	.0020	
117	NO2	.0020	
118	NO2	.0030	
119	NO2	.0110	
120	NO2	.0220	
121	NO2	.0050	
122	NO2	.0020	
123	NO2	.0020	
124	NO2	.0030	
125	NO2	.0020	
END		.0000	
VERTICAL PROFILE			
A	ALL	35296.0000 5038.0000	4
	0.	.0000	
	100.	.0000	
	120.	1.0000	
	503.	1.0000	
END		.0000	0
ENDTIME			

FILE NAME --- AIRQUALITY		INITIAL POLLUTANT CONCENTRATIONS ST LOUIS 500 76195										PAGE 1
AIR QUALITY VALUES (IN PARTS PER MILLION) SPECIES NO		VERT. LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 5.02										
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12
22	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020
21	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020
20	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0021	.0021	.0021
19	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0021	.0021	.0021	.0021
18	.0020	.0020	.0020	.0020	.0021	.0021	.0020	.0021	.0021	.0021	.0021	.0021
17	.0020	.0020	.0020	.0021	.0021	.0021	.0020	.0021	.0022	.0021	.0022	.0022
16	.0020	.0020	.0021	.0021	.0022	.0022	.0022	.0023	.0023	.0020	.0025	.0024
15	.0020	.0020	.0021	.0022	.0023	.0024	.0024	.0026	.0026	.0028	.0033	.0029
14	.0020	.0020	.0022	.0023	.0025	.0025	.0026	.0030	.0028	.0032	.0050	.0034
13	.0020	.0020	.0022	.0024	.0030	.0026	.0024	.0026	.0026	.0020	.0033	.0030
12	.0020	.0020	.0021	.0023	.0024	.0023	.0020	.0025	.0030	.0025	.0030	.0026
11	.0020	.0020	.0020	.0021	.0022	.0021	.0021	.0022	.0020	.0020	.0020	.0021
10	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0021	.0020	.0020	.0020	.0020
9	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020
8	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020
7	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020
6	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020
5	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020
4	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020
3	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020
2	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020
1	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020

Exhibit VII-2 (Continued)

FILE NAME -- AIRQUALITY INITIAL POLLUTANT CONCENTRATIONS ST LOUIS 500 76195

AIR QUALITY VALUES (IN PARTS PER MILLION) SPECIES NO VERT. LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 5.02

GRID CELL 13 14 15 16 17

22	.0020	.0020	.0020	.0020	.0020
21	.0020	.0020	.0020	.0020	.0020
20	.0021	.0021	.0020	.0020	.0020
19	.0021	.0021	.0021	.0020	.0020
18	.0021	.0021	.0021	.0020	.0020
17	.0021	.0021	.0021	.0020	.0020
16	.0020	.0021	.0021	.0020	.0020
15	.0025	.0022	.0021	.0020	.0020
14	.0027	.0023	.0020	.0020	.0020
13	.0026	.0023	.0021	.0020	.0020
12	.0023	.0022	.0021	.0020	.0020
11	.0020	.0020	.0020	.0020	.0020
10	.0020	.0020	.0020	.0020	.0020
9	.0020	.0020	.0020	.0020	.0020
8	.0020	.0020	.0020	.0020	.0020
7	.0020	.0020	.0020	.0020	.0020
6	.0020	.0020	.0020	.0020	.0020
5	.0020	.0020	.0020	.0020	.0020
4	.0020	.0020	.0020	.0020	.0020
3	.0020	.0020	.0020	.0020	.0020
2	.0020	.0020	.0020	.0020	.0020
1	.0020	.0020	.0020	.0020	.0020

Exhibit VII-2 (Concluded)

B. BOUNDARY

The BOUNDARY file contains a time-invariant definition of the boundaries of the region to be modeled and time-varying matrices of pollutant concentrations in each external boundary cell. These boundary values are used by the Airshed Simulation Program to represent pollutant concentrations passing over the boundary into the modeling region. The program BNDARY is used to create the BOUNDARY file. BNDARY requires subroutines from the libraries UTILITY and FILUTIL. Figure VII-3 is an information flow diagram illustrating the job control to be used. In the following sections we discuss the input to the BNDARY program.

1. Variables

The output variables for the BOUNDARY file are the species named in the CONTROL packet. Additional user-defined input variables (e.g., "reactive hydrocarbons") can be specified in the UNITS packet. The internal units for the concentrations of all species except AEROSOLS are parts per million (ppm); for AEROSOLS, the units are micrograms per cubic meter ($\mu\text{g}/\text{m}^3$). The standard names for reactive species recognized by the Airshed Simulation Program are listed in Section IX.A. If any of these species does not appear on the BOUNDARY file, the boundary concentrations will default to a value defined in the CHEMPARAM file. If any additional species appear on BOUNDARY, they will be ignored.

2. Methods

The methods that can be used to generate the BOUNDARY file are:

- > CONSTANT
- > BOUNDVALUE
- > SPLIT/COMB
- > USER.

The methods CONSTANT and BOUNDVALUE are equivalent. All these methods are discussed in detail in Section VI.A.6.




Figure VII-3. Information Flow Diagram for the BOUNDARY File

Since the BOUNDARY file varies in the vertical direction, a vertical method must also be specified for each output variable in each subregion. The vertical methods that can be used are:

- > CONSTANT
- > ABSPROFILE
- > RELPROFILE
- > ABSPROFRAT
- > RELPROFRAT
- > VERTUSER.

These vertical methods are discussed in detail in Section VI.A.7.

3. Time Variation

The time span of the BOUNDARY file must include the entire time span of the simulation runs for which it is to be used. Boundary concentrations are considered to be constant during each time interval.

4. Packets

Figure VII-4 shows the input deck structure in terms of the packets to be used. Each of these packets is described in detail in Section VI.B. Following are special input packet considerations for the BOUNDARY file:

- > CONTROL
 - The file name on Card 2 must be BOUNDARY.
 - The control variables to be specified on Cards 4 to 8 for BOUNDARY are shown in Table VII-2.
 - The number of species must be greater than zero.
 - If there are input variables that do not appear as output variables, their number must appear as the number of user-defined variables. All such variables must also be named in the UNITS packet.




Figure VII-4. Input Card Deck Structure for Preparing the BOUNDARY File

Table VII-2. CONTROL Packet Entries for the BOUNDARY File

<u>Card Number</u>	<u>Entry</u>
4	Number of species
	Number of user-defined variables
	Number of boundary line segments
	Spare
	Number of parameters
	Spare
5	Output file number
	Print input cards
	Print output boundary values
	Spare
	Spare
	Spare
6	Print units table
	Print boundary line segment locations table
	Print regional grid
	Print methods table
	Print boundary values table
	Spare
7	Number of vertical parameters
	Number of heights in profile
	Print vertical methods table
	Print vertical profile tables
	Spare
	Spare
8	DIFFBREAK file number
	REGIONTOP file number
	TOPCONC file number
	Spare
	Spare
	Spare

- The number of boundary line segments must be at least three.
 - The maximum number of parameters must be sufficient to include all specifications of all parameters.
 - The vertical controls card (No. 7) must include maximum vertical parameter and profile entries as applicable.
 - The file unit assignment card (No. 8) must provide entries for the DIFFBREAK, REGIONTOP, and TOPCONC files if, and only if, these files are required by the vertical methods selected.
 - The beginning and ending dates and times should reflect the time variation considerations discussed in Section 3 above.
 - A set of output species names is required; their number must be the same as the entry in the first control parameter on Card 4. If either the ABSPROFRAT or RELPROFRAT vertical method is selected for any variable, the output species names specified here must match the species names on the TOPCONC file.
- > REGION. This packet must follow the CONTROL packet. The vertical parameters must be provided for the BOUNDARY file.
 - > UNITS. This packet, if present, must follow the REGION packet. The UNITS packet must be provided if:
 - Any input variable will be input in other than internal units.
 - Any user-defined variables are specified.
 - COORD or HEIGHT unit conversions are to be used.
 The number of user-defined variables must not exceed the maximum specified in the CONTROL packet.
 - > BOUNDARIES. This packet is required; it names the line segments that define the boundaries of the region. The number of line segments specified must equal the number specified in the CONTROL packet.

- > TIME INTERVAL. One or more TIME INTERVAL packets must be present. The first time interval must begin at or before the beginning of the time span specified on Card 10 of the CONTROL packet. All time intervals must be contiguous and of nonzero length. Each TIME INTERVAL packet contains one or more of the following packets and ends with an ENDTIME card. Following the first time interval, only those data that are to be changed need be specified.
- > METHOD. A method must be provided for every variable--including user-defined variables--for every boundary line segment in the first time interval. In the METHOD packet, the boundary line segment name is entered in the "subregion" field. Methods can be changed in subsequent TIME INTERVAL packets if desired. Note that each parameter entry contributes to the overall parameter count; the total number of parameters must not exceed the maximum specified in the CONTROL packet.
- > VERTICAL METHOD. A vertical method must be provided for every variable--including user-defined variables--for every boundary line segment in the first time interval. In the VERTICAL METHOD packet, the boundary line segment name is entered in the "subregion" field. Vertical methods can be changed in subsequent TIME INTERVAL packets if desired. Note that each vertical parameter entry contributes to the overall vertical parameter count; the total must not exceed the maximum specified in the CONTROL packet.
- > CONSTANTS. If the method CONSTANT is assigned to any variable in the METHOD packet, the first time interval must contain a CONSTANTS packet. More than one CONSTANTS packet can appear in any time interval.
- > BOUNDARY READINGS. If the method BOUNDVALUE is assigned to any variable in the METHOD packet, the first time interval must contain a BOUNDARY READINGS packet. More than one BOUNDARY READINGS packet can appear in any time interval.

- > VERTICAL PROFILES. If any of the profile methods are assigned to any species in the VERTICAL METHOD packet, the first time interval must contain a VERTICAL PROFILES packet. There must be a vertical profile defined (or implied using ALL) for every variable for every boundary line segment for which a profile method was specified. In the VERTICAL PROFILES packet, the boundary line segment name is entered in the "subregion" field. The number of height-value pairs in any single profile must not exceed the maximum specified in the CONTROL packet. More than one VERTICAL PROFILES packet can appear in any time interval.

5. Additional Input Files

If any vertical method besides CONSTANT was selected, the DIFFBREAK and REGIONTOP files must be input to BNDARY. In addition, if the vertical method ABSPROFRAT or RELPROFRAT was selected, the TOPCONC file must also be input.

6. Examples

Exhibit VII-3 shows a sample input deck for BOUNDARY file generation. The output from a BNDARY run using that input deck is shown in Exhibit VII-4.

CONTROL									
BOUNDARY									
BOUNDARY	11	1	4	1	10				
DEFINITION	22	1	1						
AND	1	1	1						
CONCENTRATIONS	5	5		0					
	11	12	13						
NO									
NO2									
O3									
ETH									
OLE									
PAR									
CARB									
ARO									
BZA									
PAN									
CO	76195	500	76195	2400					
END									
REGION	725000.	4252000.	15						
	-19000.	-16000.							
	4000.	4000.							
	17	22	4						
	2	2	0.	50.	200.				
END									
UNITS									
RHC			1.						
END									
BOUNDARIES									
TOP	-13000.	66000.	43000.	66000.					
BOTTOM	-13000.	-10000.	43000.	-10000.					
LEFT	-13000.	-10000.	-13000.	66000.					
RIGHT	43000.	-10000.	43000.	66000.					
END									

Exhibit VII-3. Sample Input Deck for the BNDARY Program

TIME INTERVAL		500	76195	600	
76195					
METHOD	NO	BOUNDVALUE	BOUNDVALUE	0.0	90.
ALL	NO2	BOUNDVALUE	BOUNDVALUE	0.0	90.
ALL	O3	BOUNDVALUE	BOUNDVALUE	0.0	90.
ALL	RHC	BOUNDVALUE	BOUNDVALUE	0.0	90.
ALL	PAN	BOUNDVALUE	BOUNDVALUE	0.0	90.
ALL	CO	BOUNDVALUE	BOUNDVALUE	0.0	90.
ALL	ETH	SPLIT/COMB	SPLIT/COMB	0.0	10.
RHC		.0217			1
ALL	OLE	SPLIT/COMB	SPLIT/COMB	0.0	10.
RHC		.0440			1
ALL	PAR	SPLIT/COMB	SPLIT/COMB	0.001	10.
RHC		.6665			1
ALL	CARB	SPLIT/COMB	SPLIT/COMB	0.0	10.
RHC		.0810			1
ALL	ARO	SPLIT/COMB	SPLIT/COMB	0.0	10.
RHC		.0248			1
ALL	BZA	SPLIT/COMB	SPLIT/COMB	0.0	10.
RHC		.0001			1
END					
VERTICAL METHOD					
ALL	ALL	RELPROFRAT		.0000	100.0
END					

Exhibit VII-3 (Continued)

BOUNDARY READINGS		
ALL	PAN	.00001
TOP	O3	.023
RIGHT	O3	.026
BOTTOM	O3	.026
LEFT	O3	.023
TOP	CO	.121
RIGHT	CO	.192
BOTTOM	CO	.192
LEFT	CO	.121
TOP	RHC	.079
RIGHT	RHC	.050
BOTTOM	RHC	.050
LEFT	RHC	.079
TOP	NO	.003
RIGHT	NO	.002
BOTTOM	NO	.002
LEFT	NO	.003
TOP	NO2	.007
RIGHT	NO2	.002
BOTTOM	NO2	.002
LEFT	NO2	.007
END		
VERTICAL PROFILE		
ALL	ALL	35296.
	0.	0.
	102.	0.
	122.	1.
	5000.	1.
END		
ENDTIME		

PROCESSING OF INPUT DATA FOR THE PREPARATION OF FILE BOUNDARY
BOUNDARY DEFINITION AND CONCENTRATIONS

NUMBER OF USER-DEFINED VARIABLES = 1
 NUMBER OF BOUNDARY LINES = 4
 NUMBER OF METHOD PARAMETERS = 10
 NUMBER OF VERTICAL METHOD PARAMETERS = 5
 NUMBER OF VERTICAL PROFILE HEIGHTS = 5
 PROGRAM OUTPUT WILL BE PLACED ON FILE NUMBER 22
 INPUT DATA FOR DIFFUSION BREAK WILL BE OBTAINED FROM FILE NUMBER 11
 INPUT DATA FOR REGION TOP WILL BE OBTAINED FROM FILE NUMBER 12
 INPUT DATA FOR TOP CONCENTRATIONS WILL BE OBTAINED FROM FILE NUMBER 13
 INPUT CARDS WILL BE PRINTED
 OUTPUT GRID WILL BE PRINTED
 UNIT TABLE WILL BE PRINTED
 BOUNDARY LINE TABLE WILL BE PRINTED
 BOUNDARY LINE MAP WILL BE PRINTED
 INPUT VALUES METHOD TABLE WILL NOT BE PRINTED
 BOUNDARY VALUES WILL NOT BE PRINTED
 VERTICAL METHOD TABLE WILL NOT BE PRINTED
 VERTICAL PROFILE VALUES WILL NOT BE PRINTED
 BEGINNING DATE OF FILE 76195 BEGINNING TIME OF FILE 5.00
 ENDING DATE OF FILE 76195 ENDING TIME OF FILE 24.00

A TOTAL OF 11 SPECIES NAMES WERE READ, THE SPECIES NAMES ARE --

NO			
NO2			
O3			
ETH			
OLE			
PAR			
CARB			
ARO			
BZA			
PAN			
CO			
REGION		15	
	725000.	4252000.	
	-19000.	-16000.	
	4000.00	4000.00	
	17	22	
	2	2	
			4
			.00
			50.00
			200.00
END			

VARIABLE NAME	UNIT NAME	UNIT CONVERSION TABLE	
		MULTIPLICATIVE FACTOR	ADDITIVE FACTOR
ND		-9.00000000	-9.00000000
ND2		-9.00000000	-9.00000000
O3		-9.00000000	-9.00000000
ETH		-9.00000000	-9.00000000
OLE		-9.00000000	-9.00000000
PAR		-9.00000000	-9.00000000
CARB		-9.00000000	-9.00000000
ARO		-9.00000000	-9.00000000
BZA		-9.00000000	-9.00000000
PAN		-9.00000000	-9.00000000
CO		-9.00000000	-9.00000000
RHC	PPH	1.00000000	-9.00000000
COORD		-9.00000000	-9.00000000
HEIGHT		-9.00000000	-9.00000000
BOUNDARIES			
TOP	-13000.	66000.	66000.
BOTTOM	-13000.	43000.	-10000.
LEFT	-13000.	-13000.	66000.
RIGHT	43000.	43000.	66000.
END	0.	0.	0.

Exhibit VII-4 (Continued)

BOUNDARY LINE LOCATION TABLE

B. LINE NAME	X-BEGINNING(GRID SQ)	X-ENDING (GRID SQ)	Y-BEGINNING (GRID SQ)	Y-ENDING(GRID SQ)
TOP	1.50	15.50	20.50	20.50
BOTTOM	1.50	15.50	1.50	1.50
LEFT	1.50	1.50	1.50	20.50
RIGHT	15.50	15.50	1.50	20.50
***** NOTE ***** BOUNDARY LINES LEFT AND BOTTOM INTERSECT IN CELL (2, 2).				
THIS CELL WILL TAKE ITS VALUE FROM THE LATTER LINE				
***** NOTE ***** BOUNDARY LINES RIGHT AND BOTTOM INTERSECT IN CELL (16, 2).				
THIS CELL WILL TAKE ITS VALUE FROM THE LATTER LINE				
***** NOTE ***** BOUNDARY LINES LEFT AND TOP INTERSECT IN CELL (2, 21).				
THIS CELL WILL TAKE ITS VALUE FROM THE LATTER LINE				
***** NOTE ***** BOUNDARY LINES RIGHT AND TOP INTERSECT IN CELL (16, 21).				
THIS CELL WILL TAKE ITS VALUE FROM THE LATTER LINE				

FILE NAME --- BOUNDARY BOUNDARY DEFINITION AND CONCENTRATIONS

MAP OF BOUNDARY LINE NUMBERS ON THE REGIONAL GRID

GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17
22	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0
21	0	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	0
20	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
19	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
18	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
17	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
16	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
15	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
14	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
13	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
12	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
11	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
10	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
9	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
8	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
7	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
6	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
5	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
4	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
3	0	3	0	0	0	0	0	0	0	0	0	0	0	0	0	4	0
2	0	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	0
1	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0

BOUNDARY LINE IDENTIFICATION

NUMBER	NAME					
1	TOP					
2	BOTTOM					
3	LEFT					
4	RIGHT					
TIME INTERVAL		500	76195	600		
76195						
** READING DIFFBREAK		FILE :	DATE= 76195	TIME=	5.00 **	
** READING REGTOP		FILE :	DATE= 76195	TIME=	5.00 **	
** READING TOPCONC		FILE :	DATE= 76195	TIME=	5.00 **	
METHOD						
ALL	NO	BOUNDVALUE	.0000	90.0000	0	
ALL	NO2	BOUNDVALUE	.0000	90.0000	0	
ALL	O3	BOUNDVALUE	.0000	90.0000	0	
ALL	RHC	BOUNDVALUE	.0000	90.0000	0	
ALL	PAN	BOUNDVALUE	.0000	90.0000	0	
ALL	CO	BOUNDVALUE	.0000	90.0000	0	
ALL	ETH	SPLIT/COMB	.0000	10.0000	1	
RHC		.0217				
ALL	OLE	SPLIT/COMB	.0000	10.0000	1	
RHC		.0440				
ALL	PAR	SPLIT/COMB	.0010	10.0000	1	
RHC		.6665				
ALL	CARB	SPLIT/COMB	.0000	10.0000	1	
RHC		.0810				
ALL	ARO	SPLIT/COMB	.0000	10.0000	1	
RHC		.0248				
ALL	BZA	SPLIT/COMB	.0000	10.0000	1	
RHC		.0001				
END			.0000	.0000	0	
VERTICAL METHOD						
ALL	ALL	RELPROFRAT	.0000	100.0000	0	
END			.0000	.0000	0	

BOUNDARY READINGS

ALL	PAH	.0000
TOP	O3	.0230
RIGHT	O3	.0260
BOTTOM	O3	.0260
LEFT	O3	.0230
TOP	CO	.1210
RIGHT	CO	.1920
BOTTOM	CO	.1920
LEFT	CO	.1210
TOP	RHC	.0790
RIGHT	RHC	.0500
BOTTOM	RHC	.0500
LEFT	RHC	.0790
TOP	NO	.0030
RIGHT	NO	.0020
BOTTOM	NO	.0020
LEFT	NO	.0030
TOP	NO2	.0070
RIGHT	NO2	.0020
BOTTOM	NO2	.0020
LEFT	NO2	.0070
END		.0000

VERTICAL PROFILE

ALL	ALL	35296.0000	5038.0000	4
	9.	.0000		
	102.	.0000		
	122.	1.0000		
	5000.	1.0000		
END		.0000	.0000	0
ENDTIME				

FILE NAME	--	BOUNDARY	BOUNDARY DEFINITION AND CONCENTRATIONS												PAGE
			VERT. LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00												1
BOUNDARY CONCENTRATIONS (PARTS PER MILLION) FOR NO															
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12			
4	-9.0000	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010		
3	-9.0000	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010		
2	-9.0000	.0020	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030		
1	-9.0000	.0020	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030		

Exhibit VII-4 (Continued)

FILE NAME -- BOUNDARY BOUNDARY DEFINITION AND CONCENTRATIONS

BOUNDARY CONCENTRATIONS (PARTS PER MILLION) FOR NO VERT. LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00

GRID CELL	13	14	15	16	17	18	19	20	21	22
4	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	-9.0000
3	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	-9.0000
2	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	-9.0000
1	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	-9.0000

Exhibit VII-4 (Continued)

FILE NAME	--	BOUNDARY	BOUNDARY DEFINITION AND CONCENTRATIONS												PAGE
BOUNDARY CONCENTRATIONS (PARTS PER MILLION) FOR			NO	VERT. LEVEL 2 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00										1	
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12			
4	-9.0000	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010		
3	-9.0000	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010		
2	-9.0000	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020		
1	-9.0000	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020		

FILE NAME -- BOUNDARY BOUNDARY DEFINITION AND CONCENTRATIONS PAGE 2
 BOUNDARY CONCENTRATIONS (PARTS PER MILLION) FOR VERT. LEVEL 2 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00
 GRID CELL 13 14 15 16 17 18 19 20 21 22
 4 .0010 .0010 .0010 .0010 .0010 .0010 .0010 .0010 .0010 -9.0000
 3 .0010 .0010 .0010 .0010 .0010 .0010 .0010 .0010 .0010 -9.0000
 2 .0020 .0020 .0020 .0020 .0020 .0020 .0020 .0020 .0030 -9.0000
 1 .0020 .0020 .0020 .0020 .0020 .0020 .0020 .0020 .0030 -9.0000

FILE NAME	--	BOUNDARY	BOUNDARY DEFINITION AND CONCENTRATIONS												PAGE
			VERT. LEVEL 3 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00												1
BOUNDARY CONCENTRATIONS (PARTS PER MILLION) FOR NO															
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12			
4	-9.0000	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010		
3	-9.0000	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010		
2	-9.0000	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020		
1	-9.0000	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020	.0020		

Exhibit VII-4 (Continued)

FILE NAME -- BOUNDARY BOUNDARY DEFINITION AND CONCENTRATIONS

BOUNDARY CONCENTRATIONS (PARTS PER MILLION) FOR NO VERT. LEVEL 3 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00

GRID CELL	13	14	15	16	17
4	.0010	.0010	.0010	.0010	-9.0000
3	.0010	.0010	.0010	.0010	-9.0000
2	.0020	.0020	.0020	.0020	-9.0000
1	.0020	.0020	.0020	.0020	-9.0000

Exhibit VII-4 (Continued)

FILE NAME	--	BOUNDARY	BOUNDARY DEFINITION AND CONCENTRATIONS												PAGE
BOUNDARY CONCENTRATIONS (PARTS PER MILLION) FOR			NO	VERT. LEVEL 4 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00											
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12			
4	-9.0000	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010		
3	-9.0000	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010		
2	-9.0000	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030		
1	-9.0000	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030	.0030		

Exhibit VII-4 (Continued)

FILE NAME -- BOUNDARY BOUNDARY DEFINITION AND CONCENTRATIONS

BOUNDARY CONCENTRATIONS (PARTS PER MILLION) FOR NO VERT. LEVEL 4 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00

GRID CELL	13	14	15	16	17
4	.0010	.0010	.0010	.0010	-9.0000
3	.0010	.0010	.0010	.0010	-9.0000
2	.0030	.0030	.0030	.0030	-9.0000
1	.0030	.0030	.0030	.0030	-9.0000

C. DIFFBREAK

The DIFFBREAK file contains time-varying two-dimensional matrices of diffusion break heights. The diffusion break is used to define the distribution of cells in the vertical direction and to delimit layers of the atmosphere with different diffusion characteristics. The diffusion break is usually set to the mixing height or the height of the inversion base. The program DFSNBK is used to create the DIFFBREAK file. DFSNBK requires subroutines from the libraries UTILITY and FILUTIL. Figure VII-5 is an information flow diagram illustrating the job control to be used. In the following sections we discuss the input to the DFSNBK program.

1. Variables

The output variable for the DIFFBREAK file is also named DIFFBREAK. This is an "implicit output variable" and need not be referred to anywhere in the CONTROL packet. The internal units for DIFFBREAK are meters (m). If the input values for this variable are to be in any other units, DIFFBREAK must be specified in the UNITS packet.

2. Methods

The methods that can be used to generate the DIFFBREAK file are:

- > CONSTANT
- > GRID VALUE
- > STATINTERP
- > POISSON
- > E-WINTERP
- > N-SINTERP
- > USER.

These methods are discussed in detail in Section VI.A.6.




Figure VII-5. Information Flow Diagram for the DIFFBREAK File

3. Time Variation

The diffusion break values on the DIFFBREAK file are considered to apply at the beginning of the time interval. Because the Airshed Simulation Program calculates diffusion break values continuously over time by linear interpolation, it also requires values at the end of the time interval. These are read by the program as the values at the beginning of the next time interval. Thus, the last time interval on the file must begin at or after the ending simulation time. For example, if a simulation is to be made from 0500-1700, and diffusion break values are input hourly, the values used between 500 and 600 are calculated by interpolating between values input for the 0500-0600 time interval and those input for the 0600-0700 time interval. Similarly, to calculate values between 1600 and 1700, the simulation program requires values for the interval 1600-1700 as well as another set for an interval beginning at 1700.

4. Packets

Figure VII-6 shows the input deck structure in terms of the packets to be used. Each of these packets is described in detail in Section VI.B. Following are special input packet considerations for the DIFFBREAK file:

> CONTROL

- The file name on Card 2 must be DIFFBREAK.
- The control variables to be specified on Cards 4 to 8 for DIFFBREAK are shown in Table VII-3.
- The number of species should be zero.
- If there are input variables that do not appear as output variables, their number must appear as the number of user-defined variables. All such variables must also be named in the UNITS packet.




Figure VII-6. Input Card Deck Structure for Preparing the DIFFBREAK FILE

Table VII-3. CONTROL Packet Entries for the DIFFBREAK File

<u>Number</u>	<u>Entry</u>
4	Number of species (=0)
	Number of user-defined variables
	Number of stations
	Number of subregions
	Number of parameters
	Spare
5	Output file number
	Print input cards
	Print output grid
	Spare
	Spare
6	Print units table
	Print station locations table
	Print regional grid
	Print methods table
	Print station values table
	Spare
7	Spare
	Spare
	Spare
	Spare
	Spare
	Spare
8	Spare
	Spare
	Spare
	Spare
	Spare
	Spare

- If data from measuring stations are to be used (methods STATINTERP or POISSON), the maximum number of such stations must be given.
 - The number of subregions must be at least one.
 - The maximum number of parameters must be sufficient to include all specifications of all parameters.
 - The vertical controls card (No. 7) should be left blank.
 - The file unit assignment card (No. 8) should be left blank.
 - The beginning and ending dates and times should reflect the time variation considerations discussed in Section 3 above.
 - A set of output species names is not required; if they are present, their number must be the same as the entry in the first control parameter on Card 4, but they will be ignored by the program.
- > REGION. This packet must follow the CONTROL packet. The vertical parameters will be ignored for the DIFFBREAK file.
 - > UNITS. This packet, if present, must follow the REGION packet. The UNITS packet must be provided if:
 - Any input variable will be input in other than internal units.
 - Any user-defined variables are specified.
 - COORD or HEIGHT unit conversions are to be used.
 The number of user-defined variables must not exceed the maximum specified in the CONTROL packet.
 - > STATIONS. This packet is required if either of the methods STATINTERP or POISSON is specified. The number of stations listed must not exceed the maximum specified in the CONTROL packet.
 - > TIME INTERVAL. Two or more TIME INTERVAL packets must be present. The first time interval must begin at or before the beginning of the time span specified on Card 10 of the CONTROL packet. The last time interval must begin at or

after the ending time of any simulation run. All time intervals must be contiguous and of nonzero length. Each TIME INTERVAL packet contains one or more of the following packets and ends with an ENDTIME card. Following the first time interval, only those data that are to be changed need be specified.

- > SUBREGION. The first time interval must contain a SUBREGION packet; the inclusion of this packet in other time intervals is optional. The number of subregions must not exceed the maximum specified in the CONTROL packet.
- > METHOD. A method must be provided for every variable--including user-defined variables--in every subregion in the first time interval. Methods can be changed in subsequent TIME INTERVAL packets if desired. Note that each parameter entry contributes to the overall parameter count; the total number of parameters must not exceed the maximum specified in the CONTROL packet.
- > CONSTANTS. If the method CONSTANT is assigned to any variable in the METHOD packet, the first time interval must contain a CONSTANTS packet. More than one CONSTANTS packet can appear in any time interval.
- > GRID VALUES. If the method GRID VALUE is assigned to any variable in the METHOD packet, the first time interval must contain a GRID VALUES packet. More than one GRID VALUES packet can appear in any time interval.
- > STATION READINGS. If either the POISSON or STATINTERP method is assigned to any variable in the METHOD packet, the first time interval must contain a STATION READINGS packet. More than one STATION READINGS packet can appear in any time interval.

5. Additional Input Files

No additional input files are required.

6. Examples

Exhibit VII-5 shows a sample input deck for DIFFBREAK file generation. The output from a DFSNBK run using that input deck is shown in Exhibit VII-6.

CONTROL									
DIFFBREAK									
HEIGHT OF THE MIXED LAYER									
23	1	12	1	10					
76195	500	76196	10						
END									
REGION									
725000.	4252000.	15							
-19000.	-16000.								
4000.	4000.								
17	22	4							
2	2	0.	50.	200.					
END									
STATIONS									
141	17949.	27053.							
141A	14000.	23000.							
141B	14000.	27000.							
141C	14000.	31000.							
141D	18000.	31000.							
141E	18000.	23000.							
141F	22000.	23000.							
141G	22000.	27000.							
141H	22000.	31000.							
142	-9294.	14115.							
143	35296.	5030.							
144	30861.	56067.							
END									
TIME INTERVAL									
76195	500	76195	600						
SUBREGION									
A	1	1	-1						
END									

Exhibit VII-5. Sample Input Deck for the DFNSBK Program

METHOD	DIFFBREAK	POISSON	0.	2000.	3
A					
RMAXIT	200.				
TLRNC	0.5				
ROMEGA	1.4				
END					
STATION READINGS					
141	DIFFBREAK	402.			
141A	DIFFBREAK	402.			
141B	DIFFBREAK	402.			
141C	DIFFBREAK	402.			
141D	DIFFBREAK	402.			
141E	DIFFBREAK	402.			
141F	DIFFBREAK	402.			
141G	DIFFBREAK	402.			
141H	DIFFBREAK	402.			
142	DIFFBREAK	102.			
143	DIFFBREAK	102.			
144	DIFFBREAK	102.			
END					
ENDTIME					
TIME INTERVAL					
76195	600	76195	700		
STATION READINGS					
141	DIFFBREAK	418.			
141A	DIFFBREAK	418.			
141B	DIFFBREAK	418.			
141C	DIFFBREAK	418.			
141D	DIFFBREAK	418.			
141E	DIFFBREAK	418.			
141F	DIFFBREAK	418.			
141G	DIFFBREAK	418.			
141H	DIFFBREAK	418.			
142	DIFFBREAK	167.			
143	DIFFBREAK	167.			
144	DIFFBREAK	167.			
END					
ENDTIME					

Exhibit VII-5 (Concluded)

PROCESSING OF INPUT DATA FOR THE PREPARATION OF FILE DIFFBREAK

HEIGHT OF THE MIXED LAYER

NUMBER OF STATIONS = 12
 NUMBER OF SUBREGIONS = 1
 NUMBER OF METHOD PARAMETERS = 10
 PROGRAM OUTPUT WILL BE PLACED ON FILE NUMBER 23
 INPUT CARDS WILL BE PRINTED
 OUTPUT GRID WILL BE PRINTED
 UNIT TABLE WILL NOT BE PRINTED
 STATION LOCATIONS WILL NOT BE PRINTED
 SUBREGION GRID WILL NOT BE PRINTED
 METHOD TABLE WILL NOT BE PRINTED
 STATION VALUES WILL NOT BE PRINTED
 BEGINNING DATE OF FILE 76195 BEGINNING TIME OF FILE 5.00
 ENDING DATE OF FILE 76196 ENDING TIME OF FILE .17

REGION
 72500. 4252000. 15
 -19000. -16000.
 4000.00 4000.00
 17 22 4
 2 2 .00 50.00 200.00
 END

Exhibit VII-6. Sample Output from the DFNSBK Program

FILE NAME -- DIFFBREAK		HEIGHT OF THE MIXED LAYER										PAGE 1
DIFFUSION BREAK VALUES (IN METERS ABOVE GROUND LEVEL)		VERT. LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00										
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12
22	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000
21	102.0000	104.0061	105.9784	107.8764	109.6442	111.2035	112.4517	113.2621	113.4869	112.9678	111.5785	109.4017
20	102.0000	106.0492	110.0391	113.8977	117.5229	120.7653	123.4199	125.2271	125.8663	124.9496	122.0040	116.6038
19	102.0000	108.1576	114.2490	120.1900	125.8482	131.0156	135.3871	138.5582	140.0230	139.1342	134.8865	124.9782
18	102.0000	110.3394	118.6380	126.8301	134.7796	142.2370	148.8003	153.8979	156.8324	156.8625	153.3217	145.7940
17	102.0000	112.5715	123.1758	133.8129	144.3856	154.6312	164.0430	171.8205	176.9206	178.3270	175.4780	168.5566
16	102.0000	114.7858	127.7453	141.0099	154.5890	168.2632	181.4332	192.9575	201.1329	204.1504	201.2368	192.7235
15	102.0000	116.8553	132.1119	148.1159	165.0816	182.9509	201.1351	218.0985	230.9451	235.9049	231.8983	219.3304
14	102.0000	118.5852	135.8983	154.5894	175.1980	198.0348	222.8621	248.0858	269.0660	276.4828	270.2190	249.5590
13	102.0000	119.7123	138.5788	159.6205	183.7796	211.9917	245.0963	283.0558	321.0929	330.4662	321.8958	283.8507
12	102.0000	119.9191	139.5127	162.1920	189.1754	222.0373	263.4087	318.6224	402.0000	402.0000	402.0000	318.1304
11	102.0000	118.8524	137.9964	161.3214	189.7096	224.6137	268.7601	326.5473	402.0000	402.0000	402.0000	324.6042
10	102.0000	116.1240	133.1719	156.4365	184.8351	218.9656	261.2449	317.1956	402.0000	402.0000	402.0000	313.3499
9	102.0000	111.3740	123.2244	147.5830	175.3284	206.0785	240.6791	279.2575	317.1860	325.2433	314.3020	272.3603
8	102.0000	105.3165	102.0000	136.5030	163.7951	190.0691	216.5829	242.1357	262.1583	267.2108	257.2377	231.7732
7	102.0000	107.2511	114.7118	133.6508	154.0439	174.3307	193.7312	210.6377	222.0515	224.0679	215.5090	196.6989
6	102.0000	108.3177	117.0373	130.1234	144.9114	159.7828	173.5247	184.6783	191.3240	191.4567	183.9997	168.4714
5	102.0000	108.1039	115.7802	125.3862	135.9776	146.5089	155.9673	163.2427	167.1079	166.4374	160.5847	149.4631
4	102.0000	107.0870	113.0524	119.9097	127.2197	134.3517	140.6021	145.2149	147.4289	146.6159	142.4751	135.1894
3	102.0000	105.6063	109.6386	114.9663	118.6635	123.0710	126.8604	129.5737	130.7749	130.1351	127.5416	123.2044
2	102.0000	103.8637	105.8902	108.0631	110.2833	112.3872	114.1739	115.4294	115.9563	115.6151	114.3737	112.3549
1	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000	102.0000

Exhibit VII-6 (Continued)

FILE NAME -- DIFFBREAK HEIGHT OF THE MIXED LAYER

DIFFUSION BREAK VALUES (IN METERS ABOVE GROUND LEVEL) VERT. LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00

GRID CELL	13	14	15	16	17
22	102.0000	102.0000	102.0000	102.0000	102.0000
21	107.2683	107.4373	107.3662	105.8242	102.0000
20	109.6837	111.9638	112.2625	109.0659	102.0000
19	102.0000	116.8009	118.0606	112.6005	102.0000
18	135.3789	132.9462	127.3580	117.1122	102.0000
17	158.9566	149.4731	137.5922	121.9777	102.0000
16	180.1957	165.2262	147.5758	126.6674	102.0000
15	201.3668	180.3163	156.8746	130.8992	102.0000
14	223.0223	194.5563	165.1207	134.4611	102.0000
13	244.1440	206.8965	171.6151	137.0459	102.0000
12	260.6950	214.9730	175.1758	138.1938	102.0000
11	263.9149	215.4856	174.4594	137.4240	102.0000
10	253.7866	207.5854	168.9463	134.5254	102.0000
9	229.6791	191.6240	158.8958	129.6244	102.0000
8	200.6825	170.1863	145.3731	123.1938	102.0000
7	171.0517	143.1141	129.3504	115.9792	102.0000
6	143.7772	102.0000	113.1119	109.5702	102.0000
5	133.6663	115.8389	111.6856	107.3430	102.0000
4	125.6634	116.0918	110.5570	106.2150	102.0000
3	117.7668	112.3746	108.3042	105.0166	102.0000
2	109.8678	107.3805	105.3094	103.5776	102.0000
1	102.0000	102.0000	102.0000	102.0000	102.0000

Exhibit VII-6 (Concluded)

D. EMISSIONS

The EMISSIONS file contains time-varying matrices of ground-level emission fluxes. At present, there is no general-purpose program for creating the EMISSIONS file because its generation is so highly dependent on the form of the emissions data available: traffic, stationary sources, area sources, airports, and so on. There is a program structure, similar to that of the other data preparation programs, that includes the reading of control packets, unit conversions, and writing the proper output records. This program can be tailored to particular input requirements as necessary. The skeleton program is named EMISSN. EMISSN requires subroutines from the libraries UTILITY and FILUTIL. Figure VII-7 is an information flow diagram illustrating the job control to be used. In the following sections we discuss the card input to the EMISSN program.

1. Variables

The output variables for the EMISSIONS file are the species named in the CONTROL packet. Additional user-defined input variables (e.g. "reactive hydrocarbons") can be specified in the UNITS packet. The internal units for ground-level emissions of all species except AEROSOLS are gram-moles per hour (g-mol/hr); for AEROSOLS, the units are grams per hour (g/hr). The standard names for reactive species recognized by the Airshed Simulation Program are listed in Section IX.A. If any of these species does not appear on the EMISSIONS file, the emissions values default to zero. If any additional species appear on EMISSIONS, they will be ignored.

2. Methods

The methods that can be used to generate the EMISSIONS file are:

- > CONSTANT
- > GRID VALUE
- > SPLIT/COMB
- > USER.




Figure VII-7. Information Flow Diagram for the EMISSIONS File

The actual methods for generating output values from specific input data files must be written for each new application.

3. Time Variation

The time span of the EMISSIONS file must include the entire time span of the simulation runs for which it is to be used. Ground-level emissions are considered to be constant during each time interval.

4. Packets

The packets to be used for EMISSN will depend on the particular version that is developed for a given set of input data files. Information on control parameters, units, time intervals, computation methods, and data entry will have to be provided when the program has been implemented. Figure VII-8 shows a possible input structure in terms of the packets to be used.

5. Additional Input Files

Point source, line source, area source, or gridded area emissions might be input to EMISSN.




Figure VII-8. A Possible Input Card Deck Structure for Preparing the EMISSIONS File

E. METSCALARS

The METSCALARS file contains a set of time-varying scalars to be used in meteorological calculations. It has no spatial dependence. The program METSCL is used to create the METSCALARS file. METSCL requires subroutines from the libraries UTILITY and FILUTIL. Figure VII-9 is an information flow diagram illustrating the job control to be used. In the following sections we discuss the input to the METSCL program.

1. Variables

There are six output variables for the METSCALARS file. Their names and internal units are:

- > TGRADBELOW--temperature gradient below the diffusion break ($^{\circ}\text{K/m}$).
- > TGRADABOVE--temperature gradient above the diffusion break ($^{\circ}\text{K/m}$).
- > EXPCLASS--exposure class, an integer scale (+3 to -2) of the near ground-level atmospheric stability due to surface heating or cooling. It can be estimated from insolation as follows:

$$\text{exposure class} = \left\{ \begin{array}{ll} \begin{array}{l} 3, \text{ strong} \\ 2, \text{ moderate} \\ 1, \text{ slight} \end{array} & \text{daytime insolation,} \\ 0, \text{ heavy overcast} & \text{day or night,} \\ \begin{array}{l} -1, \geq \frac{4}{8} \text{ cloud cover} \\ -2, \leq \frac{3}{8} \text{ cloud cover} \end{array} & \text{nighttime cloudiness.} \end{array} \right.$$

- > RADFACTOR--the NO_2 photolysis rate constant, k_1 (min^{-1}).
- > CONCWATER--average concentration of water (ppm).
- > ATMOSPRESS--atmospheric pressure (atm).




Figure VII-9. Information Flow Diagram for the METSCALARS File

2. Methods

Since the METSCALARS variables do not vary spatially, there is no need to define a method for determining spatial distribution. It is assumed that the variables will be explicitly entered in SCALARS packets and that only simple unit conversions, which are defined in the UNITS packet, need be performed.

3. Time Variation

Five of the METSCALARS variables, TGRADBELOW, TGRADABOVE, EXPCLASS, CONCWATER, and ATMOSPRESS, are considered to be constant during each time interval. The sixth variable, RADFACTOR, however, is considered to apply at the end of the time interval. Because the Airshed Simulation Program calculates radiation factor values continuously over time by linear interpolation, it also requires values at the beginning of the time interval. These are saved by the program as the values read for the end of the previous time interval. Thus the first time interval on the file must end at or before the beginning simulation time. For example, if a simulation is to be made from 0500-1700, and radiation factor values are input hourly, the values used between 500 and 600 are calculated by interpolating between values input for the 0400-0500 time interval and those input for the 0500-0600 time interval.

4. Packets

Figure VII-10 shows the input deck structure in terms of the packets to be used. Each of these packets is described in detail in Sections VI.B. Following are special input packet considerations for the file:

> CONTROL

- The file name on Card 2 must be METSCALARS.
- The control variables to be specified on Cards 4 to 8 for METSCALARS are shown in Table VII-4.




Figure VII-10. Input Card Deck Structure for Preparing the METSCALARS File

Table VII-4. CONTROL Packet Entries for the METSCALARS File

<u>Card Number</u>	<u>Entry</u>
4	Number of species (=0) Spare Spare Spare Spare Spare
5	Output file number Print input cards Print output values Spare Spare Spare
6	Print units table Spare Spare Spare Spare Spare
7	Spare Spare Spare Spare Spare Spare
8	Spare Spare Spare Spare Spare Spare

- The number of species should be zero.
 - The vertical controls card (No. 7) should be left blank.
 - The file unit assignment card (No. 8) should be left blank.
 - The beginning and ending dates and times should reflect the time variation considerations discussed in Section 3 above.
 - A set of output species names is not required; if they are present, their number must be the same as the entry in the first control parameter on Card 4, but they will be ignored by the program.
- > REGION. This packet must follow the CONTROL packet. The vertical parameters will be ignored for the METSCALARS file.
 - > UNITS. This packet, if present, must follow the REGION packet. The UNITS packet must be provided if any input variable will be input in other than internal units. The units of RADFACTOR must be min^{-1} and cannot be changed.
 - > TIME INTERVAL. Two or more TIME INTERVAL packets must be present. The first time interval must end at or before the beginning time of any simulation run. All time intervals must be contiguous and of nonzero length. Each TIME INTERVAL packet contains a SCALARS packet and ends with an ENDTIME card. Following the first time interval, only those data that are to be changed need be specified.
 - > SCALARS. The first time interval must contain a SCALARS packet. Following the first time interval, the SCALARS packet can be omitted if no values are to be changed.

5. Additional Input Files

No additional input files are required.

6. Examples

Exhibit VII-7 shows a sample input deck for METSCALARS file generation. The output from a METSCL run using that input deck is shown in Exhibit VII-8.

```

CONTROL
MET SCALARS
VALUES FOR METEOROLOGICAL SCALARS
0 0 0 1 3
24 1 1
1

END 76195 400 76195 2400
REGION 725000. 4252000. 15
-19000. -16000.
4000. 4000.
17 22 4
2 2 0. 50. 200.

END
TIMEINTERVAL 76195 400 76195 500
SCALARS
TGRADBELOW -0.01
TGRADABOVE 0.0039
EXPCLASS -1.
ATMOSPRESS 0.99
RADFACTOR .008
CONCHATER 12687.
END
ENDTIME
TIME INTERVAL 76195 500 76195 600
SCALARS
RADFACTOR .084
EXPCLASS 0.0
END
ENDTIME
TIME INTERVAL 76195 600 76195 700
SCALARS
EXPCLASS 1.
CONCHATER 12687.
RADFACTOR .180
END
ENDTIME

```

Exhibit VII-7. Sample Input Deck for the METSCL Program

PROCESSING OF INPUT DATA FOR THE PREPARATION OF FILE METSCALARS

VALUES FOR METEOROLOGICAL SCALARS

PROGRAM OUTPUT WILL BE PLACED ON FILE NUMBER 24

INPUT CARDS WILL BE PRINTED

OUTPUT GRID WILL BE PRINTED

UNIT TABLE WILL BE PRINTED

BEGINNING DATE OF FILE 76195 BEGINNING TIME OF FILE 4.00

ENDING DATE OF FILE 76195 ENDING TIME OF FILE 24.00

REGION	725000.	4252000.	15
	-19000.	-16000.	
	4000.00	4000.00	4
	17	22	
	2	2	.00
			50.00
			200.00
END			
TIMEINTERVAL	76195	400	76195
			500
SCALARS			
TGRADBELOW		-.0100	
TGRADABOVE		.0039	
EXPCLASS		-1.0000	
ATHOSPRESS		.9900	
RADFACTOR		.0080	
CONCHWATER		12687.0000	
END		.0000	
ENDTIME			

Exhibit VII-8. Sample Output from the METSCL Program

FILE NAME --METSALARS VALUES FOR METEOROLOGICAL SCALARS PAGE 01
 METEOROLOGICAL SCALARS (VARIABLE UNITS -- CONSULT MANUAL) START DATE/TIME ,76195 4.00 STOP DATE/TIME 76195 5.00

VARIABLE NAME	VALUE
TGRADBELOW	-.0100
TGRADABOVE	.0039
EXPCLASS	-1.0000
RADFACTOR	.0080
CONCHATER	12687.0000
ATMOSPRESS	.9900
TIME INTERVAL	
76195	500 76195 600
SCALARS	
RADFACTOR	.0840
EXPCLASS	.0000
END	.0000
ENDTIME	

FILE NAME --METSALARS VALUES FOR METEOROLOGICAL SCALARS PAGE 01
 METEOROLOGICAL SCALARS (VARIABLE UNITS -- CONSULT MANUAL) START DATE/TIME ,76195 5.00 STOP DATE/TIME 76195 6.00

VARIABLE NAME	VALUE
TGRADBELOW	-.0100
TGRADABOVE	.0039
EXPCLASS	.0000
RADFACTOR	.0840
CONCHATER	12687.0000
ATMOSPRESS	.9900
TIME INTERVAL	
76195	600 76195 700
SCALARS	
EXPCLASS	1.0000
CONCHATER	12687.0000
RADFACTOR	.1800
END	.0000
ENDTIME	

F. PTSOURCE

The PTSOURCE file contains a set of time-invariant locations of elevated point sources and time-varying emissions fluxes from each source into specific vertical cells. The file can be omitted from a simulation run. The program PTSRCE is used to create the PTSOURCE file. PTSRCE requires subroutines from the libraries UTILITY and FILUTIL. Figure VII-11 is an information flow diagram illustrating the job control to be used. In the following sections we discuss the input to the PTSRCE program.

1. Variables

The output variables for the PTSOURCE file are the species named in the CONTROL packet. Additional user-defined input variables (e.g., "reactive hydrocarbons") can be specified in the UNITS packet. The internal units for the emissions of all species except AEROSOLS are gram-moles per hour (g-mol/hr); for AEROSOLS, the units are grams per hour (g/hr). The standard names for reactive species recognized by the Airshed Simulation Program are listed in Section IX.A. If any of these species does not appear on the PTSOURCE file, the emissions will default to zero. If any additional species appear on PTSOURCE, they will be ignored.

There are five other implicit variables used in the PTSRCE program:

- > HEIGHT--stack height
- > DIAMETER--stack exit diameter
- > STACKTEMP--stack exit temperature
- > STACKVEL--stack exit velocity
- > FLOWRATE--flow rate.

The internal units for these variables are shown in Table VI-5; input unit conversions for any of these variables can be specified in the UNITS packet without adding to the count of "user-defined variables." Values




Figure VII-11. Information Flow Diagram for the PTSOURCE File

for the first four variables are entered in the POINT SOURCES packet and are considered time-invariant. FLOWRATE values, if specified, appear in the EMISSIONS VALUES packet and are modified, along with species emissions, by the emissions factors.

2. Methods

The methods that can be used to generate the PTSOURCE file are:

- > EMVALUES
- > EMFACTORS
- > SPLIT/COMB
- > USER.

These methods are discussed in detail in Section VI.A.6.

Since the PTSOURCE file varies in the vertical direction, a vertical method must also be specified for each output variable in each subregion. The vertical methods that can be used are:

- > STACKHGT
- > PLUMERISE
- > VERTUSER.

These vertical methods are discussed in detail in Section VI.A.7.

3. Time Variation

The time span of the PTSOURCE file must include the entire time span of the simulation runs for which it is to be used. Point source emissions are considered to be constant during each time interval.

4. Packets

Figure VII-12 shows the input deck structure in terms of the packets to be used. Each of these packets is described in detail in Section VI.B. Following are special input packet considerations for the PTSOURCE file:

> CONTROL

- The file name on Card 2 must be PTSOURCE.
- The control variables to be specified on Cards 4 to 8 for PTSOURCE are shown in Table VII-5.
- The number ofspecies must be greater than zero.
- If there are input variables that do not appear as output variables, their number must appear as the number of user-defined variables. All such variables must also be named in the UNITS packet.
- The number of point sources defined in the POINT SOURCES packet must be specified.
- The number of point source types must be at least one.
- The maximum number of parameters must be sufficient to include all specifications of all parameters.
- The vertical controls card (No. 7) must specify the maximum number of vertical parameters as applicable.
- The file unit assignment card (No. 8) must specify the DIFFBREAK and REGIONTOP files. In addition, it must specify TEMPERATUR, METSCALARS, and WIND if the vertical method PLUMERISE is selected.
- The beginning and ending dates and times should reflect the time variation considerations discussed in Section 3 above.
- A set of output species names is required; their number must be the same as the entry in the first control parameter on Card 4.

- > REGION. This packet must follow the CONTROL packet. The vertical parameters must be provided for the PTSOURCE file.




Figure VII-12. Input Card Deck Structure for Preparing the PTSOURCE File

Table VII-5. CONTROL Packet Entries for the PTSOURCE File

<u>Card Number</u>	<u>Entry</u>
4	Number of species
	Number of user-defined variables
	Number of point sources
	Number of point source types
	Number of parameters
	Spare
5	Output file number
	Print input cards
	Print output grid
	Spare
	Spare
	Spare
6	Print units table
	Print point source locations table
	Print regional point source distribution grid
	Print methods table
	Print point source values table
	Spare
7	Number of vertical parameters
	Spare
	Print vertical methods table
	Spare
	Spare
	Spare
8	DIFFBREAK file number
	REGIONTOP file number
	Spare
	TEMPERATUR file number
	METSCALARS file number
	WIND file number

- > UNITS. This packet, if present, must follow the REGION packet. The UNITS packet must be provided if:
 - Any input variable will be input in other than internal units.
 - Any user-defined variables are specified.
 - COORD or HEIGHT unit conversions are to be used.
 The number of user-defined variables must not exceed the maximum specified in the CONTROL packet.
- > POINT SOURCES. This packet is required. It names the point sources, assigns to each a type and location, and describes certain time-invariant stack properties. The number of point sources specified must equal the number specified in the CONTROL packet. Each point source must be given a type name. Point sources are grouped by type at the time that methods and vertical methods are assigned, and emission factors can be applied by point source type. The number of different types specified must not exceed the maximum defined in the CONTROL packet.
- > TIME INTERVAL. One or more TIME INTERVAL packets must be present. The first time interval must begin at or before the beginning of the time span specified on Card 10 of the CONTROL packet. All time intervals must be contiguous and of nonzero length. Each TIME INTERVAL packet contains one or more of the following packets and ends with an ENDTIME card. Following the first time interval, only those data that are to be changed need be specified.
- > METHOD. A method must be provided for every variable--including user-defined variables---for every point source type in the first time interval. Methods can be changed in subsequent TIME INTERVAL packets if desired. Note that each parameter entry contributes to the overall parameter count; the total number of parameters must not exceed the maximum specified in the CONTROL packet.

- > VERTICAL METHOD. A vertical method must be provided for every variable--including user-defined variables--for every point source type in the first time interval. Vertical methods can be changed in subsequent TIME INTERVAL packets if desired. Note that each vertical parameter entry contributes to the overall vertical parameter count; the total must not exceed the maximum specified in the CONTROL packet.
- > EMISSIONS VALUES. The first time interval must contain an EMISSIONS VALUES packet. More than one EMISSIONS VALUES packet can appear in any time interval.
- > EMISSIONS FACTORS. If the method EMFACTORS is selected in a subsequent time interval, the EMISSIONS FACTORS packet must appear. This packet can be used to multiply all emissions from a given point source or type by a time-varying factor. More than one EMISSIONS FACTORS packet can appear in any time interval.

5. Additional Input Files

The DIFFBREAK and REGIONTOP files must be input to PTSRCE. In addition, if the vertical method PLUMERISE was selected, the TEMPERATUR, METSCALARS, and WIND files must also be input.

6. Examples

Exhibit VII-9 shows a sample input deck for PTSOURCE file generation. The output from a PTSRCE run using that input deck is shown in Exhibit VII-10.

CONTROL									
PTSOURCE									
POINT SOURCES FOR ST. LOUIS 76195 4X4 GRID									
9	2	217	1	10					
25	0	1							
1	0	0	0	1					
11	12	0							
			14	15					16
NO									
NO2									
PAR									
OLE									
CARB									
ARO									
SO2									
AERS									
CO	76195	0500	76195	2400					
END									
REGION									
	725000.	4252000.	15						
	-19000.	-16000.							
	4000.	4000.							
	17	22	4						
	2	2	0.	50.0	200.				
END									
UNITS									
NO	KG/HR								
NO2	KG/HR								
PAR									
OLE									
CARB									
ARO									
SO2	KG/HR								
AERS	KG/HR								
CO	KG/HR								
FLOWRATE	M3/MIN								
NOX	KG/HR	60.	0.						
SOX	KG/HR	1000.							
END		1000.							
POINT SOURCES									
1414400101ST.LOUIS	78900.	32100.							
1414400201ST.LOUIS	286	26692.							
1414400401ST.LOUIS	671	23100.							
1446800101ST.LOUIS	616	53630.							
1446800102ST.LOUIS	437	53600.							
76	421								

1446000103ST.LOUIS	23770.	53580.
106	417	
1446000201ST.LOUIS	31720.	38080.
9	758	
1446000307ST.LOUIS	20520.	31130.
72	438	
1446000401ST.LOUIS	27330.	52550.
48	471	
1446000407ST.LOUIS	27220.	51850.
48	563	
1446000409ST.LOUIS	27190.	52030.
33	755	
1446000414ST.LOUIS	27180.	52010.
33	588	
1446000417ST.LOUIS	27170.	52310.
23	644	
1446000421ST.LOUIS	27130.	51570.
45	1088	
1446000422ST.LOUIS	26880.	52130.
23	1032	
1446000423ST.LOUIS	27180.	52300.
15	921	
1446000424ST.LOUIS	27020.	52010.
15	286	
1446000436ST.LOUIS	27920.	51120.
17	286	
1446000464ST.LOUIS	26960.	51900.
52	574	
1446000502ST.LOUIS	27770.	50150.
24	532	

•
•
•

Exhibit VII-9 (Continued)

•
•
•

1446800304ST.LOUIS	20520.	31070.
72	455	
1446800303ST.LOUIS	20520.	31050.
72	455	
1446800603ST.LOUIS	19300.	57400.
4	286	
1469001005ST.LOUIS	22000.	17700.
4	286	

END

TIME INTERVAL	500	76195	600
76195			

METHOD	ST.LOUIS ALL	EMVALUES	0.	50000.
ST.LOUIS NO		SPLIT/COMB	0.	50000.
NOX	0.9			
ST.LOUIS NO2		SPLIT/COMB	0.	2000.
NOX	0.1			
ST.LOUIS SO2		SPLIT/COMB	0.	50000.
SOX	1.0			

1

1

1

END

VERTICAL METHODS	ST.LOUIS ALL	PLUME RISE	0.0	10000.
ST.LOUIS ALL				

END

EMISSIONS VALUES

ALL	0.0
ALL	
1414400104AERS	.34
1414400201FLOW RATE	57.77
1414400201NOX	3.12
1414400201SOX	.17
1414400201CO	.85
1414400201AERS	.12
1414400201PAR	29.27
1414400201OLE	.37
1414400201CARB	.37
1414400201ARO	.12
1414400401FLOW RATE	28.32
1414400401NOX	20.97
1414400401CO	2.65
1414400401AERS	.06
1414400401PAR	617.23

CONTROL
PTSOURCE

POINT SOURCES FOR ST. LOUIS 76195 4X4 GRID									
9	2	217	1	10	0				
25	0	1	0	0	0				
1	0	0	0	1	0				
0	0	0	0	0	0				
11	12	0	14	15	16				

NO
NO2
PAR
OLE
CARB
ARO
SO2
AERS
CO

76195	500	76195	2400
76195	500	76195	2400

END
PROCESSING OF INPUT DATA FOR THE PREPARATION OF FILE PTSOURCE

POINT SOURCES FOR ST. LOUIS 76195 4X4 GRID

REGION

725000.	4252000.	15
-19000.	-16000.	
4000.00	4000.00	4
17	22	
2	2	.00
		50.00
		200.00

END

KCRNT = 111 NSCLFT = 23390 IN SCRSET
KCRNT = 171 NSCLFT = 23330 IN SCRSET
KCRNT = 341 NSCLFT = 23160 IN SCRSET
KCRNT = 358 NSCLFT = 23143 IN SCRSET
KCRNT = 375 NSCLFT = 23126 IN SCRSET

Exhibit VII-10. Sample Output from the PTSRCE Program

KCRNT = 392	NSCLFT = 23109	IN SCRSET
KCRNT = 398	NSCLFT = 23103	IN SCRSET
KCRNT = 2568	NSCLFT = 20933	IN SCRSET
KCRNT = 2578	NSCLFT = 20923	IN SCRSET
KCRNT = 2795	NSCLFT = 20706	IN SCRSET
KCRNT = 3012	NSCLFT = 20489	IN SCRSET
KCRNT = 3229	NSCLFT = 20272	IN SCRSET
KCRNT = 5616	NSCLFT = 17885	IN SCRSET
KCRNT = 8003	NSCLFT = 15498	IN SCRSET
KCRNT = 8014	NSCLFT = 15487	IN SCRSET
KCRNT = 8025	NSCLFT = 15476	IN SCRSET
KCRNT = 8036	NSCLFT = 15465	IN SCRSET
KCRNT = 8047	NSCLFT = 15454	IN SCRSET
KCRNT = 8058	NSCLFT = 15443	IN SCRSET
KCRNT = 8158	NSCLFT = 15343	IN SCRSET
KCRNT = 8168	NSCLFT = 15333	IN SCRSET
KCRNT = 8179	NSCLFT = 15322	IN SCRSET
KCRNT = 8190	NSCLFT = 15311	IN SCRSET
KCRNT = 8201	NSCLFT = 15300	IN SCRSET
KCRNT = 8212	NSCLFT = 15289	IN SCRSET
KCRNT = 8223	NSCLFT = 15278	IN SCRSET
KCRNT = 8440	NSCLFT = 15061	IN SCRSET
KCRNT = 8657	NSCLFT = 14844	IN SCRSET
KCRNT = 8674	NSCLFT = 14627	IN SCRSET
KCRNT = 9091	NSCLFT = 14410	IN SCRSET
KCRNT = 9465	NSCLFT = 14036	IN SCRSET
KCRNT = 9839	NSCLFT = 13662	IN SCRSET
KCRNT = 10213	NSCLFT = 13288	IN SCRSET
KCRNT = 11709	NSCLFT = 11792	IN SCRSET
KCRNT = 13205	NSCLFT = 10296	IN SCRSET
KCRNT = 13579	NSCLFT = 9922	IN SCRSET
KCRNT = 13796	NSCLFT = 9705	IN SCRSET
KCRNT = 14013	NSCLFT = 9488	IN SCRSET
KCRNT = 14230	NSCLFT = 9271	IN SCRSET
KCRNT = 14447	NSCLFT = 9054	IN SCRSET
KCRNT = 14664	NSCLFT = 8837	IN SCRSET
KCRNT = 17051	NSCLFT = 6450	IN SCRSET
UNITS		

VARIABLE NAME	UNIT NAME	UNIT CONVERSION TABLE	
		MULTIPLICATIVE FACTOR	ADDITIVE FACTOR
NO	KG/HR	1000.00000000	-9.00000000
NO2	KG/HR	1000.00000000	-9.00000000
PAR		-9.00000000	-9.00000000
OLE		-9.00000000	-9.00000000
CARB		-9.00000000	-9.00000000
ARO		-9.00000000	-9.00000000
SO2	KG/HR	1000.00000000	-9.00000000
AERS	KG/HR	1000.00000000	-9.00000000
CO	KG/HR	1000.00000000	-9.00000000
NOX	KG/HR	1000.00000000	-9.00000000
SOX	KG/HR	1000.00000000	-9.00000000
COORD		-9.00000000	-9.00000000
HEIGHT		-9.00000000	-9.00000000
DIAHETER		-9.00000000	-9.00000000
STACKTEMP		-9.00000000	-9.00000000
STACKVEL		-9.00000000	-9.00000000
FLOWRATE	M3/MIN	60.00000000	-9.00000000
			1.00000000

Exhibit VII-10 (Continued)

POINT SOURCES
 TIME INTERVAL 500 76195 600
 76195
 METHOD
 VERTICAL METHODS
 EMISSIONS VALUES
 ENDTIME
 ***** NOTE ***** EMISSIONS FROM POINT SOURCE 1414400104 IN CELL (25, 13)
 ARE OUTSIDE HORIZONTAL DIMENSIONS OF MODEL DOMAIN. EMISSIONS FROM THIS SOURCE HAVE BEEN SET TO ZERO

 ***** NOTE ***** EMISSIONS FROM POINT SOURCE 1414400201 IN CELL (25, 11)
 ARE OUTSIDE HORIZONTAL DIMENSIONS OF MODEL DOMAIN. EMISSIONS FROM THIS SOURCE HAVE BEEN SET TO ZERO

 ***** NOTE ***** EMISSIONS FROM POINT SOURCE 1414400401 IN CELL (27, 10)
 ARE OUTSIDE HORIZONTAL DIMENSIONS OF MODEL DOMAIN. EMISSIONS FROM THIS SOURCE HAVE BEEN SET TO ZERO

 ***** NOTE ***** EMISSIONS FROM POINT SOURCE 1446803301 IN CELL (21, 15)
 ARE OUTSIDE HORIZONTAL DIMENSIONS OF MODEL DOMAIN. EMISSIONS FROM THIS SOURCE HAVE BEEN SET TO ZERO

 ***** NOTE ***** EMISSIONS FROM POINT SOURCE 1464600101 IN CELL (18, 1)
 ARE OUTSIDE HORIZONTAL DIMENSIONS OF MODEL DOMAIN. EMISSIONS FROM THIS SOURCE HAVE BEEN SET TO ZERO

 ***** NOTE ***** EMISSIONS FROM POINT SOURCE 1464600103 IN CELL (18, 1)
 ARE OUTSIDE HORIZONTAL DIMENSIONS OF MODEL DOMAIN. EMISSIONS FROM THIS SOURCE HAVE BEEN SET TO ZERO

Exhibit VII-10 (Continued)

POINT SOURCE EMISSIONS (GRAM-MOLES/HOUR) SPECIES NO

PT. SOURCE NAME	PT. SOURCE TYPE NAME	X-CELL	Y-CELL	Z-CELL	FLOW RATE (MM ³ /HOUR)	PLUME HGT. (METERS)	EMS. VALUE (G-MOL/HR)	EMS. FACTOR (G-MOL/HR)	EMS. FLUX
1446800101	ST. LOUIS	11	18	3	224607.	209.2825	.00	-9.00	2778.85
1446800102	ST. LOUIS	11	18	3	143602.	186.3772	.00	-9.00	173.93
1446800103	ST. LOUIS	11	18	3	940271.	310.3101	.00	-9.00	13977.59
1446800201	ST. LOUIS	13	14	1	10610.	37.2358	.00	-9.00	57.72
1446800307	ST. LOUIS	10	12	2	708572.	267.5112	.00	-9.00	8499.52
1446800401	ST. LOUIS	12	18	3	168270.	177.9466	.00	-9.00	3082.70
1446800407	ST. LOUIS	12	17	3	232827.	214.4082	.00	-9.00	655.63
1446800409	ST. LOUIS	12	18	3	93777.	180.0519	.00	-9.00	578.15
1446800414	ST. LOUIS	12	18	2	34609.	106.4060	.00	-9.00	135.20
1469003401	ST. LOUIS	12	12	1	21472.	25.0118	.00	-9.00	19.37
2622800101	ST. LOUIS	6	1	1	7767.	41.9041	.00	-9.00	373.11
2641600101	ST. LOUIS	8	19	4	884461.	391.2513	.00	-9.00	123442.24
2642800301	ST. LOUIS	10	10	1	53908.	157.5535	.00	-9.00	1091.15
2642800302	ST. LOUIS	10	10	1	1274.	77.3614	.00	-9.00	20.35
2642800305	ST. LOUIS	10	10	1	52349.	85.0143	.00	-9.00	795.13
2642800601	ST. LOUIS	9	13	1	28226.	127.1465	.00	-9.00	328.30
2642901201	ST. LOUIS	9	9	2	88058.	216.5848	.00	-9.00	6.46
264281202	ST. LOUIS	9	9	2	103633.	202.7230	.00	-9.00	6.46
264281701	ST. LOUIS	10	12	1	26015.	104.6543	.00	-9.00	355.89
264281704	ST. LOUIS	10	12	1	797.	40.1493	.00	-9.00	9.98
2642801705	ST. LOUIS	10	12	1	21491.	49.4752	.00	-9.00	444.13
2642802302	ST. LOUIS	10	11	1	41191.	104.3999	.00	-9.00	854.02
2642802401	ST. LOUIS	10	13	2	177407.	291.4135	.00	-9.00	393.07
2642802501	ST. LOUIS	9	10	2	177407.	291.7539	.00	-9.00	393.07
2642803801	ST. LOUIS	10	12	1	61006.	139.7895	.00	-9.00	722.15
2642804001	ST. LOUIS	9	11	1	9312.	85.9915	.00	-9.00	196.24
2642805601	ST. LOUIS	9	12	1	1099.	16.8529	.00	-9.00	42.26
2642805702	ST. LOUIS	10	13	1	16990.	57.9199	.00	-9.00	52.63
2642805801	ST. LOUIS	10	12	1	43367.	91.3986	.00	-9.00	498.52
2642805901	ST. LOUIS	9	11	1	16990.	65.4218	.00	-9.00	1.98
2642806001	ST. LOUIS	9	13	1	16990.	65.0096	.00	-9.00	1.96
2643000101	ST. LOUIS	7	8	3	407762.	258.4892	.00	-9.00	2244.33
2643000208	ST. LOUIS	4	9	1	4499.	57.4342	.00	-9.00	368.80
2643000701	ST. LOUIS	6	15	1	5097.	28.8824	.00	-9.00	216.39
2643000704	ST. LOUIS	6	15	1	7287.	42.0511	.00	-9.00	102.91
2643000708	ST. LOUIS	7	15	1	3309.	34.5166	.00	-9.00	85.30
2643000801	ST. LOUIS	9	14	3	679603.	299.2691	.00	-9.00	4935.72
2643000901	ST. LOUIS	9	9	1	57008.	88.8184	.00	-9.00	620.02
2643000903	ST. LOUIS	9	9	1	71429.	93.7199	.00	-9.00	1331.02
2643000905	ST. LOUIS	9	9	1	23143.	54.6988	.00	-9.00	126.78
2643000910	ST. LOUIS	9	9	1	47572.	75.3069	.00	-9.00	88.43
2643000911	ST. LOUIS	9	9	1	110435.	82.1603	.00	-9.00	88.43
2643000913	ST. LOUIS	9	9	1	118931.	96.3039	.00	-9.00	88.43
2643001001	ST. LOUIS	7	5	3	244627.	205.0220	.00	-9.00	11451.13
2643001003	ST. LOUIS	7	5	3	832438.	311.3381	.00	-9.00	32980.50
2643001401	ST. LOUIS	8	8	1	4078.	78.8097	.00	-9.00	37.96
2643001601	ST. LOUIS	8	12	1	8860.	85.0452	.00	-9.00	156.33
2643003101	ST. LOUIS	4	9	1	0.	17.9998	.00	-9.00	101.74

Exhibit VII-10 (Continued)

FILE NAME --- PTSOURCE	POINT SOURCES FOR ST. LOUIS 76195 4X4 GRID										PAGE 1	
POINT SOURCE EMISSIONS (GRAM-MOLES/HOUR) SPECIES NO	VERT. LEVEL 0 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00											
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12
22	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00
21	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00
20	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00
19	.00	.00	.00	.00	.00	.00	.00 123442.24	.00	.00	21.33	.00	.00
18	.00	.00	.00	.00	.00	.00	.00	.00	.00	639.59	22346.61	4501.76
17	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	5216.28
16	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00
15	.00	.00	.00	.00	.00	319.30	85.30	.00	.00	.00	.00	.00
14	.00	.00	.00	.00	.00	.00	.00	.00	4935.72	.00	19.76	.00
13	.00	.00	.00	.00	.00	.00	.00	.00	330.26	445.70	6952.89	.00
12	.00	.00	.00	.00	.00	.00	.00	156.33	42.26	10530.20	292.11	19.37
11	.00	.00	.00	.00	.00	.00	.00	.00	197.22	854.02	1329.46	.00
10	.00	.00	.00	.00	.00	.00	.00	.00	393.07	1906.63	2464.83	9.78
9	.00	.00	.00	470.54	.00	.00	.00	.00	2356.04	.00	.00	.00
8	.00	.00	.00	.00	.00	.00	2244.33	37.96	.00	.00	.00	.00
7	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00
6	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00
5	.00	.00	.00	.00	.00	.00	44431.63	.00	.00	.00	.00	.00
4	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00
3	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00
2	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00	.00
1	.00	.00	.00	.00	.00	373.11	.00	.00	.00	.00	.00	.00

Exhibit VII-10 (Continued)

POINT SOURCE EMISSIONS (GRAM-MOLES/HOUR) SPECIES NO VERT. LEVEL 0 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00

GRID CELL	13	14	15	16	17
22	.00	.00	.00	.00	.00
21	.00	.00	.00	.00	.00
20	.00	.00	.00	.00	.00
19	.00	.00	.00	.00	.00
18	.00	.00	.00	.00	.00
17	1761.46	.00	.00	.00	.00
16	.00	.00	.00	.00	.00
15	.00	.00	.00	.00	.00
14	57.72	.00	.00	.00	.00
13	.00	.00	.00	.00	.00
12	.00	.00	.00	.00	.00
11	.00	.00	.00	.00	.00
10	.00	.00	.00	.00	.00
9	.00	.00	.00	.00	191.74
8	.00	63.39	23.48	.00	.00
7	.00	.00	.00	.00	.00
6	.00	.00	.00	.00	.00
5	.00	.00	.00	.00	.00
4	.00	.00	.00	.00	.00
3	.00	.00	.00	.00	.00
2	.00	.00	.00	.00	.00
1	.00	.00	.00	.00	.00

Exhibit VII-10 (Concluded)

G. REGIONTOP

The REGIONTOP file contains time-varying two-dimensional matrices of region top heights. The region top height can be linked to the diffusion break or can be independently specified. The program REGNTP is used to create the REGIONTOP file. REGNTP requires subroutines from the libraries UTILITY and FILUTIL. Figure VII-13 is an information flow diagram illustrating the job control to be used. In the following sections we discuss the input to the REGNTP program.

1. Variables

The output variable for the REGIONTOP file is also named REGIONTOP. This is an "implicit output variable" and need not be referred to anywhere in the CONTROL packet. The internal units for REGIONTOP are meters (m). If the input values for this variable are to be in any other units, REGIONTOP must be specified in the UNITS packet.

2. Methods

The methods that can be used to generate the REGIONTOP file are:

- > CONSTANT
- > GRID VALUE
- > STATINTERP
- > POISSON
- > FIXDHEIGHT
- > SAMEHEIGHT
- > E-WINTERP
- > N-SINTERP
- > USER.

These methods are discussed in detail in Section VI.A.6.




Figure VII-13. Information Flow Diagram for the REGIONTOP File

3. Time Variation

The top of the region values on the REGIONTOP file are considered to apply at the beginning of the time interval. Because the Airshed Simulation Program calculates region top values continuously over time by linear interpolation, it also requires values at the end of the time interval. These are read by the program as the values at the beginning of the next time interval. Thus, the last time interval on the file must begin at or after the ending simulation time. For example, if a simulation is to be made from 0500-1700 and region top values are input hourly, the values used between 500 and 600 are calculated by interpolating between values input for the 0500-0600 time interval and those input for the 0600-0700 time interval. Similarly, to calculate values between 1600 and 1700, the simulation program requires values for the interval 1600-1700, and another set for an interval beginning at 1700.

4. Packets

Figure VII-14 shows the input deck structure in terms of the packets to be used. Each of these packets is described in detail in Sections VI.B. Following are special input packet considerations for the REGIONTOP file:

> CONTROL

- The file name on Card 2 must be REGIONTOP.
- The control variables to be specified on Cards 4 to 8 for REGIONTOP are shown in Table VII-6.
- The number of species should be zero.
- If there are input variables that do not appear as output variables, their number must appear as the number of user-defined variables. All such variables must also be named in the UNITS packet.
- If data from measuring stations are to be used (methods STATINTERP or POISSON), the maximum number of such stations must be given.
- The number of subregions must be at least one.




Figure VII-14. Input Card Deck Structure for Preparing the REGIONTOP File

Table VII-6. CONTROL Packet Entries for the REGIONTOP File

<u>Card Number</u>	<u>Entry</u>
4	Number of species (=0) Number of user-defined variables Number of stations Number of subregions Number of parameters Spare
5	Output file number Print input cards Print output grid Spare Spare Spare
6	Print units table Print station locations table Print regional grid Print methods table Print station values table Spare
7	Spare Spare Spare Spare Spare Spare
8	DIFFBREAK file unit number Spare Spare Spare Spare Spare

- The maximum number of parameters must be sufficient to include all specifications of all parameters.
 - The vertical controls card (No. 7) should be left blank.
 - The file unit assignment card (No. 8) must specify DIFFBREAK if the method FIXDHEIGHT or SAMEHEIGHT is selected. Otherwise, it should be left blank.
 - The beginning and ending dates and times should reflect the time variation considerations discussed in Section 3 above.
 - A set of output species names is not required; if they are present, their number must be the same as the entry in the first control parameter on Card 4, but they will be ignored by the program.
- > REGION. This packet must follow the CONTROL packet. The vertical parameters must be provided if FIXDHEIGHT or SAMEHEIGHT is selected. Otherwise, they will be ignored.
 - > UNITS. This packet, if present, must follow the REGION packet. The UNITS packet must be provided if:
 - Any input variable will be input in other than internal units.
 - Any user-defined variables are specified.
 - COORD or HEIGHT unit conversions are to be used.
 The number of user-defined variables must not exceed the maximum specified in the CONTROL packet.
 - > STATIONS. This packet is required if either of the methods STATINTERP or POISSON is specified. The number of stations listed must not exceed the maximum specified in the CONTROL packet.
 - > TIME INTERVAL. Two or more TIME INTERVAL packets must be present. The first time interval must begin at or before the beginning of the time span specified on Card 10 of the CONTROL packet. The last time interval must begin at or after the ending time of any simulation run. All time intervals must be contiguous and of nonzero length. Each TIME INTERVAL packet contains one or more of the following

packets and ends with an ENDTIME card. Following the first time interval, only those data that are to be changed need be specified.*

- > SUBREGION. The first time interval must contain a SUBREGION packet; the inclusion of this packet in other time intervals is optional. The number of subregions must not exceed the maximum specified in the CONTROL packet.
- > METHOD. A method must be provided for every variable--including user-defined variables--in every subregion in the first time interval. Methods can be changed in subsequent TIME INTERVAL packets if desired. Note that each parameter entry contributes to the overall parameter count; the total number of parameters must not exceed the maximum specified in the CONTROL packet.
- > CONSTANTS. If the method CONSTANT is assigned to any variable in the METHOD packet, the first time interval must contain a CONSTANTS packet. More than one CONSTANTS packet can appear in any time interval.
- > GRID VALUES. If the method GRID VALUE is assigned to any variable in the METHOD packet, the first time interval must contain a GRID VALUES packet. More than one GRID VALUES packet can appear in any time interval.
- > STATION READINGS. If either the POISSON or STATINTERP method is assigned to any variable in the METHOD packet, the first time interval must contain a STATION READINGS packet. More than one STATION READINGS packet can appear in any time interval.

5. Additional Input Files

If the method FIXDHEIGHT or SAMEHEIGHT was selected, the DIFFBREAK file must be input to REGNTP. Otherwise no additional input files are required.

* If FIXDHEIGHT or SAMEHEIGHT is used, the time intervals specified here must be exactly the same as those on the DIFFBREAK file; after the first time interval, subsequent packets may contain no other packets.

6. Examples

Exhibit VII-11 shows a sample input deck for REGIONTOP file generation. The output from a REGNTP run using that input deck is shown in Exhibit VII-12.

CONTROL						
REGIONTOP	HEIGHT OF THE TOP OF THE MODELING REGION	1	5			
26	1	1	1	1	0	
1	1	1	1	1	0	
11						
76195	500	76196	10			
END						
REGION						
725000.	4252000.	15				
-19000.	-15000.					
4000.	4000.					
17	22	4				
2	2	0.	50.	200.		
END						
TIME INTERVAL						
76195	500	76195	600			
SUBREGION						
A	1	1	-1			
END						
METHOD						
A	REGIONTOP FIXDHEIGHT	500.	2038.			1
UPCELLHT	200.					
END						
ENDTIME						
TIME INTERVAL						
76195	600	76195	700			
ENDTIME						
TIME INTERVAL						
76195	700	76195	800			
ENDTIME						
TIME INTERVAL						
76195	800	76195	900			
ENDTIME						
TIME INTERVAL						
76195	900	76195	1000			
ENDTIME						

Exhibit VII-11. Sample Input Deck from the REGNTP Program

TIME INTERVAL			
76195	1000	76195	1100
ENDTIME			
TIME INTERVAL			
76195	1100	76195	1200
ENDTIME			
TIME INTERVAL			
76195	1200	76195	1300
ENDTIME			
TIME INTERVAL			
76195	1300	76195	1400
ENDTIME			
TIME INTERVAL			
76195	1400	76195	1500
ENDTIME			
TIME INTERVAL			
76195	1500	76195	1600
ENDTIME			
TIME INTERVAL			
76195	1600	76195	1700
ENDTIME			
TIME INTERVAL			
76195	1700	76195	1800
ENDTIME			
TIME INTERVAL			
76195	1800	76195	1900
ENDTIME			
TIME INTERVAL			
76195	1900	76195	2000
ENDTIME			
TIME INTERVAL			
76195	2000	76195	2100
ENDTIME			
TIME INTERVAL			
76195	2100	76195	2200
ENDTIME			
TIME INTERVAL			
76195	2200	76195	2300
ENDTIME			
TIME INTERVAL			
76195	2300	76195	2400
ENDTIME			
TIME INTERVAL			
76195	2400	76196	10
ENDTIME			

Exhibit VII-11 (Concluded)

PROCESSING OF INPUT DATA FOR THE PREPARATION OF FILE REGIONTOP

HEIGHT OF THE TOP OF THE MODELING REGION

NUMBER OF STATIONS = 0
 NUMBER OF SUBREGIONS = 1
 NUMBER OF METHOD PARAMETERS = 5
 PROGRAM OUTPUT WILL BE PLACED ON FILE NUMBER 26
 INPUT DATA FOR DIFFUSION BREAK WILL BE OBTAINED FROM FILE NUMBER 11

INPUT CARDS WILL BE PRINTED

OUTPUT GRID WILL BE PRINTED

UNIT TABLE WILL BE PRINTED

STATION LOCATIONS WILL BE PRINTED

SUBREGION GRID WILL BE PRINTED

METHOD TABLE WILL BE PRINTED

STATION VALUES WILL NOT BE PRINTED

BEGINNING DATE OF FILE 76195 BEGINNING TIME OF FILE 5.00

ENDING DATE OF FILE 76196 ENDING TIME OF FILE .17

REGION
 725000. 4252000. 15
 -19000. -16000.
 4000.00 4000.00
 17 22 4
 2 .00 50.00 200.00
 END

FILE NAME --- REGION TOP		HEIGHT OF THE TOP OF THE MODELING REGION										PAGE 1
REGION TOP VALUES (IN METERS ABOVE GROUND LEVEL)		VERT. LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00										
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12
22	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000
21	502.0000	504.0061	505.9784	507.8764	509.6442	511.2035	512.4517	513.2621	513.4869	512.9678	511.5785	509.4017
20	502.0000	506.0492	510.0391	513.8977	517.5229	520.7653	523.4199	525.2271	525.8663	524.9496	522.0040	516.6038
19	502.0000	508.1576	514.2490	520.1900	525.8482	531.0156	535.3871	538.5582	540.0230	539.1342	534.8865	524.9782
18	502.0000	510.3394	518.6380	526.8301	534.7796	542.2370	548.8003	553.8979	556.8324	556.8625	553.3217	545.7940
17	502.0000	512.5715	523.1758	533.8129	544.3856	554.6312	564.0430	571.8205	576.9206	578.3270	575.4780	568.5566
16	502.0000	514.7858	527.7453	541.0099	554.5890	568.2632	581.4332	592.9575	601.1329	604.1504	601.2368	592.7235
15	502.0000	516.8553	532.1119	548.1159	565.0816	582.9509	601.1351	618.0985	630.9451	635.9049	631.8983	619.3304
14	502.0000	518.5852	535.8983	554.5894	575.1980	598.0348	622.8621	648.0858	669.0660	676.4828	670.2190	649.5590
13	502.0000	519.7123	538.5788	559.6205	583.7796	611.9917	645.0963	683.0558	721.0929	730.4662	721.8958	683.8507
12	502.0000	519.9191	539.5127	562.1920	589.1754	622.0373	663.4087	718.6224	802.0000	802.0000	802.0000	718.1304
11	502.0000	518.8524	537.9964	561.3214	589.7096	624.6137	668.7601	726.5473	802.0000	802.0000	802.0000	724.6042
10	502.0000	516.1240	533.1719	556.4365	584.8351	618.9656	661.2449	717.1955	802.0000	802.0000	802.0000	713.3499
9	502.0000	511.3740	523.2244	547.5830	575.3284	606.0785	640.6791	679.2575	717.1860	725.2433	714.3020	672.3603
8	502.0000	505.3165	502.0000	536.5030	563.7951	590.0691	616.5829	642.1357	662.1583	667.2108	657.2377	631.7732
7	502.0000	507.2511	514.7118	533.6508	554.0439	574.3307	593.7312	610.6377	622.0515	624.0679	615.5090	596.6989
6	502.0000	508.3177	517.0373	530.1234	544.9114	559.7828	573.5247	584.6783	591.3240	591.4567	583.9997	568.4714
5	502.0000	508.1039	515.7802	525.3862	535.9775	546.5089	555.9673	563.2427	567.1079	566.4374	560.5847	549.4631
4	502.0000	507.0870	513.0524	519.9097	527.2197	534.3517	540.6021	545.2149	547.4289	546.6159	542.4751	535.1894
3	502.0000	505.6063	509.6386	514.0663	518.6635	523.0710	526.8604	529.5737	530.7749	530.1351	527.5416	523.2044
2	502.0000	503.8637	505.8902	508.0631	510.2833	512.3872	514.1739	515.4294	515.9563	515.6151	514.3737	512.3549
1	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000	502.0000

Exhibit VII-12 (Continued)

REGION TOPVALUES (IN METERS ABOVE GROUND LEVEL) VERT. LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00

GRID CELL	13	14	15	16	17
22	502.0000	502.0000	502.0000	502.0000	502.0000
21	507.2683	507.4373	507.3662	505.8242	502.0000
20	509.6837	511.9638	512.2625	509.0659	502.0000
19	502.0000	516.8008	518.0606	512.6005	502.0000
18	535.3789	532.9462	527.3580	517.1122	502.0000
17	558.9566	549.4731	537.5922	521.9777	502.0000
16	580.1956	565.2262	547.5758	526.6674	502.0000
15	601.3668	580.3163	556.8746	530.8992	502.0000
14	623.0223	594.5563	565.1207	534.4611	502.0000
13	644.1440	606.8965	571.6151	537.0459	502.0000
12	660.6950	614.9730	575.1758	538.1938	502.0000
11	663.9149	615.4856	574.4594	537.4240	502.0000
10	653.7866	607.5854	568.9463	534.5254	502.0000
9	629.6791	591.6240	558.8958	529.6244	502.0000
8	600.6825	570.1863	545.3731	523.1938	502.0000
7	571.0517	543.1141	529.3504	515.9792	502.0000
6	543.7772	502.0000	513.1119	509.5702	502.0000
5	533.6663	515.8389	511.6856	507.3430	502.0000
4	525.6634	516.0918	510.5570	506.2150	502.0000
3	517.7668	512.3746	508.3042	505.0166	502.0000
2	509.8677	507.3805	505.3094	503.5776	502.0000
1	502.0000	502.0000	502.0000	502.0000	502.0000
TIME INTERVAL					
76195	600	76195	700		
ENDTIME					

H. ROADWAY (Not recommended for use at this time)

The ROADWAY file contains time-varying matrices of emission fluxes along roadways and a descriptive parameter for automobile traffic. The ROADWAY file can be omitted from a simulation run if surface layer micro-scale calculations are not to be performed. At present, there is no general purpose program for creating the ROADWAY file because its generation is highly dependent on the form of the traffic data available. There is a program structure, similar to that of the other data preparation programs, that includes the reading of control packets, unit conversions, and writing the proper output records. This program can be tailored to particular input requirements as necessary. The skeleton program is named ROADWY. It requires subroutines from the libraries UTILITY and FILUTIL. Figure VII-15 is an information flow diagram illustrating the job control to be used. In the following sections we discuss the card input to the ROADWY program.

1. Variables

The output variables for the ROADWAY file are the species named in the CONTROL packet and the parameter CARM, which is to be calculated from the traffic data. Additional user-defined input variables (e.g. "reactive hydrocarbons") can be specified in the UNITS packet. The internal units for the roadway emissions of all species except AEROSOLS are gram-moles per hour (g-mol/hr); for AEROSOLS, the units are grams per hour (g/hr). The internal units for CARM are meters per hour (m/hr). The standard names for reactive species recognized by the Airshed Simulation Program are listed in Chapter IX. If any of these species does not appear on the ROADWAY file, the roadway emissions will default to zero. If any additional species appear on ROADWAY, they will be ignored.

2. Methods

The methods that can be used to generate the ROADWAY file are:




Figure VII-15. Information Flow Diagram for the ROADWAY File

- > CONSTANT
- > ROADVALUE
- > SPLIT/COMB
- > USER.

The methods ROADVALUE and USER have not been defined. The actual methods for generating output values from input traffic data must be written for each new application.

3. Time Variation

The time span of the ROADWAY file must include the entire time span of the simulation runs for which it is to be used. Roadway emissions and the parameter CARM are considered to be constant during each time interval.

4. Packets

The packets to be used for ROADWAY will depend on the particular version that is developed for a given set of traffic data. Information on control parameters, definition of link-node data, units, time intervals, computation methods, and data entry will have to be provided when the program has been implemented. Figure VII-16 shows a possible input structure in terms of the packets to be used.

5. Additional Input Files

In general, a traffic data file in link-node form must be provided.




Figure VII-16. A Possible Input Card Deck Structure for Preparing the ROADWAY File

I. TEMPERATUR

The TEMPERATUR file contains time-varying matrices of temperatures at ground level. If it is omitted from a simulation run, temperature-dependent calculations will not be performed (see Section IX.B). The program TMPRTR is used to create the TEMPERATUR file. TMPRTR requires subroutines from the libraries UTILITY and FILUTIL. Figure VII-17 is an information flow diagram illustrating the job control to be used. In the following sections we discuss the input to the TMPRTR program.

1. Variables

The output variable for the TEMPERATUR file is also named TEMPERATUR. This is an "implicit output variable" and need not be referred to anywhere in the CONTROL packet. The internal units for TEMPERATUR are °K. If the input values for this variable are to be in any other units, TEMPERATUR must be specified in the UNITS packet..

2. Methods

The methods that can be used to generate the TEMPERATUR file are:

- > CONSTANT
- > GRID VALUE
- > STATINTERP
- > POISSON
- > E-WINTERP
- > N-SINTERP
- > USER.

These methods are discussed in detail in Section VI.A.6.




Figure VII-17. Information Flow Diagram for the TEMPERATUR File

3. Time Variation

The time span of the TEMPERATUR file must include the entire time span of the simulation runs for which it is to be used. Ground-level temperatures are considered to be constant during each time interval.

4. Packets

Figure VII-18 shows the input deck structure in terms of the packets to be used. Each of these packets is described in detail in Section VI.B. Following are special input packet considerations for the TEMPERATUR file:

> CONTROL

- The file name on Card 2 must be TEMPERATUR.
- The control variables to be specified on Cards 4 to 8 for TEMPERATUR are shown in Table VII-7.
- The number of species should be zero.
- If there are input variables that do not appear as output variables, their number must appear as the number of user-defined variables. All such variables must also be named in the UNITS packet.
- If data from measuring stations are to be used (methods STATINTERP or POISSON), the maximum number of such stations must be given.
- The number of subregions must be at least one.
- The maximum number of parameters must be sufficient to include all specifications of all parameters.
- The vertical controls card (No. 7) should be left blank.
- The file unit assignment card (No. 8) should be left blank.
- The beginning and ending dates and times should reflect the time variation considerations discussed in Section 3 above.




Figure VII-18. Input Card Deck Structure for Preparing the TEMPERATUR File

Table VII-7. CONTROL Packet Entries for the TEMPERATUR File

<u>Card Number</u>	<u>Entry</u>
4	Number of species (=0)
	Number of user-defined variables
	Number of stations
	Number of subregions
	Number of parameters
	Spare
5	Output file number
	Print input cards
	Print output grid
	Spare
	Spare
	Spare
6	Print units table
	Print station locations table
	Print regional grid
	Print methods table
	Print station values table
	Spare
7	Spare
	Spare
	Spare
	Spare
	Spare
	Spare
8	Spare
	Spare
	Spare
	Spare
	Spare
	Spare

- A set of output species names is not required; if they are present, their number must be the same as the entry in the first control parameter on Card 4, but they will be ignored by the program.
- > REGION. This packet must follow the CONTROL packet. The vertical parameters will be ignored for the TEMPERATUR file.
- > UNITS. This packet, if present, must follow the REGION packet. The UNITS packet must be provided if:
 - Any input variable will be input in other than internal units.
 - Any user-defined variables are specified.
 - COORD or HEIGHT unit conversions are to be used.
 The number of user-defined variables must not exceed the maximum specified in the CONTROL packet.
- > STATIONS. This packet is required if either of the methods STATINTERP or POISSON is specified. The number of stations listed must not exceed the maximum specified in the CONTROL packet.
- > TIME INTERVAL. One or more TIME INTERVAL packets must be present. The first time interval must begin at or before the beginning of the time span specified on Card 10 of the CONTROL packet. All time intervals must be contiguous and of nonzero length. Each TIME INTERVAL packet contains one or more of the following packets and ends with an ENDTIME card. Following the first time interval, only those data that are to be changed need be specified.
- > SUBREGION. The first time interval must contain a SUBREGION packet; the inclusion of this packet in other time intervals is optional. The number of subregions must not exceed the maximum specified in the CONTROL packet.
- > METHOD. A method must be provided for every variable--including user-defined variables--in every subregion in the first time interval. Methods can be changed in subsequent TIME INTERVAL packets if desired. Note that each parameter

entry contributes to the overall parameter count; the total number of parameters must not exceed the maximum specified in the CONTROL packet.

- > CONSTANTS. If the method CONSTANT is assigned to any variable in the METHOD packet, the first time interval must contain a CONSTANTS packet. More than one CONSTANTS packet can appear in any time interval.
- > GRID VALUES. If the method GRID VALUE is assigned to any variable in the METHOD packet, the first time interval must contain a GRID VALUES packet. More than one GRID VALUES packet can appear in any time interval.
- > STATION READINGS. If either the POISSON or STATINTERP method is assigned to any variable in the METHOD packet, the first time interval must contain a STATION READINGS packet. More than one STATION READINGS packet can appear in any time interval.

5. Additional Input Files

No additional input files are required.

6. Examples

Exhibit VII-13 shows a sample input deck for TEMPERATUR file generation. The output from a TMPRTR run using that input deck is shown in Exhibit VII-14.

CONTROL							
TEMPERATURE							
TEMPERATURE FIELD FOR ST. LOUIS DAY 195							
0	0	25	1				10
28	1	1					
76195	500	76195	2400				
END							
REGION							
725000.	4252000.	15					
-19000.	-16000.						
4000.	4000.						
17	22	4					
2	2	0.0	50.				200.
END							
UNITS							
TEMPERATUREDEGREES C		1.	273.				1.
END							

Exhibit VII-13. Sample Input Deck for the TMRTR Program

STATIONS	101	19103.	27062.	10.
	102	17510.	34045.	10.
	103	22508.	30467.	10.
	104	22312.	25304.	10.
	105	18706.	24453.	10.
	106	13660.	25566.	10.
	107	15179.	30610.	10.
	108	23407.	39102.	10.
	109	30802.	27896.	10.
	110	22209.	20826.	10.
	111	13012.	20479.	10.
	112	8938.	28913.	10.
	113	12738.	37020.	10.
	114	19320.	45456.	10.
	115	32111.	45799.	10.
	116	37777.	38083.	10.
	117	35560.	20818.	10.
	118	18065.	11256.	10.
	119	4759.	18547.	10.
	120	-1921.	33909.	10.
	121	7414.	50376.	10.
	122	16631.	77223.	10.
	123	52320.	34378.	10.
	124	24275.	-15463.	10.
	125	-27555.	30240.	10.

END
TIME INTERVAL

76195	500	76195	600
SUBREGION			
A	1	1	-1

END

METHOD

A	TEMPERATURPOISSON
---	-------------------

MAXITER

100

ERRORTOL

0.05

OMEGA

1.4

END

1. 50. 3

Exhibit VII-13 (Continued)

STATION READINGS	
101	TEMPERATUR 22.4
102	TEMPERATUR 21.9
103	TEMPERATUR 21.7
104	TEMPERATUR 21.4
105	TEMPERATUR 21.8
106	TEMPERATUR 22.2
107	TEMPERATUR 22.5
108	TEMPERATUR 21.3
109	TEMPERATUR 21.4
110	TEMPERATUR 21.3
111	TEMPERATUR 21.3
112	TEMPERATUR 22.1
113	TEMPERATUR 21.4
114	TEMPERATUR 21.2
115	TEMPERATUR 21.7
116	TEMPERATUR 20.3
117	TEMPERATUR 20.4
118	TEMPERATUR 21.2
119	TEMPERATUR 21.6
120	TEMPERATUR 22.3
121	TEMPERATUR 21.4
122	TEMPERATUR 20.0
123	TEMPERATUR 20.5
124	TEMPERATUR 19.8
125	TEMPERATUR 21.4
END	

Exhibit VII-13 (Continued)

TEMP FOR 500

STATION READINGS	
101	TEMPERATUR 22.0
102	TEMPERATUR 21.3
103	TEMPERATUR 20.3
104	TEMPERATUR 20.8
105	TEMPERATUR 21.8
106	TEMPERATUR 22.2
107	TEMPERATUR 22.0
108	TEMPERATUR 20.4
109	TEMPERATUR 20.0
110	TEMPERATUR 20.2
111	TEMPERATUR 21.2
112	TEMPERATUR 21.8
113	TEMPERATUR 20.9
114	TEMPERATUR 20.0
115	TEMPERATUR 20.3
116	TEMPERATUR 19.4
117	TEMPERATUR 19.6
118	TEMPERATUR 20.0
119	TEMPERATUR 21.1
120	TEMPERATUR 21.9
121	TEMPERATUR 20.4
122	TEMPERATUR 19.5
123	TEMPERATUR 19.1
124	TEMPERATUR 19.1
125	TEMPERATUR 21.2

END

ENDTIME

TIME INTERVAL

76195

600

700

76195

TEMP FOR 600

PROCESSING OF INPUT DATA FOR THE PREPARATION OF FILE TEMPERATUR

TEMPERATURE FIELD FOR ST. LOUIS DAY 195

NUMBER OF STATIONS = 25
 NUMBER OF SUBREGIONS = 1
 NUMBER OF METHOD PARAMETERS = 10
 PROGRAM OUTPUT WILL BE PLACED ON FILE NUMBER 28
 INPUT CARDS WILL BE PRINTED
 OUTPUT GRID WILL BE PRINTED
 UNIT TABLE WILL NOT BE PRINTED
 STATION LOCATIONS WILL NOT BE PRINTED
 SUBREGION GRID WILL NOT BE PRINTED
 METHOD TABLE WILL NOT BE PRINTED
 STATION VALUES WILL NOT BE PRINTED
 BEGINNING DATE OF FILE 76195 BEGINNING TIME OF FILE 5.00
 ENDING DATE OF FILE 76195 ENDING TIME OF FILE 24.00

REGION	725000.	4252000.	15
	-19000.	-16000.	
	4000.00	4000.00	
	17	22	4
	2	2	.00
			50.00
			200.00
END			

Exhibit VII-14. Sample Output from the TMPRTR Program

FILE NAME -- TEMPERATUR		TEMPERATURE FIELD FOR ST. LOUIS DAY 195										PAGE 1
TEMPERATURE VALUES (IN DEGREES KELVIN ATGROUND LEVEL)		VERT. LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00										
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12
22	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000
21	292.1000	292.1427	292.1843	292.2232	292.2577	292.2863	292.3070	292.3189	292.3246	292.3269	292.3273	292.3228
20	292.1000	292.1868	292.2711	292.3501	292.4201	292.4774	292.5169	292.5343	292.5378	292.5351	292.5304	292.5189
19	292.1000	292.2338	292.3639	292.4858	292.5944	292.6837	292.7434	292.7542	292.7425	292.7251	292.7118	292.6927
18	292.1000	292.2853	292.4657	292.6351	292.7871	292.9168	293.0133	292.9875	292.9389	292.8914	292.8729	292.8534
17	292.1000	292.3425	292.5791	292.8013	293.0000	293.1791	293.4000	293.2338	293.1201	293.0101	293.0106	293.0120
16	292.1000	292.4059	292.7066	292.9893	293.2285	293.3913	293.4820	293.4164	293.2820	293.0000	293.1240	293.1685
15	292.1000	292.4745	292.8510	293.2182	293.5277	293.6664	293.7068	293.6523	293.5701	293.4127	293.2920	293.2051
14	292.1000	292.5407	293.0027	293.5015	293.9912	294.0301	294.0137	293.9000	293.9121	293.7621	293.4000	293.2309
13	292.1000	292.5841	293.1153	293.7895	294.9000	294.4395	294.4049	294.3544	294.3960	294.3000	293.5706	293.2619
12	292.1000	292.5780	293.0821	293.6364	294.2126	294.4150	294.8000	294.7025	295.0000	294.4038	293.3000	293.2116
11	292.1000	292.5431	292.9955	293.4575	293.8931	294.2008	294.4509	294.6431	295.2000	295.0000	293.8000	293.2757
10	292.1000	292.4966	292.8972	293.3018	293.6969	294.0384	294.1521	294.2098	294.2000	293.9881	293.2000	293.0827
9	292.1000	292.4447	292.7934	293.1538	293.5514	294.1000	293.9037	293.8375	293.7469	293.5457	293.1952	292.9836
8	292.1000	292.3887	292.6779	292.9673	293.2525	293.5040	293.5219	293.4857	293.4003	293.2491	293.0489	292.8701
7	292.1000	292.3330	292.5633	292.7851	292.9863	293.1394	293.1922	293.1811	293.1178	293.0000	292.8803	292.7466
6	292.1000	292.2812	292.4584	292.6247	292.7690	292.8751	292.9258	292.9278	292.8885	292.8151	292.7257	292.6252
5	292.1000	292.2352	292.3666	292.4881	292.5915	292.6676	292.7088	292.7160	292.6931	292.6458	292.5825	292.5090
4	292.1000	292.1951	292.2873	292.3720	292.4436	292.4968	292.5276	292.5357	292.5229	292.4929	292.4503	292.3992
3	292.1000	292.1600	292.2183	292.2718	292.3170	292.3509	292.3714	292.3778	292.3713	292.3537	292.3275	292.2954
2	292.1000	292.1288	292.1569	292.1827	292.2046	292.2211	292.2313	292.2349	292.2322	292.2241	292.2117	292.1963
1	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000	292.1000

FILE NAME -- TEMPERATUR TEMPERATURE FIELD FOR ST. LOUIS DAY 195

TEMPERATURE VALUES (IN DEGREES KELVIN ATGROUND LEVEL) VERT. LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00

GRID CELL	13	14	15	16	17
22	292.1000	292.1000	292.1000	292.1000	292.1000
21	292.3098	292.2851	292.2458	292.1874	292.1000
20	292.4899	292.4375	292.3584	292.2488	292.1000
19	292.6503	292.5670	292.4482	292.2942	292.1000
18	292.8037	292.6838	292.5207	292.3274	292.1000
17	292.9857	292.7933	292.5759	292.3480	292.1000
16	293.3000	292.8876	292.5972	292.3500	292.1000
15	293.0997	292.8293	292.5434	292.3241	292.1000
14	293.0325	292.7598	292.4000	292.2829	292.1000
13	293.0157	292.7565	292.4927	292.2955	292.1000
12	292.9955	292.7442	292.5077	292.2993	292.1000
11	293.0000	292.7093	292.4890	292.2909	292.1000
10	292.8676	292.6000	292.4457	292.2739	292.1000
9	292.7846	292.5855	292.4193	292.2589	292.1000
8	292.7009	292.5377	292.3870	292.2424	292.1000
7	292.6112	292.4777	292.3489	292.2237	292.1000
6	292.5197	292.4131	292.3076	292.2034	292.1000
5	292.4297	292.3478	292.2651	292.1825	292.1000
4	292.3428	292.2834	292.2227	292.1615	292.1000
3	292.2593	292.2208	292.1811	292.1407	292.1000
2	292.1787	292.1599	292.1402	292.1202	292.1000
1	292.1000	292.1000	292.1000	292.1000	292.1000

Exhibit VII-14 (Concluded)

J. TERRAIN

The TERRAIN file contains time-invariant matrices of surface roughness and vegetation factors that are used by the Airshed Simulation Program to calculate vertical diffusivity and surface deposition. If the TERRAIN file is omitted from a simulation run, single values for surface roughness and vegetation factors will be used (see Section IX.B). The program TERRAIN is used to create the TERRAIN file. TERRAIN requires subroutines from the libraries UTILITY and FILUTIL. Figure VII-19 is an information flow diagram illustrating the job control to be used. In the following sections we discuss the input to the TERRAIN program.

1. Variables

The TERRAIN program has two implicit output variables: ROUGHNESS and VEGFACTOR. The internal units for ROUGHNESS are meters (m); VEGFACTOR is the fraction of surface uptake capability compared to that of alfalfa. If the input values for ROUGHNESS are to be in any other units, that variable must be specified in the UNITS packet. VEGFACTOR is unitless; therefore, its units cannot be changed.

2. Methods

The methods that can be used to generate the TERRAIN file are:

- > CONSTANT
- > GRID VALUE
- > STATINTERP
- > POISSON
- > E-WINTERP
- > N-SINTERP
- > USER.

These methods are discussed in detail in Section VI.A.6.




Figure VII-19. Information Flow Diagram for the TERRAIN File

3. Time Variation

The TERRAIN file contains values for surface characteristics that are considered to be invariant over time.

4. Packets

Figure VII-20 shows the input deck structure in terms of the packets to be used. Each of these packets is described in detail in Section VI.B. Following are special input packet considerations for the TERRAIN file:

> CONTROL

- The file name on Card 2 must be TERRAIN.
- The control variables to be specified on Cards 4 to 8 for TERRAIN are shown in Table VII-8.
- The number of species should be zero.
- If there are input variables that do not appear as output variables, their number must appear as the number of user-defined variables. All such variables must also be named in the UNITS packet.
- If data from measuring stations are to be used (methods STATINTERP or POISSON), the maximum number of such stations must be given.
- The number of subregions must be at least one.
- The maximum number of parameters must be sufficient to include all specifications of all parameters.
- The vertical controls card (No. 7) should be left blank.
- The file unit assignment card (No. 8) should be left blank.
- The beginning and ending dates and times can be any valid numbers. They are ignored by the Airshed Simulation Program.
- A set of output species names is not required; if they are present, their number must be the same as the entry in the first control parameter on Card 4, but they will be ignored by the program.




Figure VII-20. Input Card Deck Structure for Preparing the TERRAIN File

Table VII-8. CONTROL Packet Entries for the TERRAIN File

<u>Card Number</u>	<u>Entry</u>
4	Number of species (=0)
	Number of user-defined variables
	Number of stations
	Number of subregions
	Number of parameters
	Spare
5	Output file number
	Print input cards
	Print output grid
	Spare
	Spare
6	Print units table
	Print station locations table
	Print regional grid
	Print methods table
	Print station values table
	Spare
7	Spare
	Spare
	Spare
	Spare
	Spare
	Spare
8	Spare
	Spare
	Spare
	Spare
	Spare
	Spare

- > REGION. This packet must follow the CONTROL packet. The vertical parameters will be ignored for the TERRAIN file.
- > UNITS. This packet, if present, must follow the REGION packet. The UNITS packet must be provided if:
 - Any input variable will be input in other than internal units.
 - Any user-defined variables are specified.
 - COORD or HEIGHT unit conversions are to be used.
 The number of user-defined variables must not exceed the maximum specified in the CONTROL packet.
- > STATIONS. This packet is required if either method STATINTERP or POISSON is specified. The number of stations listed must not exceed the maximum specified in the CONTROL packet.
- > SUBREGION. A SUBREGION packet is required. The number of subregions must not exceed the maximum specified in the CONTROL packet.
- > METHOD. A method must be provided for every variable--including user-defined variables--in every subregion. Note that each parameter entry contributes to the overall parameter count; the total number of parameters must not exceed the maximum specified in the CONTROL packet.
- > CONSTANTS. If the method CONSTANT is assigned to any variable in the METHOD packet, there must be one or more CONSTANTS packets.
- > GRID VALUES. If the method GRID VALUE is assigned to any variable in the METHOD packet, there must be one or more GRID VALUES packets.
- > STATION READINGS. If either the POISSON or STATINTERP method is assigned to any variable in the METHOD packet, there must be one or more STATION READINGS packets.
- > END TERRAIN. This card must appear to indicate that no more packets are to be read.

5. Additional Input Files

No additional input files are required.

6. Examples

Exhibit VII-15 shows a sample input deck for TERRAIN file generation. The output from a TERRAIN run using that input deck is shown in Exhibit VII-16.

CONTROL					
TERRAIN					
	SURFACE ROUGHNESS AND VEGETATIVE FACTORS				
	0	0	0	0	1
	11	0	1		
	0	0	0	0	1
	0				
	0				
74001	000	78365	2400		
END					
REGION					
725000.	4252000.	15			
-19000.	-16000.				
4000.	4000.				
17	22	4			
2	2	0.	50.	200.	
END					
SUBREGION	1	1	-1		
A					
END					
METHOD					
A	ALL	GRIDVALUE	0.	100.	
END					
GRIDVALUES					
A	ROUGHNESS	1	1	.48	
A	ROUGHNESS	2	1	.48	
A	ROUGHNESS	3	1	.48	
A	ROUGHNESS	4	1	.48	
A	ROUGHNESS	5	1	.48	
A	ROUGHNESS	6	1	.36	
A	ROUGHNESS	7	1	.31	
A	ROUGHNESS	8	1	.21	
A	ROUGHNESS	9	1	.19	
A	ROUGHNESS	10	1	.29	
A	ROUGHNESS	11	1	.29	
A	ROUGHNESS	12	1	.28	
A	ROUGHNESS	13	1	.28	
A	ROUGHNESS	14	1	.27	
A	ROUGHNESS	15	1	.27	
A	ROUGHNESS	16	1	.27	
A	ROUGHNESS	17	1	.27	
A	ROUGHNESS	1	2	.48	
A	ROUGHNESS	2	2	.48	
A	ROUGHNESS	3	2	.48	
A	ROUGHNESS	4	2	.48	
A	ROUGHNESS	5	2	.48	
A	ROUGHNESS	6	2	.36	
A	ROUGHNESS	7	2	.31	

A	ROUGHNESS	6	2	.21
A	ROUGHNESS	9	2	.19
A	ROUGHNESS	10	2	.29
A	ROUGHNESS	11	2	.29
A	ROUGHNESS	12	2	.28
A	ROUGHNESS	13	2	.28
A	ROUGHNESS	14	2	.27
A	VEGFAC10R	2	21	1.00
A	VEGFAC10R	3	21	1.00
A	VEGFAC10R	4	21	1.00
A	VEGFAC10R	5	21	1.00
A	VEGFAC10R	6	21	1.00
A	VEGFAC10R	7	21	1.00
A	VEGFAC10R	8	21	1.00
A	VEGFAC10R	9	21	1.00
A	VEGFAC10R	10	21	1.00
A	VEGFAC10R	11	21	1.00
A	VEGFAC10R	12	21	1.00
A	VEGFAC10R	13	21	1.00
A	VEGFAC10R	14	21	1.00
A	VEGFAC10R	15	21	1.00
A	VEGFAC10R	16	21	1.00
A	VEGFAC10R	17	21	1.00
A	VEGFAC10R	1	22	1.00
A	VEGFAC10R	2	22	1.00
A	VEGFAC10R	3	22	1.00
A	VEGFAC10R	4	22	1.00
A	VEGFAC10R	5	22	1.00
A	VEGFAC10R	6	22	1.00
A	VEGFAC10R	7	22	1.00
A	VEGFAC10R	8	22	1.00
A	VEGFAC10R	9	22	1.00
A	VEGFAC10R	10	22	1.00
A	VEGFAC10R	11	22	1.00
A	VEGFAC10R	12	22	1.00
A	VEGFAC10R	13	22	1.00
A	VEGFAC10R	14	22	1.00
A	VEGFAC10R	15	22	1.00
A	VEGFAC10R	16	22	1.00
A	VEGFAC10R	17	22	1.00
A	END			
A	ENDTERRAIN			

PROCESSING OF INPUT DATA FOR THE PREPARATION OF FILE TERRAIN

SURFACE ROUGHNESS AND VEGETATIVE FACTORS

```

REGION
725000. 4252000. 15
-19000. -16000.
4000.00 4000.00
17 22 4
2 2 .00 50.00 200.00
END
KCRNT = 41 NSCLFT = 26960 IN SCRSET
KCRNT = 81 NSCLFT = 26920 IN SCRSET
KCRNT = 85 NSCLFT = 26916 IN SCRSET
KCRNT = 89 NSCLFT = 26912 IN SCRSET
KCRNT = 93 NSCLFT = 26908 IN SCRSET
KCRNT = 103 NSCLFT = 26898 IN SCRSET
KCRNT = 477 NSCLFT = 26524 IN SCRSET
KCRNT = 479 NSCLFT = 26522 IN SCRSET
KCRNT = 481 NSCLFT = 26520 IN SCRSET
KCRNT = 483 NSCLFT = 26518 IN SCRSET
KCRNT = 485 NSCLFT = 26516 IN SCRSET
KCRNT = 487 NSCLFT = 26514 IN SCRSET
KCRNT = 861 NSCLFT = 26626 IN SCRSET
KCRNT = 1235 NSCLFT = 26252 IN SCRSET
KCRNT = 1983 NSCLFT = 25504 IN SCRSET
SUBREGION
METHOD

```

METHODS TABLE

SUBREGION	VARIABLE	METHOD	MIN. VALUE	MAX. VALUE	PARAMETER	PAR. VALUE
A	ROUGHNESS	GRIDVALUE	.0000	100.0000		
A	VEGFACTOR	GRIDVALUE	.0000	100.0000		
GRIDVALUES						
ENDTERRAIN						

Exhibit VII-16. Sample Output from the TERRAIN Program

FILE NAME --- TERRAIN		SURFACE ROUGHNESS AND VEGETATIVE FACTORS										PAGE 1	
TERRAIN VALUES (IN METERS OR ALFALFA EQUIVALENTS)		ROUGHNESS		VERT.		LEVEL 1 START DATE/TIME		0 .00 STOP DATE/TIME		0 .00		0 .00	
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12	
22	.2300	.2300	.2300	.2300	.2300	.2800	.2900	.2600	.2900	.2800	.2500	.2800	
21	.2300	.2300	.2300	.2300	.2300	.2800	.2900	.2600	.2900	.2800	.2500	.2800	
20	.2300	.2300	.2300	.2300	.2300	.2800	.2900	.2600	.2900	.2800	.2500	.2800	
19	.2200	.2200	.2200	.2200	.2200	.2700	.2800	.2500	.2700	.3400	.3200	.2600	
18	.2100	.2100	.2100	.2100	.2100	.2600	.2700	.2500	.2400	.1600	.1600	.5100	
17	.2200	.2200	.2200	.2200	.2200	.2600	.2700	.2500	.2400	.1500	.1500	.2700	
16	.2900	.2900	.2900	.2900	.2900	.3800	.5200	.4400	.3600	.2300	.1700	.1900	
15	.4400	.4400	.4400	.4400	.4400	.5900	.6700	.5700	.5100	.3400	.1800	.2000	
14	.6400	.6400	.6400	.6400	.6400	.7800	.7400	.6600	.6900	.2300	.3900	.4600	
13	.6700	.6700	.6700	.6700	.6700	.8000	.7400	.9400	1.5500	.4200	.6800	.2100	
12	.5900	.5900	.5900	.5900	.5900	.6300	.6600	2.0100	3.1700	1.7800	.3900	.3900	
11	.5800	.5800	.5800	.5800	.5800	.5800	.6700	1.2000	2.2000	1.2000	1.1200	.6700	
10	.8200	.8200	.8200	.8200	.8200	.8800	.8400	1.8400	2.2400	.5400	.3700	.4600	
9	.5400	.5400	.5400	.5400	.5400	.5300	.5200	.5600	.5500	.3800	.3300	.3400	
8	.4700	.4700	.4700	.4700	.4700	.5400	.5600	.4500	.2300	.4100	.3000	.3000	
7	.4700	.4700	.4700	.4700	.4700	.4900	.4800	.3700	.2300	.2800	.3400	.3400	
6	.4900	.4900	.4900	.4900	.4900	.3800	.3300	.2300	.2100	.3400	.2900	.3000	
5	.4800	.4800	.4800	.4800	.4800	.3600	.3100	.2100	.1900	.2900	.2800	.2800	
4	.4800	.4800	.4800	.4800	.4800	.3600	.3100	.2100	.1900	.2900	.2900	.2800	
3	.4800	.4800	.4800	.4800	.4800	.3600	.3100	.2100	.1900	.2900	.2900	.2800	
2	.4800	.4800	.4800	.4800	.4800	.3600	.3100	.2100	.1900	.2900	.2900	.2800	
1	.4800	.4800	.4800	.4800	.4800	.3600	.3100	.2100	.1900	.2900	.2900	.2800	

Exhibit VII-16 (Continued)

FILE NAME -- TERRAIN		SURFACE ROUGHNESS AND VEGETATIVE FACTORS										PAGE 1
TERRAIN VALUES (IN METERS OR ALFALFA EQUIVALENTS) VEGFACTOR		VERT.		LEVEL 1		START DATE/TIME		STOP DATE/TIME		0		0 .00
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12
22	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
21	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
20	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
19	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
18	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
17	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
16	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
15	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
14	1.0000	1.0000	1.0000	1.0000	1.0000	.5000	.5000	1.0000	1.0000	1.0000	1.0000	1.0000
13	1.0000	1.0000	1.0000	1.0000	1.0000	.5000	.5000	.5000	.5000	1.0000	1.0000	1.0000
12	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	.5000	.5000	.5000	1.0000	1.0000
11	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	.5000	.5000	.5000	1.0000	1.0000
10	.5000	.5000	.5000	.5000	.5000	.5000	.5000	.5000	.5000	1.0000	1.0000	1.0000
9	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
8	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
7	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
6	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
5	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
4	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
3	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
2	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000
1	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000	1.0000

Exhibit VII-16 (Concluded)

K. TOPCONC

The TOPCONC file contains time-varying matrices of pollutant concentrations at the top of the region. The program TPCONC is used to create the TOPCONC file. TPCONC requires subroutines from the libraries UTILITY and FILUTIL. Figure VII-21 is an information flow diagram illustrating the job control to be used. The following sections discuss the input to the TPCONC program.

1. Variables

The output variables for the TOPCONC file are the species named in the CONTROL packet. Additional user-defined input variables (e.g. "reactive hydrocarbons") can be specified in the UNITS packet. The internal units for the concentrations of all species except AEROSOLS are parts per million (ppm); for AEROSOLS, the units are micrograms per cubic meter ($\mu\text{g}/\text{m}^3$). The standard names for reactive species recognized by the Airshed Simulation Program are listed in Section IX.A. If any of these species does not appear on the TOPCONC file, the top concentrations will default to a value defined in the CHEMPARAM file. If any additional species appear on TOPCONC, they will be ignored.

2. Methods

The methods that can be used to generate the TOPCONC file are:

- > CONSTANT
- > GRID VALUE
- > STATINTERP
- > POISSON
- > SPLIT/COMB
- > ABSTOPCONC
- > RELTOPCONC




Figure VII-21. Information Flow Diagram for the TOPCONC File

- > E-WINTERP
- > N-SINTERP
- > USER.

These methods are discussed in detail in Section VI.A.6.

3. Time Variation

The time span of the TOPCONC file must include the entire time span of the simulation runs for which it is to be used. Concentrations at the top of the region are considered to be constant during each time interval.

4. Packets

Figure VII-22 shows the input deck structure in terms of the packets to be used. Each of these packets is described in detail in Section VI.B. Following are special input packet considerations for the TOPCONC file.

- > CONTROL
 - The file name on Card 2 must be TOPCONC.
 - The control variables to be specified on Cards 4 to 8 for TOPCONC are shown in Table VII-9.
 - The number of species must be greater than zero.
 - If there are input variables that do not appear as output variables, their number must appear as the number of user-defined variables. All such variables must also be named in the UNITS packet.
 - If data from measuring stations are to be used (methods STATINTERP or POISSON), the maximum number of such stations must be given.
 - The number of subregions must be at least one.
 - The maximum number of parameters must be sufficient to include all specification of all parameters.




Figure VII-22. Input Card Deck Structure for Preparing the TOPCONC File

Table VII-9. CONTROL Packet Entries for the TOPCONC File

<u>Card Number</u>	<u>Entry</u>
4	Number of species
	Number of user-defined variables
	Number of stations
	Number of subregions
	Number of parameters
	Spare
5	Output file number
	Print input cards
	Print output grid
	Spare
	Spare
	Spare
6	Print units table
	Print station locations table
	Print regional grid
	Print methods table
	Print station values table
	Spare
7	Spare
	Number of heights in profile
	Spare
	Print vertical profile tables
	Spare
	Spare
8	DIFFBREAK file number
	REGIONTOP file number
	Spare
	Spare
	Spare
	Spare

- The vertical controls card (No. 7) must contain the maximum number of profile heights if ABSTOPCONC or RELTOPCONC is used. Otherwise, this card should be blank.
 - The file unit assignment card (No. 8) must provide an entry for REGIONTOP if the method ABSTOPCONC or RELTOPCONC is selected. It must also provide an entry for DIFFBREAK if RELTOPCONC is selected.
 - The beginning and ending dates and times should reflect the time variation considerations discussed in Section 3 above.
 - A set of output species names is required; their number must be the same as the entry in the first control parameter on Card 4.
- > REGION. This packet must follow the CONTROL packet. The vertical parameters will be ignored for the TOPCONC file.
 - > UNITS. This packet, if present, must follow the REGION packet. The UNITS packet must be provided if:
 - Any input variable will be input in other than internal units.
 - Any user-defined variables are specified.
 - COORD or HEIGHT unit conversions are to be used.
 The number of user-defined variables must not exceed the maximum specified in the CONTROL packet.
 - > STATIONS. This packet is required if the method STATINTERP or POISSON is specified. The number of stations listed must not exceed the maximum specified in the CONTROL packet.
 - > TIME INTERVAL. One or more TIME INTERVAL packets must be present. The first time interval must begin at or before the beginning of the time span specified on Card 10 of the CONTROL packet. All time intervals must be contiguous and of nonzero length. Each TIME INTERVAL packet contains one or more of the following packets and ends with an ENDTIME card. Following the first time interval, only those data that are to be changed need be specified.

- > SUBREGION. The first time interval must contain a SUBREGION packet; the inclusion of this packet in other time intervals is optional. The number of subregions must not exceed the maximum specified in the CONTROL packet.
- > METHOD. A method must be provided for every variable--including user-defined variables--in every subregion in the first time interval. Methods can be changed in subsequent TIME INTERVAL packets if desired. Note that each parameter entry contributes to the overall parameter count; the total number of parameters must not exceed the maximum specified in the CONTROL packet.
- > CONSTANTS. If the method CONSTANT is assigned to any variable in the METHOD packet, the first time interval must contain a CONSTANTS packet. More than one CONSTANTS packet can appear in any time interval.
- > GRID VALUES. If the method GRID VALUE is assigned to any variable in the METHOD packet, the first time interval must contain a GRID VALUES packet. More than one GRID VALUES packet can appear in any time interval.
- > STATION READINGS. If either the POISSON or STATINTERP method is assigned to any species in the METHOD packet, the first time interval must contain a STATION READINGS packet. More than one STATION READINGS packet can appear in any time interval.
- > VERTICAL PROFILES. If the method ABSTOPCONC or RELTOPCONC is assigned to any species in the METHOD packet, the first time interval must contain a VERTICAL PROFILES packet. There must be a vertical profile defined (or implied by means of ALL) for every variable in every subregion for which the profile method was specified. The number of height-value pairs in any single profile must not exceed the maximum specified in the CONTROL packet. More than one VERTICAL PROFILES packet can appear in any time interval.

5. Additional Input Files

If the method ABSTOPCONC or RELTOPCONC was selected, the REGIONTOP file must be input to TPCONC. In addition, if the method RELTOPCONC was selected, the DIFFBREAK file must also be input.

6. Examples

Exhibit VII-17 shows a sample input deck for TOPCONC file generation. The output from a TPCONC run using that input deck is shown in Exhibit VII-18.

CONTROL		POLLUTANT CONCENTRATIONS ABOVE THE MODELING REGION									
TOPCONC		11	0	0	1	0					
		31	1	1							
		1	1	1	1	1	0				
NO											
NO2											
O3											
ETH											
OLE											
PAR											
CARB											
ARO											
BZA											
PAN											
CO											
END											
REGION		76195	000	76195	2400						
		725000.	4252000.	15							
		-19000.	-16000.								
		4000.	4000.								
		17	22	4							
		2	2	0.	50.	200.					
END											
TIME INTERVAL											
		76195	000	76195	2400						
SUBREGION											
A			1	1	-1						
END											
METHOD											
A	NO	CONSTANT	.0001		.01						
A	NO2	CONSTANT	.0001		.01						
A	O3	CONSTANT	.001		.2						
A	ETH	CONSTANT	.0001		.01						
A	OLE	CONSTANT	.0001		.01						
A	PAR	CONSTANT	.001		1.						
A	CARB	CONSTANT	.001		0.1						
A	ARO	CONSTANT	.0001		0.1						
A	BZA	CONSTANT	.000000		.0001						
A	PAN	CONSTANT	.000001		.0001						
A	CO	CONSTANT	.01		1.						
END											

CONSTANTS	NO	.001
A	NO2	.002
A	O3	.078
A	ETH	.00109
A	OIE	.00220
A	PAR	.03333
A	CARB	.00405
A	ARO	.00124
A	BZA	
A	PAN	.00001
A	CO	0.1
END		
ENDTIME		

Exhibit VII-17 (Concluded)

PROCESSING OF INPUT DATA FOR THE PREPARATION OF FILE TOPCONC

POLLUTANT CONCENTRATIONS ABOVE THE MODELING REGION

NUMBER OF USER-DEFINED VARIABLES = 0
 NUMBER OF STATIONS = 0
 NUMBER OF SUBREGIONS = 1
 NUMBER OF METHOD PARAMETERS = 0
 NUMBER OF VERTICAL PROFILE HEIGHTS = 0
 PROGRAM OUTPUT WILL BE PLACED ON FILE NUMBER 31
 INPUT CARDS WILL BE PRINTED
 OUTPUT GRID WILL BE PRINTED
 UNIT TABLE WILL BE PRINTED
 STATION LOCATIONS WILL BE PRINTED
 SUBREGION GRID WILL BE PRINTED
 METHOD TABLE WILL BE PRINTED
 STATION VALUES WILL NOT BE PRINTED
 VERTICAL PROFILE VALUES WILL NOT BE PRINTED
 BEGINNING DATE OF FILE 76195 BEGINNING TIME OF FILE .00
 ENDING DATE OF FILE 76195 ENDING TIME OF FILE 24.00
 A TOTAL OF 11 SPECIES NAMES WERE READ, THE SPECIES NAMES ARE --

NO			
NO2			
O3			
ETH			
OLE			
PAR			
CARB			
ARO			
BZA			
PAN			
CO			
REGION	725000.	4252000.	15
	-19000.	-16000.	
	4000.76	4000.00	
	17	22	4
	2	2	.00
			50.00
			200.00
END			

FILE NAME -- TOPCONC POLLUTANT CONCENTRATIONS ABOVE THE MODELING REGION

PAGE 1

TOP CONCENTRATIONS (IN PARTS PER MILLION) SPECIES NO VERT. LEVEL 1 START DATE/TIME 76195 0.00 STOP DATE/TIME 76195 24.00

GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12
22	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
21	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
20	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
19	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
18	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
17	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
16	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
15	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
14	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
13	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
12	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
11	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
10	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
9	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
8	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
7	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
6	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
5	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
4	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
3	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
2	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010
1	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010	.0010

TOP CONCENTRATIONS (IN PARTS PER MILLION) SPECIES NO VERT. LEVEL 1 START DATE/TIME 76195 0.00 STOP DATE/TIME 76195 24.00

GRID CELL	13	14	15	16	17
22	.0010	.0010	.0010	.0010	.0010
21	.0010	.0010	.0010	.0010	.0010
20	.0010	.0010	.0010	.0010	.0010
19	.0010	.0010	.0010	.0010	.0010
18	.0010	.0010	.0010	.0010	.0010
17	.0010	.0010	.0010	.0010	.0010
16	.0010	.0010	.0010	.0010	.0010
15	.0010	.0010	.0010	.0010	.0010
14	.0010	.0010	.0010	.0010	.0010
13	.0010	.0010	.0010	.0010	.0010
12	.0010	.0010	.0010	.0010	.0010
11	.0010	.0010	.0010	.0010	.0010
10	.0010	.0010	.0010	.0010	.0010
9	.0010	.0010	.0010	.0010	.0010
8	.0010	.0010	.0010	.0010	.0010
7	.0010	.0010	.0010	.0010	.0010
6	.0010	.0010	.0010	.0010	.0010
5	.0010	.0010	.0010	.0010	.0010
4	.0010	.0010	.0010	.0010	.0010
3	.0010	.0010	.0010	.0010	.0010
2	.0010	.0010	.0010	.0010	.0010
1	.0010	.0010	.0010	.0010	.0010

L. WIND

The WIND file contains time-varying matrices of horizontal wind vector values in three dimensions and scalars representing overall maxima and average values at the boundaries. The program WNDSET is used to create the WIND file. WNDSET requires subroutines from the libraries UTILITY and FILUTIL. Figure VII-23 is an information flow diagram illustrating the job control to be used. In the following sections we discuss the input to the WNDSET program.

1. Variables

The WNDSET program has four implicit variables: SPEED, DIRECTION, WINDX, and WINDY. The first two represent a wind vector in polar form, and the latter two represent the vector in terms of its x- and y-components. A three-dimensional matrix is maintained for each variable. In general, the input to the program will be SPEED and DIRECTION, whereas the variables written to the WIND file are WINDX and WINDY. The WNDSET program calculates values for the undefined variables from those for variables to which values have been assigned.

2. Methods

The methods that can be used to generate the WIND file are:

- > CONSTANT
- > GRID VALUE
- > STATINTERP
- > POISSON
- > DIVERGENCE
- > VECTORIZE
- > POLARIZE




Figure VII-23. Information Flow Diagram for the WIND File

- > E-WINTERP
- > N-SINTERP
- > USER.

These methods are discussed in detail in Section VI.A.6.

Since the WIND file varies in the vertical direction, a vertical method must also be specified for each output variable in each subregion. The vertical methods that can be used are:

- > CONSTANT
- > ABSPROFILE
- > RELPROFILE
- > DIVERGENCE
- > VECTORIZE
- > POLARIZE
- > E-WINTERP
- > N-SINTERP
- > VERTUSER.

These vertical methods are discussed in detail in Section VI.A.6.

3. Time Variation

The time span of the WIND file must include the entire time span of the simulation runs for which it is to be used. Wind vectors and scalar values are considered to be constant during each time interval.

4. Packets

Figure VII-24 shows the input deck structure in terms of the packets to be used. Each of these packets is described in detail in Section VI.B. Following are special input packet considerations for the WIND file:




Figure VII-24. Input Card Deck Structure for Preparing the WIND File

- > CONTROL
 - The file name on Card 2 must be WIND.
 - The control variables to be specified on Cards 4 to 8 for WIND are shown in Table VII-10.
 - The number of species should be zero.
 - If there are input variables other than the four implicit variables, their number must appear as the number of user-defined variables. All such variables must also be named in the UNITS packet.
 - If data from measuring stations are to be used (methods STATINTERP, POISSON, or DIVERGENCE), the maximum number of such stations must be given.
 - The number of subregions must be at least one.
 - The maximum number of parameters must be sufficient to include all specifications of all parameters.
 - The vertical controls card (No. 7) must include maximum vertical parameter and profile entries as applicable.
 - The file unit assignment card (No. 8) must provide entries for DIFFBREAK and REGIONTOP if any vertical method besides CONSTANT is selected. In addition, entries for TEMPERATUR must appear if DIVERGENCE is used.
 - The beginning and ending dates and times should reflect the time variation considerations discussed in Section 3 above.
 - A set of output species names is not required; if they are present, their number must be the same as the entry in the first control parameter on Card 4, but they will be ignored by the program.
- > REGION. This packet must follow the CONTROL packet. The vertical parameters must be provided for the WIND file.
- > UNITS. This packet, if present, must follow the REGION packet. The UNITS packet must be provided if:
 - Any input variable will be input in other than internal units.

Table VII-10. CONTROL Packet Entries for the WIND File

<u>Card Number</u>	<u>Entry</u>
4	Number of species (=0)
	Number of user-defined variables
	Number of stations
	Number of subregions
	Number of parameters
	Spare
5	Output file number
	Print input cards
	Print grids for x- and y-components
	Print grids for speed and direction
	Spare
	Spare
6	Print units table
	Print station locations table
	Print regional grid
	Print methods table
	Print station values table
	Spare
7	Number of vertical parameters
	Number of heights in profile
	Print vertical methods table
	Print vertical profile tables
	Spare
	Spare
8	DIFFBREAK file number
	REGIONTOP file number
	Spare
	TEMPERATUR file number
	Spare
	Spare

- Any user-defined variables are specified.
- COORD or HEIGHT unit conversions are to be used.

The number of user-defined variables must not exceed the maximum specified in the CONTROL packet.

- > STATIONS. This packet is required if any of the methods STATINTERP, POISSON, or DIVERGENCE is specified. The number of stations listed must not exceed the maximum specified in the CONTROL packet.
- > TIME INTERVAL. One or more TIME INTERVAL packets must be present. The first time interval must begin at or before the beginning of the time span specified on Card 10 of the CONTROL packet. All time intervals must be contiguous and of nonzero length. Each TIME INTERVAL packet contains one or more of the following packets and ends with an ENDTIME card. Following the first time interval, only those data that are to be changed need be specified.
- > SUBREGION. The first time interval must contain a SUBREGION packet; the inclusion of this packet in other time intervals is optional. The number of subregions must not exceed the maximum specified in the CONTROL packet.
- > METHOD. A method must be provided for every variable--including user-defined variables--in every subregion in the first time interval. Methods can be changed in subsequent TIME INTERVAL packets if desired. Note that each parameter entry contributes to the overall parameter count; the total number of parameters must not exceed the maximum specified in the CONTROL packet.
- > VERTICAL METHOD. A vertical method must be provided for every variable--including user-defined variables--in every subregion in the first time interval. Vertical methods can be changed in subsequent TIME INTERVAL packets if desired. Note that each vertical parameter entry contributes to the overall vertical parameter count; the total must not exceed the maximum specified in the CONTROL packet.

- > CONSTANTS. If the method CONSTANT is assigned to any variable in the METHOD packet, the first time interval must contain a CONSTANTS packet. More than one CONSTANTS packet can appear in any time interval.
- > GRID VALUES. If the method GRID VALUE is assigned to any variable in the METHOD packet, the first time interval must contain a GRID VALUES packet. More than one GRID VALUES packet can appear in any time interval.
- > STATION READINGS. If either the POISSON, DIVERGENCE, or STATINTERP method is assigned to any variable in the METHOD packet, the first time interval must contain a STATION READINGS packet. More than one STATION READINGS packet can appear in any time interval.
- > VERTICAL PROFILES. If any of the profile methods are assigned to any variable in the VERTICAL METHOD packet, the first time interval must contain a VERTICAL PROFILES packet. There must be a vertical profile defined (or implied by means of ALL) for every variable in every subregion for which a profile method was specified. The number of height-value pairs in any single profile must not exceed the maximum specified in the CONTROL packet. More than one VERTICAL PROFILES packet can appear in any time interval.

Typically, the wind values input will be in terms of SPEED and DIRECTION at measuring stations, whereas the variables output to the file are WINDX and WINDY. In this case, the methods and vertical methods should be specified as follows:

- > For SPEED and DIRECTION, use the method and vertical method POLARIZE if speed and direction grids are to be printed, or CONSTANT if they are not to be printed. If CONSTANT is chosen, supply a dummy CONSTANTS packet to give an arbitrary initial value to the SPEED and DIRECTION grids.
- > For WINDX and WINDY, specify one of the methods using station readings--STATINTERP, POISSON, or DIVERGENCE--and the vertical method desired for computation.

In each time interval, missing values of WINDX and WINDY for station readings and vertical profiles will be calculated from SPEED and DIRECTION, and vice versa. To ensure that old values are replaced with the appropriate new values, the variables WINDX and WINDY must be cleared to -9. before reading in the data for a new time interval. For station readings, the following can be done:

STATION READINGS				STATION READINGS		
ALL	WINDX	-9.	or	ALL	ALL	-9.
ALL	WINDY	-9.				
END						

A shorthand method for clearing an entire vertical profile to -9. has also been provided--simply specify -9 as the number of profile heights, as shown in the following example:

```

VERTICAL PROFILES
A _____ ALL _____ 4200. _____ 5000. _____ -9
END

```

5. Additional Input Files

If any vertical method besides CONSTANT was selected, the DIFFBREAK and REGIONTOP files must be input to WNDSET. In addition, if DIVERGENCE was selected the TEMPERATUR file must also be input.

6. Examples

Exhibit VII-19 shows a sample input deck for WIND file generation. The output from a WNDSET run using that input deck is shown in Exhibit VII-20.

CONTROL	WIND	WIND FIELD FOR ST. LOUIS	DIVERGENCE	ALGORITHM USED
	0	0	25	1
	32	0	1	0
	1	0	0	0
	10	20	0	0
	11	12	14	1
	76195	500	76195	2400
END				
	REGION			
	725000.	4252000.	15	
	-19000.	-16000.		
	4000.	4000.		
	17	22	4	
	2	2	0.0	50.
END				200.

UNITS					
WINDX	M/SEC	3600.			1.
WINDY	M/SEC	3600.			1.
SPEED	M/SEC	3600.			1.
END					
STATIONS					
101	19183.	27862.		30.	
102	17518.	34045.		30.	
103	22588.	30467.		30.	
104	22312.	25304.		30.	
105	18706.	24453.		30.	
106	13660.	25566.		30.	
107	15179.	30610.		30.	
108	23407.	39102.		10.	
109	30802.	27886.		30.	
110	22209.	20826.		10.	
111	13812.	20479.		30.	
112	8938.	28913.		30.	
113	12738.	37820.		30.	
114	19320.	45456.		10.	
115	32111.	45799.		10.	
116	37777.	38083.		10.	
117	35560.	20818.		10.	
118	18065.	11256.		10.	
119	4759.	18547.		30.	
120	-1921.	33909.		30.	
121	7414.	50376.		10.	
122	16631.	77223.		30.	
123	52320.	34378.		30.	
124	24275.	-15463.		30.	
125	-27555.	30240.		30.	
END					
TIME INTERVAL	500	76195		600	
SUBREGION					
A	1	1		-1	
END					
METHOD					
A	WINDX	DIVERGENCE		-20.	3
	RMAXIT	1000.			
	TLRICE	10000.			
	ROMEGA	1.4			
A	WINDY	DIVERGENCE		-20.	3
	RMAXIT	1000.			
	TLRICE	10000.			
	ROMEGA	1.4			
A	SPEED	CONSTANT		0.	20.
A	DIRECTION	CONSTANT		-7.	7.
END					

VERTICAL METHOD			
A WINDY	DIVERGENCE	-20.	-
A WINDY	DIVERGENCE	-20.	20.
A SPEED	CONSTANT	0.	20.
A DIRECTION	CONSTANT	-7.	7.
END			
CONSTANTS			
A SPEED	3.0		
A DIRECTION	3.14		
END			
STATION READINGS			
ALL	ALL	-9.0	
101	SPEED	3.51	
101	DIRECTION	1.83	
102	SPEED	3.26	
102	DIRECTION	2.21	
103	SPEED	2.18	
103	DIRECTION	1.88	
104	SPEED	3.17	
104	DIRECTION	1.96	
105	SPEED	3.24	
105	DIRECTION	1.72	
106	SPEED	3.75	
106	DIRECTION	1.77	
107	SPEED	2.96	
107	DIRECTION	1.93	
108	SPEED	2.06	
108	DIRECTION	1.98	
109	SPEED	2.94	
109	DIRECTION	1.75	
110	SPEED	1.66	
110	DIRECTION	1.62	
111	SPEED	2.38	
111	DIRECTION	1.81	
112	SPEED	2.83	
112	DIRECTION	1.82	
113	SPEED	3.83	
113	DIRECTION	2.10	
114	SPEED	1.77	
114	DIRECTION	1.92	
115	SPEED	2.16	
115	DIRECTION	1.86	
116	SPEED	2.70	
116	DIRECTION	1.80	
117	SPEED	2.67	
117	DIRECTION	1.97	

WINDS FOR 500

Exhibit VII-19 (Continued)

118	SPEED	-9.00			
118	DIRECTION	-9.00			
119	SPEED	3.24			
119	DIRECTION	1.84			
120	SPEED	3.21			
120	DIRECTION	1.98			
121	SPEED	2.68			
121	DIRECTION	1.84			
122	SPEED	2.51			
122	DIRECTION	2.37			
123	SPEED	2.26			
123	DIRECTION	2.04			
124	SPEED	-9.00			
125	SPEED	3.12			
125	DIRECTION	1.76			
END					
VERTICAL PROFILE					
A	ALL		2	STA	
	-9.0	-9.0			
	-9.0	-9.0			
A	SPEED	42948.0	79053.0		
	.0				
	34.5				
	116.1				
	197.0				
	276.7				
	355.4				
	433.2				
	510.0				
	586.0				
	660.9				
	734.2				
	807.2				
	880.2				
	953.2				
	1026.2				
	1099.2				
	1172.2				
	1245.6				
	1319.0				
	1392.0				
A	DIRECTION	42948.0	79053.0	20	STA 141
	.0				
	34.5				
	116.1				
	197.0				
	276.7				
	355.4				
	433.2				
	510.0				
	586.0				
	660.9				

734.2 5.6
807.2 5.6
880.2 5.6
953.2 5.7
1026.2 5.7
1099.2 5.7
1172.2 5.7
1245.6 5.7
1319.0 5.6
1392.0 5.6

END

ENDTIME

TIME INTERVAL

STATION READINGS

700

76195

WINDS FOR 600

STATION READINGS	76195	700
ALL	-9.0	
101	SPEED	3.29
101	DIRECTION	2.07
102	SPEED	3.17
102	DIRECTION	2.15
103	SPEED	2.56
103	DIRECTION	2.16
104	SPEED	2.54
104	DIRECTION	2.28
105	SPEED	2.69
105	DIRECTION	2.34
106	SPEED	2.90
106	DIRECTION	2.16
107	SPEED	2.96
107	DIRECTION	2.13
108	SPEED	2.64
108	DIRECTION	2.15
109	SPEED	2.87
109	DIRECTION	2.04
110	SPEED	2.05
110	DIRECTION	2.25
111	SPEED	2.45
111	DIRECTION	2.20
112	SPEED	3.16
112	DIRECTION	2.01
113	SPEED	3.92
113	DIRECTION	2.13
114	SPEED	1.95
114	DIRECTION	2.05
115	SPEED	2.50
115	DIRECTION	1.92
116	SPEED	2.97
116	DIRECTION	1.89
117	SPEED	3.31
117	DIRECTION	2.16
118	SPEED	2.99
118	DIRECTION	2.10
119	SPEED	2.70
119	DIRECTION	2.18
120	SPEED	3.20
120	DIRECTION	2.31
121	SPEED	3.08

PROCESSING OF INPUT DATA FOR THE PREPARATION OF FILE WIND

WIND FIELD FOR ST. LOUIS DIVERGENCE ALGORITHM USED

REGION	725000.	4252000.	15	
	-19000.	-16000.		
	4000.00	4000.00		
	17	22	4	
	2	2	.00	50.00 200.00
END				
KCRNT = 61	NSCLFT = 11840	IN	SCRSET	
KCRNT = 121	NSCLFT = 11780	IN	SCRSET	
KCRNT = 127	NSCLFT = 11774	IN	SCRSET	
KCRNT = 133	NSCLFT = 11768	IN	SCRSET	
KCRNT = 139	NSCLFT = 11762	IN	SCRSET	
KCRNT = 389	NSCLFT = 11512	IN	SCRSET	
KCRNT = 489	NSCLFT = 11412	IN	SCRSET	
KCRNT = 514	NSCLFT = 11387	IN	SCRSET	
KCRNT = 539	NSCLFT = 11362	IN	SCRSET	
KCRNT = 564	NSCLFT = 11337	IN	SCRSET	
KCRNT = 574	NSCLFT = 11327	IN	SCRSET	
KCRNT = 948	NSCLFT = 10953	IN	SCRSET	
KCRNT = 952	NSCLFT = 10949	IN	SCRSET	
KCRNT = 956	NSCLFT = 10945	IN	SCRSET	
KCRNT = 960	NSCLFT = 10941	IN	SCRSET	
KCRNT = 964	NSCLFT = 10937	IN	SCRSET	
KCRNT = 968	NSCLFT = 10933	IN	SCRSET	
KCRNT = 1068	NSCLFT = 10833	IN	SCRSET	
KCRNT = 1078	NSCLFT = 10823	IN	SCRSET	
KCRNT = 1082	NSCLFT = 10819	IN	SCRSET	
KCRNT = 1086	NSCLFT = 10815	IN	SCRSET	
KCRNT = 1090	NSCLFT = 10811	IN	SCRSET	
KCRNT = 1094	NSCLFT = 10807	IN	SCRSET	
KCRNT = 1098	NSCLFT = 10803	IN	SCRSET	
KCRNT = 1198	NSCLFT = 10703	IN	SCRSET	
KCRNT = 1208	NSCLFT = 10693	IN	SCRSET	
KCRNT = 1212	NSCLFT = 10689	IN	SCRSET	
KCRNT = 1216	NSCLFT = 10685	IN	SCRSET	
KCRNT = 1296	NSCLFT = 10605	IN	SCRSET	
KCRNT = 1376	NSCLFT = 10525	IN	SCRSET	
KCRNT = 1750	NSCLFT = 10151	IN	SCRSET	
KCRNT = 2124	NSCLFT = 9777	IN	SCRSET	
KCRNT = 2498	NSCLFT = 9403	IN	SCRSET	
KCRNT = 2872	NSCLFT = 9029	IN	SCRSET	
KCRNT = 3246	NSCLFT = 8655	IN	SCRSET	
KCRNT = 9230	NSCLFT = 2671	IN	SCRSET	
KCRNT = 9604	NSCLFT = 2297	IN	SCRSET	
UNITS				
STATIONS				

STATION IDENTIFICATION TABLE

STATION NAME	X-LOCATION(GRID SQ)	Y-LOCATION (GRID SQ)	STATION HEIGHT(METERS)
101	9.55	10.97	30.00
102	9.13	12.51	30.00
103	10.40	11.62	30.00
104	10.33	10.33	30.00
105	9.43	10.11	30.00
106	8.16	10.39	30.00
107	8.54	11.65	30.00
108	10.60	13.78	10.00
109	12.45	10.97	30.00
110	10.30	9.21	10.00
111	8.20	9.12	30.00
112	6.98	11.23	30.00
113	7.93	13.45	30.00
114	9.58	15.36	10.00
115	12.78	15.45	10.00
116	14.19	13.52	10.00
117	13.64	9.20	10.00
118	9.27	6.81	10.00
119	5.94	8.64	30.00
120	4.27	12.48	30.00
121	6.60	16.59	10.00
122	8.91	23.31	30.00
123	17.83	12.59	30.00
124	10.82	.13	30.00
125	-2.14	11.56	30.00
TIME INTERVAL	500	600	

SUBREGION
METHOD
VERTICAL METHOD

METHODS TABLE

SUBREGION	VARIABLE	METHOD	MIN. VALUE	MAX. VALUE	PARAMETER	PAR. VALUE
A	WINDX	DIVERGENCE	-72000.0000	72000.0000		
A	WINDY	DIVERGENCE	-72000.0000	72000.0000		
A	SPEED	CONSTANT	.0000	72000.0000		
A	DIRECTION	CONSTANT	-7.0000	7.0000		
CONSTANTS						
STATION READINGS						
VERTICAL PROFILE						
ENDTIME						
KCRNT =	21	NSCLFT = 2277	IN SCRSET			
KCRNT =	41	NSCLFT = 2257	IN SCRSET			
KCRNT =	45	NSCLFT = 2253	IN SCRSET			
KCRNT =	49	NSCLFT = 2249	IN SCRSET			
KCRNT =	69	NSCLFT = 2229	IN SCRSET			
KCRNT =	89	NSCLFT = 2209	IN SCRSET			
KCRNT =	93	NSCLFT = 2205	IN SCRSET			
KCRNT =	467	NSCLFT = 1831	IN SCRSET			
KCRNT =	841	NSCLFT = 1457	IN SCRSET			

WINDS FOR 500

WIND SCALAR VALUES BETWEEN DATE 76195 / TIME 5.00 AND DATE 76195 / TIME 6.00

AVERAGE STATION REFERENCE HEIGHT	23.60 METERS
MAXIMUM SPEED IN X-DIRECTION	22453.18 METERS/HOUR
MAXIMUM SPEED IN Y-DIRECTION	9602.99 METERS/HOUR
AVERAGE SPEED AT WEST BORDER	14801.04 METERS/HOUR
AVERAGE SPEED AT EAST BORDER	14801.11 METERS/HOUR
AVERAGE SPEED AT SOUTH BORDER	14799.13 METERS/HOUR
AVERAGE SPEED AT NORTH BORDER	14798.96 METERS/HOUR

FILE NAME	--- WIND	WIND FIELD FOR ST. LOUIS										DIVERGENCE	ALGORITHM USED										PAGE
WIND VELOCITIES	(IN METERS PER HOUR)	COMPONENT WINDX										VERT.	LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00										
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12											
22	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24										
21	-9608.41	-9597.95	-9579.41	-9568.13	-9560.89	-9556.42	-9554.05	-9553.15	-9553.21	-9553.97	-9555.34	-9557.28											
20	-9629.52	-9617.58	-9590.74	-9570.93	-9556.77	-9547.54	-9542.64	-9540.86	-9541.03	-9542.76	-9545.91	-9550.42											
19	-9639.70	-9629.26	-9598.60	-9572.82	-9552.85	-9539.38	-9532.62	-9530.53	-9530.89	-9533.54	-9538.42	-9545.61											
18	-9643.83	-9635.78	-9603.36	-9573.39	-9548.70	-9531.51	-9524.08	-9522.62	-9522.87	-9526.22	-9532.48	-9540.82											
17	-9644.58	-9639.11	-9606.02	-9573.32	-9545.04	-9524.29	-9517.11	-9516.83	-9515.88	-9520.07	-9528.19	-9537.93											
16	-9643.51	-9640.49	-9607.57	-9573.79	-9544.33	-9522.76	-9512.11	-9508.57	-9507.45	-9513.54	-9524.24	-9535.49											
15	-9641.41	-9640.50	-9608.27	-9574.50	-9545.05	-9523.00	-9509.68	-9503.90	-9502.55	-9506.55	-9516.48	-9530.33											
14	-9638.67	-9639.30	-9608.03	-9574.90	-9546.36	-9524.56	-9509.46	-9502.23	-9499.21	-9499.19	-9507.85	-9524.57											
13	-9635.44	-9636.88	-9606.73	-9574.58	-9547.76	-9527.51	-9512.23	-9502.66	-9495.58	-9491.19	-9498.89	-9519.23											
12	-9631.80	-9633.17	-9604.48	-9573.99	-9548.09	-9528.70	-9514.25	-9503.75	-9491.93	-9483.51	-9492.50	-9516.89											
11	-9627.67	-9627.86	-9600.59	-9571.54	-9546.27	-9527.42	-9514.08	-9504.30	-9493.14	-9483.70	-9490.80	-9516.09											
10	-9623.07	-9620.88	-9595.05	-9567.46	-9542.58	-9524.25	-9511.06	-9499.94	-9490.60	-9486.79	-9496.40	-9521.06											
9	-9618.20	-9612.45	-9588.23	-9563.00	-9538.46	-9521.13	-9509.01	-9498.25	-9491.60	-9492.15	-9503.50	-9525.90											
8	-9613.28	-9603.53	-9579.32	-9559.94	-9536.94	-9519.30	-9506.79	-9497.73	-9493.74	-9497.33	-9509.89	-9531.00											
7	-9608.43	-9600.24	-9578.86	-9557.41	-9536.29	-9519.35	-9507.22	-9499.57	-9497.39	-9502.89	-9516.07	-9535.96											
6	-9603.65	-9596.32	-9575.93	-9555.66	-9536.86	-9521.61	-9510.75	-9504.55	-9503.75	-9509.49	-9521.85	-9540.34											
5	-9598.84	-9591.76	-9572.87	-9554.95	-9539.02	-9526.22	-9517.22	-9512.42	-9512.33	-9517.57	-9528.28	-9544.21											
4	-9593.75	-9586.84	-9570.19	-9555.47	-9543.00	-9533.22	-9526.46	-9523.02	-9523.23	-9527.42	-9535.76	-9548.15											
3	-9587.81	-9581.43	-9568.03	-9557.36	-9548.92	-9542.55	-9538.25	-9536.14	-9536.39	-9539.18	-9544.63	-9552.80											
2	-9579.70	-9574.95	-9566.50	-9560.83	-9556.77	-9553.88	-9552.01	-9551.13	-9551.29	-9552.56	-9555.02	-9558.76											
1	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24											

FILE NAME -- WIND

WIND FIELD FOR ST. LOUIS

DIVERGENCE

ALGORITHM USED

WIND VELOCITIES (IN METERS PER HOUR) COMPONENT WINDX VERT. LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00

GRID CELL	13	14	15	16	17
22	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24
21	-9559.75	-9562.87	-9567.58	-9574.91	-9578.55
20	-9556.05	-9561.82	-9570.62	-9582.49	-9586.79
19	-9556.27	-9562.33	-9574.61	-9589.70	-9593.28
18	-9551.24	-9563.53	-9579.54	-9597.14	-9598.94
17	-9549.96	-9565.47	-9584.86	-9604.72	-9604.12
16	-9549.26	-9567.40	-9590.16	-9612.26	-9609.00
15	-9547.77	-9569.70	-9595.53	-9619.70	-9613.69
14	-9545.83	-9571.59	-9600.60	-9626.83	-9618.20
13	-9544.25	-9573.41	-9605.34	-9633.48	-9622.57
12	-9544.28	-9575.70	-9609.89	-9639.59	-9626.94
11	-9545.81	-9578.68	-9614.32	-9645.04	-9631.46
10	-9550.51	-9583.39	-9618.79	-9649.68	-9636.27
9	-9554.72	-9587.83	-9622.96	-9653.00	-9641.28
8	-9558.72	-9590.80	-9624.42	-9653.57	-9645.85
7	-9561.93	-9590.70	-9621.48	-9650.46	-9649.26
6	-9563.83	-9582.33	-9613.42	-9644.51	-9650.73
5	-9564.38	-9585.54	-9610.81	-9640.02	-9649.32
4	-9564.13	-9582.82	-9605.28	-9632.82	-9643.69
3	-9563.68	-9577.48	-9595.45	-9619.94	-9631.59
2	-9563.98	-9571.18	-9581.71	-9598.90	-9608.83
1	-9566.24	-9566.24	-9566.24	-9566.24	-9566.24

Exhibit VII-20 (Continued)

FILE NAME -- WIND	WIND FIELD FOR ST. LOUIS				DIVERGENCE	ALGORITHM USED							PAGE 1
WIND VELOCITIES (IN METERS PER HOUR)	COMPONENT WINDY				VERT. LEVEL 1	START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 6.00							
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12	
22	3119.40	3161.58	3180.31	3185.97	3183.71	3176.66	3167.01	3156.30	3145.39	3134.84	3125.04	3116.40	
21	3119.40	3152.35	3170.68	3178.39	3178.33	3172.83	3163.96	3153.45	3142.37	3131.53	3121.70	3113.60	
20	3119.40	3136.33	3149.15	3155.83	3156.53	3152.41	3145.25	3137.09	3128.60	3120.44	3113.50	3106.58	
19	3119.40	3127.43	3134.67	3138.66	3138.49	3134.46	3128.06	3122.24	3116.30	3110.66	3106.48	3104.55	
18	3119.40	3122.24	3125.32	3126.90	3125.90	3121.98	3115.80	3112.40	3108.25	3103.97	3101.59	3100.84	
17	3119.40	3119.21	3119.65	3119.87	3119.29	3117.67	3114.93	3111.19	3106.77	3102.02	3100.30	3099.76	
16	3119.40	3117.45	3116.27	3115.86	3116.23	3117.51	3118.89	3115.10	3111.41	3107.45	3103.42	3100.82	
15	3119.40	3116.33	3114.04	3113.03	3113.59	3115.98	3118.37	3117.57	3116.92	3114.48	3107.52	3102.53	
14	3119.40	3115.54	3112.34	3110.55	3110.55	3113.38	3116.92	3119.12	3119.69	3116.66	3108.76	3103.24	
13	3119.40	3114.90	3110.92	3108.45	3107.91	3109.45	3112.72	3116.09	3117.01	3112.68	3105.14	3101.36	
12	3119.40	3114.30	3109.46	3105.90	3103.96	3102.56	3102.94	3104.28	3105.10	3103.27	3099.26	3097.51	
11	3119.40	3113.73	3107.95	3102.78	3098.29	3094.01	3091.04	3088.53	3085.43	3086.46	3088.70	3091.05	
10	3119.40	3113.45	3107.16	3100.83	3094.62	3088.26	3083.76	3078.84	3073.46	3074.10	3080.12	3085.96	
9	3119.40	3113.63	3107.79	3101.13	3095.10	3089.57	3084.33	3079.58	3076.41	3077.14	3082.73	3087.52	
8	3119.40	3114.19	3110.99	3102.97	3097.85	3094.21	3089.48	3085.84	3084.18	3085.28	3089.66	3094.02	
7	3119.40	3114.09	3109.30	3104.12	3100.40	3098.02	3095.84	3094.74	3095.31	3097.67	3101.28	3104.85	
6	3119.40	3114.01	3109.23	3105.34	3103.09	3102.51	3103.10	3104.97	3108.15	3112.24	3115.83	3118.64	
5	3119.40	3113.86	3109.33	3106.50	3105.88	3107.48	3110.89	3115.74	3121.48	3127.25	3131.76	3134.23	
4	3119.40	3113.33	3108.99	3107.24	3108.45	3112.47	3118.76	3126.59	3135.01	3142.83	3148.68	3151.41	
3	3119.40	3111.87	3107.55	3107.09	3110.40	3117.00	3126.15	3136.87	3147.98	3158.09	3165.74	3169.60	
2	3119.40	3108.20	3104.13	3105.58	3111.39	3120.62	3132.32	3145.44	3158.81	3171.12	3180.99	3187.15	
1	3119.40	3105.94	3102.63	3105.45	3112.28	3121.77	3132.94	3144.98	3157.18	3168.81	3179.08	3187.07	

Exhibit VII-20 (Continued)

ALGORITHM USED

FILE NAME --- WIND

WIND FIELD FOR ST. LOUIS

DIVERGENCE

VERT.

LEVEL 1

START DATE/TIME

76195

5.00

STOP DATE/TIME

76195

6.00

WIND VELOCITIES

(IN METERS PER HOUR)

COMPONENT WINDY

GRID CELL

13

14

15

16

17

18

19

20

21

22

23

24

25

26

27

28

29

30

31

32

33

34

35

36

37

38

39

40

41

42

43

44

45

46

47

48

49

50

51

52

53

54

55

56

57

58

59

60

61

62

63

64

65

66

67

68

69

70

71

72

73

74

75

76

77

78

79

80

81

82

83

84

85

86

87

88

89

90

91

92

93

94

95

96

97

98

99

100

101

102

103

104

105

106

107

108

109

110

111

112

113

114

115

116

117

118

119

120

121

122

123

124

125

126

127

128

129

130

131

132

133

134

135

136

137

138

139

140

141

142

143

144

145

146

147

148

149

150

151

152

153

154

155

156

157

158

159

160

161

162

163

164

165

166

167

168

169

170

171

172

173

174

175

176

177

178

179

180

181

182

183

184

185

186

187

188

189

190

191

192

193

194

195

196

197

198

199

200

201

202

203

204

205

206

207

208

209

210

211

212

213

214

215

216

217

218

219

220

221

222

223

224

225

226

227

228

229

230

231

232

233

234

235

236

237

238

239

240

241

242

243

244

245

246

247

248

249

250

251

252

253

254

255

256

257

258

259

260

261

262

263

264

265

266

267

268

269

270

271

272

273

274

275

276

277

278

279

280

281

282

283

284

285

286

287

288

289

290

291

292

293

294

295

296

297

298

299

300

301

302

303

304

305

306

307

308

309

310

311

312

313

314

315

316

317

318

319

320

321

322

323

324

325

326

327

328

329

330

331

332

333

334

335

336

337

338

339

340

341

342

343

344

345

346

347

348

349

350

351

VIII SEGMENTATION OF M.E.B. FILES

If the entire modeling region is too large to fit within the core limitations of the Airshed Simulation Program, the region must be subdivided into rectangular subregions called "segments" that will fit into core. The segmentation process involves (1) determining the size and layout of the segments and (2) running the file segmentation program to create segmented versions of each spatially varying data file. This chapter first describes how to determine the core requirements for a given segmentation scheme and then how to use the file segmentation program.

A. CALCULATING CORE REQUIREMENTS

The maximum horizontal dimensions allowable for a single segment depend on the number of segments, the number of vertical levels and chemical species, and the number of point sources within the modeling region; the program options selected; and the amount of core available on the host computer. When the Airshed Simulation Program is installed on a particular computer, it will contain a vector of available space. The length of this vector is specified when the program is compiled and should be as large as possible. The vector of available space is used to hold the following four tables:

- > Segment
- > Local
- > Boundary
- > Segment scratch.

The detailed contents of these tables appear in Chapter VII of the Systems Manual. Only the methods of calculating the length of each table are described here.

To determine whether a segment of a given size will fit in core, the calculated sizes of the tables must be summed and that total compared with the amount of available core. The calculations for each table are discussed next, followed by Exhibit VIII-1, which is a worksheet to be used for the calculations. Finally, a sample problem is presented showing the calculation of core requirements for different segmentation schemes for the same region.

1. Segment Table

The Segment Table contains 65 entries for each segment.

$$S.T. = 65 * seg \quad ,$$

where seg = number of segments.

2. Local Table

The Local Table contains vectors used by the numerical integration routines.

$$\begin{aligned} L.T. = & 5 + 32z + zs + 5s \\ & + 4r + 2r^2 \\ & + 6x_{\max} \quad , \end{aligned}$$

where

z = number of vertical levels,
s = number of chemical species,
r = number of reactive species,
 $x_{\max}$ = maximum dimension in x or y direction for
any segment.

Fixed Dimensions

z = _____
s = _____
r = _____

Simulation Options (1 = yes, 0 = no)

TEMPERATUR = _____
TERRAIN = _____
ROADWAY = _____
VARIATION = _____

	Segment			
	1	2	3	4
x				
y				
p				
interface				

$$65 \times \frac{\text{seg}}{\text{seg}} = \text{_____ (S.T.)}$$

$$\left[\begin{array}{l} 5 + \frac{\text{ }{32z}}{\text{ }} + \frac{\text{ }{zs}}{\text{ }} + \frac{\text{ }{5s}}{\text{ }} \\ + \frac{\text{ }{4r}}{\text{ }} + \frac{\text{ }{2r^2}}{\text{ }} \\ + \frac{\text{ }{6(x,y)_{\text{max}}}}{\text{ }} \end{array} \right] = \text{_____ (L.T.)}$$

$$\left[\frac{\text{ }{8(x+y)}}{\text{ }} + \frac{\text{ }{zs (\text{interface})}}{\text{ }} \right] = \text{_____ (B.T.)}$$

$$\left[\begin{array}{l} 8 + \frac{\text{ }{2terr}}{\text{ }} + \frac{\text{ }{temp}}{\text{ }} + \frac{\text{ }{road}}{\text{ }} \\ + \frac{\text{ }{2z}}{\text{ }} \\ + \frac{\text{ }{s}}{\text{ }} \left(2 + \frac{\text{ }{road}}{\text{ }} + \frac{\text{ }{var}}{\text{ }} \right) \\ + \frac{\text{ }{zs}}{\text{ }} \end{array} \right] \rightarrow \left[\text{ } \right] \times \frac{\text{ }{xy}}{\text{ }} + \frac{\text{ }{2+s}}{\text{ }} \times \frac{\text{ }{p}}{\text{ }} = \text{_____ (S.S.T.)}$$

Sum of all tables = _____
Available storage = _____

3. Boundary Table

The Boundary Table contains the boundary cell definitions and the concentrations in the interface cells for a single segment. The "interface cells" of a segment are those that lie within the two-cell overlap into the adjacent segment. The number of interface cells in a segment is two times the sum of the lengths of each nonexternal edge. For non-symmetrical segmentation schemes (such as that shown in Figure VIII-3), the Boundary Table length for each segment must be calculated to determine the maximum storage requirement.

$$B.T. = 8(x + y) + zs \text{ (interface)} ,$$

where

$$\begin{aligned} z &= \text{number of vertical levels,} \\ s &= \text{number of chemical species,} \\ (x+y) &= \text{sum of } x \text{ and } y \text{ dimensions for the segment,} \\ (\text{interface}) &= \text{number of interface cells in the segment,} \\ &\quad \text{i.e., 2 times the length of all nonexternal} \\ &\quad \text{edges.} \end{aligned}$$

4. Segment Scratch Table

The Segment Scratch Table contains all the other spatially varying data arrays, including predicted concentrations and variations, and the point source data, for one segment.

$$\begin{aligned} S.S.T. = xy \bigg\{ & 8 + 2(\text{terr}) + 1(\text{temp}) + 1(\text{road}) \\ & + 2z + s[2 + 1(\text{road}) + 1(\text{var})] + zs \bigg\} \\ & + p(2 + s) , \end{aligned}$$

where

x = number of cells in x direction;
y = number of cells in y direction;
p = number of point sources;
z = number of vertical levels;
s = number of chemical species;
terr = 1, if TERRAIN file input,
0, otherwise;
temp = 1, if TEMPERATUR file input,
0, otherwise;
road = 1, if ROADWAY file input,
0, otherwise;
var = 1, if concentration variations are calculated,
0, otherwise.

5. A Sample Problem

As an example, consider the region shown in Figure VIII-1, which is 17 x 22 cells, with the outer edge used as the boundary; the area modeled is thus 15 x 20 cells. There are 4 cells in the vertical direction, 13 chemical species to be modeled, and 200 elevated point sources. There are spatially varying terrain and temperature data but no roadway emissions file and, therefore, no surface layer variations. The core requirement calculations for this unsegmented region, which are shown in Exhibit VIII-2, indicate that the vector of available space must be at least 40373 words long. If it is not that long, the region must be divided into segments small enough to fit in core.

First, the user must try dividing the region in half, as shown in Figure VIII-2. (Recall that at each segment interface there is a two-cell overlap into the adjacent segment.) The resulting two segments are each 17 x 13 and the area modeled within each is 15 x 10. Each has one non-external edge 17 cells long. If the point sources are distributed fairly

<u>Segment</u>	<u>Inner Area</u>	<u>Total Area</u>	<u>Interface Cells</u>
1	15 x 20	17 x 22	0




Figure VIII-1. Sample Region--Unsegmented

Fixed Dimensions Simulation Options (1 = yes, 0 = no)

$$\begin{aligned} z &= \underline{4} \\ s &= \underline{13} \\ r &= \underline{12} \end{aligned}$$

$$\begin{aligned} \text{TEMPERATUR} &= \underline{1} \\ \text{TERRAIN} &= \underline{1} \\ \text{ROADWAY} &= \underline{0} \\ \text{VARIATION} &= \underline{0} \end{aligned}$$

	Segment			
	1	2	3	4
x	17			
y	22			
p	200			
interface	-			

$$65 \times \frac{1}{\text{seg}} = \underline{65} \text{ (S.T.)}$$


$$\left[5 + \frac{128}{32z} + \frac{52}{zs} + \frac{65}{5s} + \frac{48}{4r} + \frac{288}{2r^2} + \frac{132}{6(x,y)_{\max}} \right] = \underline{718} \text{ (L.T.)}$$

$$\left[\frac{8 \cdot 39}{8(x+y)} + \frac{0}{zs \text{ (interface)}} \right] = \underline{312} \text{ (B.T.)}$$

$$\left[8 + \frac{2}{2\text{terr}} + \frac{1}{\text{temp}} + \frac{0}{\text{road}} + \frac{8}{2z} + \frac{13}{s} \left(2 + \frac{0}{\text{road}} + \frac{0}{\text{var}} \right) + \frac{52}{zs} \right] \rightarrow \left[\frac{97}{1} \times \frac{374}{xy} + \frac{15}{2+s} \times \frac{200}{p} \right] = \underline{39278} \text{ (S.S.T.)}$$

$$\begin{aligned} \text{Sum of all tables} &= \underline{40373} \\ \text{Available storage} &= \underline{30,000} \end{aligned}$$

<u>Segment</u>	<u>Inner Area</u>	<u>Total Area</u>	<u>Interface Cells</u>
1	15 x 10	17 x 13	2 x 17
2	15 x 10	17 x 13	2 x 17



* Segment origins input to the file segmentation program.

Figure VIII-2. Sample Region Divided into Two Segments

evenly throughout the region, there will be approximately 100 in each segment (count only the point sources within the modeled area, not those in the interface cells). Exhibit VIII-3 shows the computation of a core requirement of 25763 for this two-segment scheme.

If the two-segment scheme is still too large, the region can be further divided. Figure VIII-3 illustrates a three-segment scheme, without the actual segment edges drawn in. Size computations are shown in Exhibit VIII-4.

The objective of any segment layout design is to minimize the length of the segment boundaries to obtain segments that are as nearly square and equal sized as possible. Thus, the arrangement of the three segments shown in Figure VIII-3 represents a more efficient utilization of core space than that which would be obtained by merely cutting the region into three slices along either axis.

B. THE FILE SEGMENTATION PROGRAM

The spatially varying data files must be converted into segmented form according to the region segmentation scheme selected. If segmentation is not necessary, the files may be used in their unconverted form since unsegmented files are structured like segmented files that contain only one segment. The file segmentation program (SEGDEF) is used to create a segmented file from an unsegmented file. It will operate on any of the 11 spatially varying M.E.B. files, but only on one at a time. SEGDEF requires subroutines from the libraries UTILITY and FILUTIL.

The input to SEGDEF consists of a card deck and one unsegmented file, as illustrated in Figure VIII-4. The CONTROL and REGION packets are described in detail in Section V.A. The SEGMENTDEF and SEGMENT FILE packets are defined here in Sections B.1 and B.2.

Fixed Dimensions Simulation Options (1 = yes, 0 = no)

$$\begin{aligned} z &= \underline{4} \\ s &= \underline{13} \\ r &= \underline{12} \end{aligned}$$

$$\begin{aligned} \text{TEMPERATUR} &= \underline{1} \\ \text{TERRAIN} &= \underline{1} \\ \text{ROADWAY} &= \underline{6} \\ \text{VARIATION} &= \underline{0} \end{aligned}$$

	Segment			
	1	2	3	4
x	17	17		
y	13	13		
p	100	100		
interface	34	34		

$$65 \times \frac{2}{\text{seg}} = \underline{130} \text{ (S.T.)}$$

$$\left[\begin{aligned} &5 + \frac{128}{32z} + \frac{52}{zs} + \frac{65}{5s} \\ &+ \frac{48}{4r} + \frac{288}{2r^2} \\ &+ \frac{102}{6(x,y)_{\max}} \end{aligned} \right] = \underline{688} \text{ (L.T.)}$$

$$\left[\frac{240}{8(x+y)} + \frac{52 \cdot 34}{zs \text{ (interface)}} \right] = \underline{2008} \text{ (B.T.)}$$


$$\left[\begin{aligned} &8 + \frac{2}{2\text{terr}} + \frac{1}{\text{temp}} + \frac{0}{\text{road}} \\ &+ \frac{8}{2z} \\ &+ \frac{13}{5} \left(2 + \frac{0}{\text{road}} + \frac{0}{\text{var}} \right) \\ &+ \frac{52}{zs} \end{aligned} \right] \rightarrow \left[\right] \times \frac{97}{xy} \times \frac{221}{xy}$$

$$+ \frac{15}{2+s} \times \frac{100}{p} = \underline{22937} \text{ (S.S.T.)}$$

$$\text{Sum of all tables} = \underline{25763}$$

$$\text{Available storage} = \underline{30000}$$

<u>Segment</u>	<u>Inner Area</u>	<u>Total Area</u>	<u>Interface Cells</u>
1	7 x 13	10 x 16	2 x (10 + 16)
2	8 x 13	11 x 16	2 x (11 + 16)
3	15 x 7	17 x 10	2 x 17



* Segment origins input to the file segmentation program.

Figure VIII-3. Sample Region Divided into Three Segments

Fixed Dimensions Simulation Options (1 = yes, 0 = no)

$$\begin{aligned} z &= \underline{4} \\ s &= \underline{13} \\ r &= \underline{12} \end{aligned}$$

$$\begin{aligned} \text{TEMPERATUR} &= \underline{1} \\ \text{TERRAIN} &= \underline{1} \\ \text{ROADWAY} &= \underline{0} \\ \text{VARIATION} &= \underline{0} \end{aligned}$$

	Segment			
	1	2	3	4
x	10	11	17	
y	16	16	10	
p				
interface	52	54	34	

$$65 \times \frac{3}{\text{seg}} = \underline{195} \text{ (S.T.)}$$

$$\left[\begin{aligned} &5 + \frac{128}{32z} + \frac{52}{zs} + \frac{65}{5s} \\ &+ \frac{48}{4r} + \frac{288}{2r^2} \\ &+ \frac{102}{6(x,y)_{\max}} \end{aligned} \right] = \underline{688} \text{ (L.T.)}$$

$$\left[\frac{8 \cdot 27}{8(x+y)} + \frac{52 \cdot 54}{zs \text{ (interface)}} \right] = \underline{3024} \text{ (B.T.)}$$

$$\left[\begin{aligned} &8 + \frac{2}{2\text{terr}} + \frac{1}{\text{temp}} + \frac{0}{\text{road}} \\ &+ \frac{8}{2z} \\ &+ \frac{13}{s} \left(2 + \frac{-}{\text{road}} + \frac{-}{\text{var}} \right) \\ &+ \frac{52}{zs} \end{aligned} \right] \rightarrow \left[\right] \times \frac{97}{xy} \times \frac{176}{xy} + \frac{15}{2+s} \times \frac{80}{p} = \underline{18272} \text{ (S.S.T.)}$$

$$\text{Sum of all tables} = \underline{22179}$$

$$\text{Available storage} = \underline{30000}$$




Figure VIII-4. Information Flow Diagram for the File Segmentation Program

The CONTROL packet entries for SEGDEF are shown in Table VIII-1. The following are special considerations for the CONTROL and REGION packets that pertain to this program:

> CONTROL

- The file name provided in Card 2 must be SEGMENTDEF.
- The only options recognized by the file segmentation program are the number of species, the number of segments, and the print flags for the input cards and the segmented regional grid.
- The beginning and ending dates can be the same as or contained within those of the file to be segmented.
- The list of species may be a subset of the list in the file; their number must be the same as the entry in the control parameter above. If the file to be segmented contains no species, the list can be omitted.

> REGION

- This packet is standard in all respects. The region can be a subregion of the region described in the file; if the file is three-dimensional, vertical parameters in the REGION packet must match those on the file.

1. The SEGMENTDEF Packet

The SEGMENTDEF packet provides the definition of the segmentation scheme. The contents of this packet are described in Table VIII-2, and the format is shown in Exhibit VIII-5. For every segment there should be one Card 2 containing parameters defining the inner, modeled area of the grid. Thus, in the Figure VIII-2, a two-segment scheme, the origin of Segment 1 is defined as Cell (2,2) and its dimensions are 15 x 10. The origin of Segment 2 is defined as Cell (2,12) and its dimensions are also 15 x 10. The file segmentation program adds extra cells as necessary at external boundaries and at segment interfaces, and adjusts the origins and dimensions accordingly. In Figure VIII-3, the segment origins to be specified in the SEGMENTDEF packet are indicated by stars in the grid cells.

Table VIII-1. CONTROL Packet Entries for File Segmentation

<u>Card Number</u>	<u>Entry</u>
4	Number of species
	Spare
	Spare
	Number of segments
	Spare
	Spare
5	Spare
	Print input cards
	Print regional grid
	Spare
	Spare
	Spare
6	Spare
	Spare
	Spare
	Spare
	Spare
	Spare
7	Spare
	Spare
	Spare
	Spare
	Spare
	Spare
8	Spare
	Spare
	Spare
	Spare
	Spare
	Spare

Table VIII-2. Contents of SEGMENTDEF Packet Cards

Card Number and Name	Item and Columns	Format	Units	Comments
¹ Packet Header	Header 1-10	60A1	--	Must be SEGMENTDEF, left adjusted
²⁺ Segment Defini- tion	x-origin 1-10	I10	Grid units	x-index of cell in lower left corner of the modeled area of the segment
	y-origin 11-20	I10	Grid units	y-index of cell above
	Number of x- cells 21-30	I10	--	Length in x-direction of the modeled area of the segment
	Number of y- cells 31-40	I10	--	Length in y-direction of the modeled area of the segment
³ Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	1-10	11-20	21-30	31-40	41-50	51-60	FORTTRAN Format
1	Packet Header	SEGMENTDEF						60A1
2+	Segment Definition	x-origin	y-origin	x-size	y-size			4110
3	Packet Terminator	END					.	10A1

Exhibit VIII-5. SEGMENTDEF Packet Format

2. The SEGMENT FILE Packet

The SEGMENT FILE packet provides the name of the file to be segmented and the standard input and output units for the unsegmented and segmented files, respectively. The contents of this packet are described in Table VIII-3, and the format is shown in Exhibit VIII-6. The file name on the file designation card must be one of the following:

- > AIRQUALITY
- > BOUNDARY
- > DIFFBREAK
- > EMISSIONS
- > PTSOURCE
- > REGIONTOP
- > ROADWAY
- > TEMPERATUR
- > TERRAIN
- > TOPCONC
- > WIND

The input file unit number must always be 17, and the output file unit number must always be 27.

Exhibit VIII-7 shows sample input to the file segmentation program; Exhibit VIII-8 shows sample output from this program.

Table VIII-3. Contents of SEGMENT FILE Packet Cards

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	60A1	--	Must be SEGMENT FILE, left adjusted
2 File Designation	File name 1-10	10A1	--	File name
	Input unit 11-20	I10	--	Unit number of unsegmented file-- must be 17
	Output unit 21-30	I10	--	Unit number of segmented file-- must be 27
3 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	1-10	11-20	21-30	31-40	41-50	51-60	FORTAN Format
1	Packet Header	SEGMENT FILE						60A1
2	File Designation	file name	input unit	output unit				10A1, 2110
3	Packet Terminator	END						10A1

Exhibit VIII-6. SEGMENT FILE Packet Format

CONTROL
 SEGMENT DEFINITION
 SEGMENTATION OF ST. LOUIS FILES FOR 4 X 4 GRID

NO	76195	500	76195	2400
NO2				
O3				
ETH				
OLE				
PAR				
CARB				
ARO				
BZA				
PAN				
CO				
END				
REGION	725000.	4252000.	15	
	-19000.	-16000.		
	4000.	4000.		
	17	22	4	
	2	2	0.0	50.
				200.
END				
SEGMENTDEF	2	2	2	15
1				10
2				10
END				
SEGMENT FILE				
TEMPERATUR	17		27	
END				

Exhibit VIII-7. Sample Input to the File Segmentation Program

REGIONAL DEFINITION

UTM ORIGIN X-COORDINATE	725000.
UTM ORIGIN Y-COORDINATE	4252000.
UTM ORIGIN ZONE NUMBER	15
REGION ORIGIN X-COORDINATE	-19000.
REGION ORIGIN Y-COORDINATE	-16000.
CELL LENGTH IN X-DIRECTION	4000.00
CELL LENGTH IN Y-DIRECTION	4000.00
NUMBER OF CELLS IN X-DIRECTION	17
NUMBER OF CELLS IN Y-DIRECTION	22
NUMBER OF CELLS IN Z-DIRECTION	4
NUMBER OF CELLS IN LOWER VERTICAL LAYER	2
NUMBER OF CELLS IN UPPER VERTICAL LAYER	2
HEIGHT OF SURFACE LAYER	.00
MINIMUM CELL HEIGHT IN LOWER LAYER	50.00
MINIMUM CELL HEIGHT IN UPPER LAYER	200.00
KCRNT = 113 NSCLFT = 35798 IN SCRSET	
KCRNT = 115 NSCLFT = 35796 IN SCRSET	
KCRNT = 117 NSCLFT = 35794 IN SCRSET	
KCRNT = 119 NSCLFT = 35792 IN SCRSET	
KCRNT = 130 NSCLFT = 35781 IN SCRSET	
KCRNT = 150 NSCLFT = 35761 IN SCRSET	
KCRNT = 524 NSCLFT = 35387 IN SCRSET	
SEGMENTDEF	
1 2 2 15 10	
2 2 12 15 10	
END 0 0 0 0	

FILE NAME	--	SEGMENTDEF	SEGMENTATION OF ST. LOUIS FILES FOR 4 X 4 GRID																PAGE
SEGMENT DEFINITION FOR DATA FILE CONTAINING,			SEGMENTDEF VERT. LEVEL 1 START DATE/TIME 76195 5.00 STOP DATE/TIME 76195 24.00																
GRID CELL	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17		
22	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0		
21	0	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	0		
20	0	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	0		
19	0	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	0		
18	0	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	0		
17	0	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	0		
16	0	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	0		
15	0	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	0		
14	0	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	0		
13	0	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	0		
12	0	2	2	2	2	2	2	2	2	2	2	2	2	2	2	2	0		
11	0	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	0		
10	0	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	0		
9	0	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	0		
8	0	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	0		
7	0	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	0		
6	0	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	0		
5	0	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	0		
4	0	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	0		
3	0	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	0		
2	0	1	1	1	1	1	1	1	1	1	1	1	1	1	1	1	0		
1	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0	0		

Exhibit VIII-8 (Continued)

SEGMENT DEFINITION TABLE

SEGMENT NAME	X-ORIGIN CELL	Y-ORIGIN CELL	NO. X-CELLS	NO. Y-CELLS
1	0	0	17	13
2	0	9	17	13
SEGMENT FILE				
TEMPERATUR 17 27				
KCRNT = 375 NSCLFT = 35013 IN SCRSET				
KCRNT = 749 NSCLFT = 34639 IN SCRSET				
KCRNT = 1123 NSCLFT = 34265 IN SCRSET				
END 0 0				

Exhibit VIII-8 (Continued).

PROCESSING OF INPUT DATA FOR THE PREPARATION OF FILE SEGMENTDEF
SEGMENTATION OF ST. LOUIS FILES FOR 4 X 4 GRID

NUMBER OF SPECIES = 11
NUMBER OF SEGMENTS = 2
INPUT CARDS WILL BE PRINTED
BEGINNING DATE OF FILE 76195 BEGINNING TIME OF FILE 5.00
ENDING DATE OF FILE 76195 ENDING TIME OF FILE 24.00
A TOTAL OF 11 SPECIES NAMES WERE READ ,
THE SPECIES NAMES ARE --

NO
NO2
O3
ETH
OLE
PAR
CARB
ARO
BZA
PAN
CO

REGION	725000.	4252000.	15
	-19000.	-16000.	
	4000.00	4000.00	
	17	22	4
	2	2	.00
			50.00
			200.00
END			

IX PREPARATION OF CONTROL DATA

Of the 14 files input to the Airshed Simulation Program, two are classified as control data files: the Chemistry Parameters file (CHEMPARAM), and the Simulation Controls file (SIMCONTROL). This chapter describes in detail the preparation of these files and includes for each a job control illustration, packet item definitions and packet formats, worksheets, and sample input and output listings.

A. THE CHEMISTRY PARAMETERS FILE

The Chemistry Parameters (CHEMPARAM) file names the species to be simulated and specifies values for species-related and reaction-related parameters. Figure IX-1 is an information flow diagram for use in setting up the job control for a CHEMPARAM file creation run. The program that creates the CHEMPARAM file is called CPREP; it requires as input a CONTROL packet, a SPECIES packet, and if there is to be chemistry, a REACTIONS packet and a COEFFICIENTS packet (fully described below). The printed output from CPREP consists of input numbers, error messages, if any, and the values written to the CHEMPARAM file (see Section A.5 of this chapter for sample input and output listings). The file itself is written to FORTRAN Unit 2, and the file format is given in Chapter IX of the Systems Manual.

1. CONTROL Packet Rules for the CHEMPARAM File

An abbreviated CONTROL packet is used to create the CHEMPARAM file. The packet names and identifies the file and specifies for it the number of species, reactions, and coefficients. This packet must be entered before any other packet. The contents of each card in the CONTROL packet are described in Table IX-1 and the format is shown in Exhibit IX-1.




Figure IX-1. Information Flow Diagram for Use in Creation of the CHEMPARAM File

Table IX-1. CONTROL Packet for the CHEMPARAM File

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	10A1	--	Must be CONTROL, left adjusted
2 File Name	File name 1-10	10A1	--	Must be CHEMPARAM, left adjusted
3 File Identifier	Identifier 1-60	60A1	--	Any 60 characters; the file identifier will appear on the File Description Header Record
4 Control Options	Number of species 1-10	I10	--	Must be at least 1; the number of species that will appear in the SPECIES packet and that will thus be included in the airshed simulation; at present, this number must be ≤ 20
	Number of reactions 11-20	I10	--	The number of reactions that will be described in the REACTIONS packet; for the Carbon-Bond Mechanism, this number should be 69; at present, this number must be ≤ 80 .
	Number of coefficients 21-30	I10	--	The number of coefficients that will be defined in the COEFFICIENTS packet; if inert species only are to be simulated, set this number to zero and omit the COEFFICIENTS packet; for the Carbon-Bond Mechanism, this number should be 4; at present, this number must be ≤ 10
5 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	1-10	11-20	21-30	31-40	41-50	51-60	FORTAN Format
1	Packet Header	CONTROL						10A1
2	File Name	CHEMPARAM						10A1
3	File Identifier							60A1
4	Control Parameters	# species	# reacs	# coeffs				3I10
5	Packet Terminator	END						10A1

Exhibit IX-1. CONTROL Packet Format for the CHEMPARAM File

2. SPECIES Packet Rules for the CHEMPARAM File

The SPECIES packet must follow the CONTROL packet in the input deck used to create the CHEMPARAM file. The SPECIES packet consists of a packet header card, one pair of Cards 2 and 3 for each species to be simulated, and a packet terminator card. The contents of each card in the SPECIES packet are described in Table IX-2, and the format is shown in Exhibit IX-2.

The chemical species can appear in any order on the CHEMPARAM file, provided that all the reactive species precede all the unreactive species. The output files AVERAGE, INSTANT, and VARIATION will contain these species in this order.

If any reactive species are to be simulated, their names must correspond to the species names used in the chemical mechanism that is built into the program. For the Carbon-Bond II Mechanism (currently built into the program), the following species names are required:

- > NO
- > NO2
- > O3
- > ETH
- > OLE
- > PAR
- > CARB
- > ARO
- > BZA
- > PAN
- > CO.

All the first 10 species (NO through PAN) must appear (though not necessarily in the order listed) and all must be flagged as reactive. CO must

Table IX-2. SPECIES Packet for the CHEMPARAM File

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	10A1	--	Must be SPECIES, left adjusted
Species Name and Flags				
	Species name 1-10	10A1	--	Any 10-characters, left adjusted
	Reactive flag 11	A1, 9X	--	An R in Col. 11 indicates that the species is reactive; anything else means unreactive
	Steady-state initial condi- tions flag 30	9X, L1	--	T or F in Col. 30--a blank means false; if true, steady-state computations will be performed in the Airshed Simulation Program to set initial concentrations; at present, these computations are implemented in the Carbon-Bond Mechanism for O ₃ only; when computations are performed for O ₃ , concentrations of NO and NO ₂ are also adjusted
	Steady-state boundary condi- tions flag 40	9X, L1	--	T or F in Col. 40--a blank means false; if true, steady-state computations will be performed at each time slice in the airshed simulation to set boundary concentrations on the vertically varying west, east, south, and north planes (from file BOUNDARY) and on the x-y plane at the top of the region (from file TOPCONC); at present, these computations are implemented in the Carbon-Bond Mechanism for O ₃ only; when computations are performed for O ₃ , concentrations of NO and NO ₂ are also adjusted

Table IX-2 (Concluded)

Card Number and Name	Item and Columns	Format	Units	Comments
3 Other Parameters				
	Surface uptake resistance 1-10	F10.0	(m/hr) ⁻¹	To eliminate surface deposition, set this number to a high value, e.g., 1.E6
	Steady-state lower bound 11-20	F10.0	ppm (μg/m ³ for AEROSOLS)	Computed steady-state concentrations will not be allowed to go below this value, which will also be used for initial or boundary concentrations if this species is missing from an input data file (AIRQUALITY, BOUNDARY, or TOPCONC)
	Steady-state upper bound 21-30	F10.0	ppm (μg/m ³ for AEROSOLS)	This number must be greater than the steady-state lower bound; computed steady-state concentrations will not be allowed to exceed this value.
	Numerical lower bound 31-40	F10.0	ppm (μg/m ³ for AEROSOLS)	Computed concentrations will not be allowed to go below this value in the horizontal transport steps of the simulation
	Numerical upper bound 41-50	F10.0	ppm (μg/m ³ for AEROSOLS)	This number must be greater than the numerical lower bound; computed concentrations will not be allowed to exceed this value in the horizontal transport steps of the simulation (at present, this test is not implemented)
4 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	1-10	11-20	21-30	31-40	41-50	51-60	FORTRAN Format
1	Packet Header	SPECIES						10A1
2	Species Name and Flags	species name	reactive	st-st i conc	st-st b conc			10A1, A1, 9X, 2L10
3	Other Species Parameters	surf uptake resis	low bd st-st	up bd st-st	low bd num	up bd num		5F10.0
4	Packet Terminator	END						10A1

Exhibit IX-2. SPECIES Packet Format for the CHEMPARAM File

also appear, without a reactive flag, and must follow the listing of all the reactive species. SO2 and AEROSOLS each can be named as reactive or unreactive, or they can be omitted from the simulation altogether. Any other reactive species are illegal, since there have been no reactions defined to deal with them. However, any other unreactive species can be specified without limitation other than core availability.

The species names on the species-varying data files must also correspond to the names in the CHEMPARAM file. If a name that is not on the CHEMPARAM file appears on a data file, the data for that species will be ignored. If a name is on the CHEMPARAM file but does not appear on a data file, the following default values apply:

- > For concentration data (from AIRQUALITY, BOUNDARY, or TOPCONC), the steady-state lower bound values (see Card 3 of the SPECIES packet) will be used.
- > For emissions data (from EMISSIONS, ROADWAY, or PTSOURCE), the value zero will be used.

Exhibit IX-3(a) is a worksheet that can be used to aid in the preparation of the SPECIES packet. Exhibit IX-3(b) is a sample of that worksheet filled in with typical values used for the Carbon-Bond II Mechanism.

Species	Reactive?	Steady-State Initial	Steady-State Boundary	Surface Uptake Resistance	Steady-State Lower Bound	Steady-State Upper Bound	Numerical Lower Bound	Numerical Upper Bound
	11	21-30	31-40	1-10	11-20	21-30	31-40	41-50
	A1	L10	L10	F10.0	F10.0	F10.0	F10.0	F10.0
NO	R	F	F	0.28	1.E-5	1.E+6	1.E-5	1.E+6
NO2	R	F	F	0.0111	1.E-4		1.E-4	
O3	R	T	T	0.0147	1.E-9		1.E-9	
ETH	R	F	F	1.E+10	1.E-4		1.E-4	
OLE	R	F	F	1.E+10	1.E-4		1.E-4	
PAR	R	F	F	1.E+10	1.E-4		1.E-4	
CARB	R	F	F	1.E+10	1.E-4		1.E-4	
ARG	R	F	F	1.E+10	1.E-4		1.E-4	
PAN	R	F	F	1.E+10	1.E-8		1.E-8	
BZA	R	F	F	1.E+10	1.E-8		1.E-8	
AEROSOLS	R	F	F	1.E+10	24.0		24.0	
SO2	R	F	F	.0097	1.E-6		1.E-6	
CO	L	F	F	1.E+10	0.01		0.01	

(b) Worksheet Filled In with Typical Values Used for the Carbon-Bond II Mechanism

Exhibit IX-3 (Concluded)

3. REACTIONS Packet Rules for the CHEMPARAM File

If the number of reactions specified in the CONTROL packet is greater than zero, there must be a REACTIONS packet following the SPECIES packet. If there are no reactions, the REACTIONS packet must be omitted. This packet consists of a header card, a mechanism name, one card for each reaction, and a packet terminator. The contents of each card in the REACTIONS packet are listed in Table IX-3, and the format is shown in Exhibit IX-4.

For simulation purposes, a reaction is considered to be photolysis, or temperature-dependent, or neither of these. If the photolysis flag is "on" (i.e., a value of P is punched in Column 21), the reaction is photolysis. If the photolysis field is not P and the reaction rate constant and activation energy are nonzero, the reaction is temperature-dependent, and a nonzero value for the reference temperature must be provided. If the reaction rate constant or the activation energy is zero, the reaction is considered to be not temperature dependent. Exhibit IX-5(a) is a worksheet that can be used to aid in the preparation of the REACTIONS packet. Exhibit IX-5(b) is a sample of that worksheet filled in with typical values used for the Carbon-Bond II Mechanism. Since temperature-dependent reaction rates are recalculated with an exponential expression at each time step in each grid cell, it is suggested that the temperature-dependence parameters--activation energy and reference temperatures--be specified for only those reactions for which the temperature range experienced during the simulation period will produce significant differences in predicted concentrations. For the Carbon-Bond Mechanism, the activation energies considered important at present are indicated in the example of Exhibit IX-5(b).

Table IX-3. REACTIONS Packet for the CHAMPARAM File

Card Number and Name	Item and Columns	Format	Units	Comments
1 Packet Header	Header 1-10	10A1	--	Must be REACTIONS, left adjusted
2 Mechanism Name	Mechanism name 1-60	60A1	--	Any 60-character string; this name will appear in the file and on any simulation runs using the file
3 Reaction Parameters	Reaction number 1-10	I10	--	Must be 1 card for each reaction
	Nominal reaction rate constant 11-20	F10.0	ppm ⁻ⁿ hours ⁻¹ * for nonphotolysis reactions	This number is used to place the reaction parameters in their respective vectors, as well as to aid in visual identification; although the scheme described allows reaction parameter cards to appear in any sequence, strict adherence to numerical order is suggested to avoid omission or duplication of reactions For photolysis reactions, this number is multiplied by the parameter RADFACTOR on the METSCALARS file (see Chapter VII on METSCALARS); RADFACTOR is the NO₂ photolysis rate constant expressed in min⁻¹; therefore, this number is not a rate constant but rather is a dimensionless factor for relating each photolysis rate constant to the temporally varying NO₂ photolysis rate constant and for converting the rate from min⁻¹ to hour⁻¹

Table IX-3. (Concluded)

Card Number and Name	Item and Columns	Format	Units	Comments
3 (cont'd)				
	Reaction type 21	A1, 9X	--	If Col. 21 is set to P, it will be considered a photolysis reaction
	Activation energy 31-40	F10.0	°K	If this field is left blank, temperature dependence calculations will not be performed
	Reference temperature 41-50	F10.0	°K	This field must be set to nonzero if both the reaction rate and the activation energy are nonzero
4 Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

* The value of n is determined by the order of the reaction. For example, n takes on values of 0, 1, and 2 for first-, second-, and third-order reactions, respectively.

Card Number	Card Identifier	1-10	11-20	21-30	31-40	41-50	51-60	FORTTRAN Format
1	Packet Header	REACTIONS						10A1
2	Mechanism Name							60A1
3	Reaction Parameters	reac #	rate const	type	act energy	ref temp		I10, F10.0, A1, 9X, 2F10.0
4	Packet Terminator	END						10A1

Exhibit IX-4. REACTIONS Packet Format for the CHEMPARAM File

Reaction	Number	Rate Constant	Type	Activation Energy	Reference Temperature
	1-10	11-20	21	31-40	41-50
	110	F10.0	A1	F10.0	F10.0
$\text{NO}_2 + h\nu \rightarrow \text{NO} + \text{O}$	1	60.	P		
$\text{O}_2 + \text{M} \rightarrow \text{O}_2 + \text{O}_3$	2	$2.64\text{E} + 8$			
$\text{O}_3 + \text{NO} \rightarrow \text{NO}_2 + \text{O}_2$	3	$1.434\text{E} + 3$		1450.	298.
$\text{O}_3 + \text{NO}_2 \rightarrow \text{NO}_3 + \text{O}_2$	4	2.88		2450.	298.
$\text{O} + \text{NO}_2 \rightarrow \text{NO} + \text{O}_2$	5	$8.04\text{E} + 5$			
$\text{O}_3 + \text{OH} \rightarrow \text{HO}_2 + \text{O}_2$	6	$4.62\text{E} + 3$		1000.	298.
$\text{O}_3 + \text{HO}_2 \rightarrow \text{OH} + 2\text{O}_2$	7	$3.00\text{E} + 2$		1525.	298.
$\text{NO}_2 + \text{OH} \rightarrow \text{HNO}_3$	8	$8.40\text{E} + 5$			
$\text{CO} + \text{OH} \xrightarrow{\text{O}_2} \text{HO}_2 + \text{CO}_2$	9	$2.64\text{E} + 4$			
$\text{NO} + \text{NO} \xrightarrow{\text{O}_2} 2\text{NO}_2$	10	$9.00\text{E} - 3$			
$\text{NO}_3 + \text{NO} \rightarrow 2\text{NO}_2$	11	$1.68\text{E} + 6$			

Column
Format

Column
Format

Reaction	Number	Rate Constant	Type	Activation Energy	Reference Temperature
	1-10	11-20	21	31-40	41-50
	I10	F10.0	A1	F10.0	F10.0
NO ₃ + NO ₂ + H ₂ O → 2HNO ₃	12	9.00E - 3		-10600.	298.
HO ₂ + NO → NO ₂ + OH	13	7.20E + 5			
HO ₂ + HO ₂ → H ₂ O ₂ + O ₂	14	9.00E + 5			
PAR + O → MEO ₂ + OH	15	1.20E + 3			
PAR + OH → MEO ₂	16	9.00E + 4			
OLE + O → MEO ₂ + ACO ₃ + X	17	1.62E + 5			
OLE + O → CARB + PAR	18	1.62E + 5			
OLE + OH → RAO ₂	19	2.52E + 6			
OLE + O ₃ → CARB + CRIG	20	4.80E - 1			
OLE + O ₃ → CARR + MCRG + X	21	4.80E - 1			
ETH + O → MEO ₂ + HO ₂ + CO	22	3.60E + 4			
ETH + O → CARR + PAR	23	3.60E + 4			
ETH + OH → RBO ₂	24	7.20E + 5			

Column

Format

Reaction	Number	Rate Constant	Type	Activation Energy	Reference Temperature
	1-10	11-20	21	31-40	41-50
	110	F10.0	A1	F10.0	F10.0
ETH + O ₃ → CARB + CRIG	25	1.44E - 1			
ACO ₃ + NO + NO ₂ + MEO ₂ + CO ₂	26	2.28E + 5			
RBO ₂ + NO + NO ₂ + 2 CARB + HO ₂	27	7.20E + 5			
RAO ₂ + NO + NO ₂ + 2 CARB + HO ₂	28	7.20E + 5			
MEO ₂ + NO + NO ₂ + CARB + MEO ₂ + X ·	29	2.30E + 5			
MEO ₂ + NO + NO ₂ + CARB + HO ₂	30	4.60E + 5			
MEO ₂ + NO + Nitrates	31	3.00E + 4			
RBO ₂ + O ₃ + 2 CARB + HO ₂	32	3.00E + 2			
RAO ₂ + O ₃ + 2 CARB + HO ₂	33	1.20E + 4			
MEO ₂ + O ₃ + CARB + HO ₂	34	3.00E + 2			
CARB + OH → α (HO ₂ + CO) + (1 - α) (ACO ₃ + X)	35	1.14E + 6			
CARB + hν → CO	36	1.35E - 3	P		
CARB + hν → (1 + α) HO ₂ + (1 - α) (MEO ₂ + X) + CO	37	1.215E - 1	P		

Reaction	Number	Rate Constant	Type	Activation Energy	Reference Temperature
	1-10	11-20	21	31-40	41-50
	110	F10.0	A1	F10.0	F10.0
X + PAR + Products	38	6.00E + 6			
ACO ₃ + NO ₂ + PAN	39	1.20E + 5			
PAN + ACO ₃ + NO ₂	40	1.68E + 0		12500.	298.
ACO ₃ + NO ₂ + Products	41	2.40E + 5			
MEO ₂ + NO ₂ + Products	42	2.40E + 5			
CRIG + NO + NO ₂ + CARB	43	7.20E + 5			
CRIG + NO ₂ + NO ₃ + CARB	44	4.80E + 5			
CRIG + CARB + Ozonide	45	1.20E + 5			
MCRG + NO + NO ₂ + CARB + PAR	46	7.20E + 5			
MCRG + NO ₂ + NO ₃ + CARB + PAR	47	4.80E + 5			
MCRG + CARB + Ozonide	48	2.00E + 3			
CRIG + CO	49	4.02E + 4			
CRIG + Products	50	1.44E + 4			

Column

Format

Column
Format

Reaction	Number	Rate Constant	Type	Activation Energy	Reference Temperature
	1-10	11-20	21	31-40	41-50
	110	F10.0	A1	F10.0	F10.0
CRIG + 2HO ₂ + CO ₂	51	5.40E + 3			
MERG + Products	52	9.00E + 3			
MERG + MEO ₂ + OH + CO	53	2.04E + 4			
MERG + MEO ₂ + HO ₂ + CO ₂	54	2.55E + 4			
MERG + CARB + 2HO ₂ + CO	55	5.10E + 3			
ARO + OH + HO ₂ + 3 ARP1	56	3.60E + 5			
ARO + OH + HO ₂ + BZA + X	57	9.60E + 4			
ARO + OH + OH + BZA + W	58	9.00E + 5			
CARB + W + Products	59	6.00E + 6			
NO + ARP1 + PAR + CARB + NO	60	1.80E + 3			
NO + ARP1 + NO ₂ + Aerosol	61	9.00E + 2			
NO ₃ + ARP1 + 2 CARB	62	2.10E + 6			

Column
Format

Reaction	Number	Rate Constant	Type	Activation Energy	Reference Temperature
	1-10	11-20	21	31-40	41-50
	110	F10.0	A1	F10.0	F10.0
$O_3 + APRI \rightarrow \text{Aerosol}$ $BZA + OH + NO_2 + CO + 3 APRI$ $BZA + ME O_2 + HO_2 + 3 APRI$ $SO_2 + OH \xrightarrow{O_2} HSO_5$ $HSO_5 + NO + NO_2 + HSO_4$ $HSO_4 + NO_2 + H_2SO_4 + HNO_3$ $SO_2 + \text{Aerosol}$	63 64 65 66 67 68 69	3.60E + 1 6.00E + 5 2.16E + 0 5.40E + 1 4.80E + 4 5.40E + 5 3.00E - 2	P		

4. COEFFICIENTS Packet Rules for the CHEMPARAM File

If the number of coefficients specified in the CONTROL packet is greater than zero, there must be a COEFFICIENTS packet, and it must follow the REACTIONS packet (or the SPECIES packet, if there is no REACTIONS packet). If there are no coefficients, this packet must be omitted. The COEFFICIENTS packet consists of a header card, one card for each coefficient, and a packet terminator. The contents of each card are described in Table IX-4, and the format is shown in Exhibit IX-6.

Exhibit IX-7(a) is a worksheet that can be used to aid in the preparation of the COEFFICIENTS packet. Exhibit IX-7(b) is a sample of that worksheet filled in with typical values used for the Carbon-Bond II Mechanism.

Table IX-4. COEFFICIENTS Packet for the CHEMPARAM File

Card Number and Name	Item and Columns	Format	Units	Comments
¹ Packet Header	Header 1-10	10A1	--	Must be COEFFICIENTS, left adjusted
² Coefficient	Coefficient name 1-10	10A1	--	10 characters, left adjusted; must be identical to a coefficient name required by the built-in chemical mechanism
	Coefficient value 11-20	F10.0	--	
³ Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	1-10	11-20	21-30	31-40	41-50	51-60	FORTAN Format
1	Packet Header	COEFFICIENTS						10A1
2	Coefficients	Name	Value					10A1, F10.0
3	Packet Terminator	END						10A1

Exhibit IX-6. COEFFICIENTS Packet Format for the CHEMPARAM File

Column Format	Meaning	Name	Value
		1-10	11-20
		10A1	F10.0

(a) Format

Exhibit IX-7. COEFFICIENTS Definition Worksheet

Column Format	Meaning	Name	Value
		1-10	11-20
		10A1	F10.0
		ALPHA	0.5
		BETA	.48
		GAMMA	1 0
		ETA	0.1

(b) Worksheet Filled In with Typical Values Used for the
Carbon-Bond Mechanism

Exhibit IX-7 (Concluded)

5. CPREP Sample Input and Output

Exhibit IX-8 is a listing of an input deck used to create a CHEMPARAM file; it contains the values from the sample worksheets [Exhibits IX-3(b), IX-5(b), and IX-7(b)]. Exhibit IX-9 is the printout that was generated by CPREP; the first two pages list the values on the input cards as they are read in, and the last two show the values put out to the CHEMPARAM file.

CONTROL		CHEMPARAM		CHEMISTRY PARAMETERS		NEW CHEM		HIGHER PARAFINS LOWER LIMIT	
11		69		4		4			
END									
SPECIES									
NO	0.28	R	F	1.0E+6	F	1.0E+6	1.0E-5	1.0E+6	
NO2		R	F	1.0E+6	F	1.0E+6	1.0E-4	1.0E+6	
O3	0.0111	R	T	1.0E+6	T	1.0E+6	1.0E-9	1.0E+6	
ETH	0.0147	R	F	1.0E+6	F	1.0E+6	1.0E-6	1.0E+6	
OLE	1.E10	R	F	1.0E+6	F	1.0E+6	1.0E-6	1.0E+6	
PAR	1.E10	R	F	1.0E+6	F	1.0E+6	1.0E-6	1.0E+6	
CARB	1.E10	R	F	1.0E+6	F	1.0E+6	1.0E-4	1.0E+6	
ARO	1.E10	R	F	1.0E+6	F	1.0E+6	1.0E-6	1.0E+6	
BZA	1.E10	R	F	1.0E+6	F	1.0E+6	1.0E-6	1.0E+6	
PAN	1.E10	R	F	1.0E+6	F	1.0E+6	1.0E-6	1.0E+6	
CO	1.E10	R	F	1.0E+6	F	1.0E+6	1.0E-6	1.0E+6	
END									
REACTIONS									
CARBON BOND MECHANISM									
1	60.00E+0P								
2	264.E+6								
3	1434.						1450.	298.	
4	288.E-2						2450.	298.	
5	80.4E+4								
6	462.E+1						1000.	298.	
7	300.						1525.	298.	
8	84.E+4								
9	264.E+2								
10	90.E-4								
11	168.E+4								
12	9.0E-3								
13	72.E+4								
14	90.E+4								
15	120.E+1								
16	90.E+3								
17	162.E+3								
18	162.E+3								
19	252.E+4								
20	480.E-3								
21	480.E-3								
22	360.E+2								
23	360.E+2								
24	72.E+4								

25	144.E-3	
26	228.E+3	
27	72.E+4	
28	72.E+4	
29	2.3E+5	
30	4.6E+5	
31	300.E+2	
32	300.	
33	120.E+2	
34	300.	
35	114.E+4	
36	81.E-3P	
37	121.5E-3P	
38	60.E+5	
39	120.E+3	
40	168.E-2	
41	240.E+3	
42	240.E+3	
43	72.E+4	
44	480.E+3	
45	120.E+3	
46	72.E+4	
47	480.E+3	
48	120.E+3	
49	402.E+2	
50	144.E+2	
51	540.E+1	
52	90.E+2	
53	204.E+2	
54	255.E+2	
55	510.E+1	
56	3.60E+5	
57	9.6E+4	
58	9.0E+5	
59	6.0E+6	
60	1.8E+3	
61	9.0E+2	
62	2.1E+6	
63	3.6E+1	
64	6.0E+5	
65	2.160E+0P	
66	540.00E+2	
67	480.00E+2	
68	540.00E+3	
69	3.00E-2	

12500. 298.

END
 COEFFICIENTS
 ALPHA 0.5
 BETA .48
 GAMMA 1.0
 ETA 0.1
 END

CONTROL
CHEMPARAM
CHEMISTRY PARAMETERS NEW CHEM HIGHER PARAFINS LOWER LIMIT

11 69 4

END SPECIES	NO	R	1.0000-001	F	1.0000-005	F	1.0000+006	1.0000-005	1.0000+006
	N02	R	1.0000-002	F	1.0000-004	F	1.0000+006	1.0000-004	1.0000+006
	O3	R	1.0000-002	T	1.0000-009	T	1.0000+006	1.0000-009	1.0000+006
	ETH	R	1.0000+010	F	1.0000-006	F	1.0000+006	1.0000-006	1.0000+006
	OLE	R	1.0000+010	F	1.0000-006	F	1.0000+006	1.0000-006	1.0000+006
	PAR	R	1.0000+010	F	1.0000-003	F	1.0000+006	1.0000-004	1.0000+006
	CARB	R	1.0000+010	F	1.0000-006	F	1.0000+006	1.0000-006	1.0000+006
	APO	R	1.0000+010	F	1.0000-006	F	1.0000+006	1.0000-006	1.0000+006
	BZA	R	1.0000+010	F	1.0000-006	F	1.0000+006	1.0000-006	1.0000+006
	PAN	R	1.0000+010	F	1.0000-006	F	1.0000+006	1.0000-006	1.0000+006
	CO	R	1.0000+010	F	1.0000-002	F	1.0000+006	1.0000-002	1.0000+006

END REACTIONS	CAPROH BOND MECHANISM -- NOVEMBER 78	1	6.0000+001	P	.0000	.0000	.0000	.0000	.0000
		2	2.6400+008		.0000	.0000	.0000	.0000	.0000
		3	1.4340+003		1.4500+003	1.4500+003	2.9600+002	2.9600+002	2.9600+002
		4	2.8800+000		2.4500+003	2.4500+003	.0000	.0000	.0000
		5	8.0400+005		.0000	.0000	.0000	.0000	.0000
		6	4.6200+003		1.0000+003	1.0000+003	2.9300+002	2.9300+002	2.9300+002
		7	3.0000+002		1.5250+003	1.5250+003	.0000	.0000	.0000
		8	8.4000+005		.0000	.0000	.0000	.0000	.0000
		9	2.6400+004		.0000	.0000	.0000	.0000	.0000
		10	9.0000-003		.0000	.0000	.0000	.0000	.0000
		11	1.6300+006		.0000	.0000	.0000	.0000	.0000
		12	9.0000-003		.0000	.0000	.0000	.0000	.0000
		13	7.2000+005		.0000	.0000	.0000	.0000	.0000
		14	9.0000+005		.0000	.0000	.0000	.0000	.0000
		15	1.2000+003		.0000	.0000	.0000	.0000	.0000
		16	9.0000+004		.0000	.0000	.0000	.0000	.0000
		17	1.6200+005		.0000	.0000	.0000	.0000	.0000
		18	1.6200+005		.0000	.0000	.0000	.0000	.0000
		19	2.5200+006		.0000	.0000	.0000	.0000	.0000
		20	4.8000-001		.0000	.0000	.0000	.0000	.0000
		21	4.8000-001		.0000	.0000	.0000	.0000	.0000
		22	3.6000+004		.0000	.0000	.0000	.0000	.0000
		23	3.6000+004		.0000	.0000	.0000	.0000	.0000
		24	7.2000+005		.0000	.0000	.0000	.0000	.0000
		25	1.4400-001		.0000	.0000	.0000	.0000	.0000

Exhibit IX-9. Sample CPREP Output for the CHEMPARAM file

26	2.2800+005	.0000	.0000
27	7.2000+005	.0000	.0000
28	7.2000+005	.0000	.0000
29	2.3000+005	.0000	.0000
30	4.6000+005	.0000	.0000
31	3.0000+004	.0000	.0000
32	3.0000+002	.0000	.0000
33	1.2000+004	.0000	.0000
34	3.0000+002	.0000	.0000
35	1.1400+006	.0000	.0000
36	8.1000-002	.0000	.0000
37	1.2150-001 P	.0000	.0000
38	6.0000+006	.0000	.0000
39	1.2000+005	.0000	.0000
40	1.6000+000	1.2500+004	2.9300+002
41	2.4000+005	.0000	.0000
42	2.4000+005	.0000	.0000
43	7.2000+005	.0000	.0000
44	4.8000+005	.0000	.0000
45	1.2000+005	.0000	.0000
46	7.2000+005	.0000	.0000
47	4.8000+005	.0000	.0000
48	1.2000+005	.0000	.0000
49	4.0200+004	.0000	.0000
50	1.4400+004	.0000	.0000
51	5.4000+003	.0000	.0000
52	9.0000+003	.0000	.0000
53	2.0400+004	.0000	.0000
54	2.5500+004	.0000	.0000
55	5.1000+003	.0000	.0000
56	3.6000+005	.0000	.0000
57	9.6000+004	.0000	.0000
58	9.0000+005	.0000	.0000
59	6.0000+006	.0000	.0000
60	1.8000+003	.0000	.0000
61	9.0000+002	.0000	.0000
62	2.1000+006	.0000	.0000
63	3.6000+001	.0000	.0000
64	6.0000+005	.0000	.0000
65	2.1600+000	.0000	.0000
66	5.4000+004	.0000	.0000
67	4.8000+004	.0000	.0000
68	5.4000+005	.0000	.0000
69	3.0000-002	.0000	.0000
END			
COEFFICIENT			
ALPHA	5.00000-001		
BETA	4.80000-001		
GRITA	1.00000+000		
ETA	1.00000-001		
END			

***** CHEMPARAM FILE *****

FILE DESCRIPTION HEADER RECORD

FILE TYPE = CHEMPARAM
FILE ID = CHEMISTRY PARAMETERS NEW CHEM HIGHER PARAFINS LOWER LIMI
NO OF SECHENTS = 0
NO OF SPECIES = 11
BEG DATE = 0
BEG TIME = 0.
END DATE = 0
END TIME = 0.

SPECIES DESCRIPTION HEADER RECORD

NO
NO2
O3
ETH
OLE
PAR
CARB
ARO
BZA
PAN
CO

CHEMISTRY DEFINITION RECORD

MECHANISM ID = CARBON BOND MECHANISM -- NOVEMBER 78
NO OF REACTIONS = 69
NO OF COEFFS = 4

SPECIES PARAMETERS RECORD

SPEC NAME	REACT	SSIC	SSBC	OVRES	LOW BD SS	UP BD SS	LOW BD NUM	UP BD NUM
NO	T	F	F	2.8000-001	1.0000-005	1.0000+006	1.0000-005	1.0000+006
NO2	T	F	F	1.1100-002	1.0000-004	1.0000+006	1.0000-004	1.0000+006
O3	T	T	T	1.4700-002	1.0000-009	1.0000+006	1.0000-009	1.0000+006
ETH	T	F	F	1.0000+010	1.0000-006	1.0000+006	1.0000-006	1.0000+006
OLE	T	F	F	1.0000+010	1.0000-006	1.0000+006	1.0000-006	1.0000+006
PAR	T	F	F	1.0000+010	1.0000-003	1.0000+006	1.0000-004	1.0000+006
CARB	T	F	F	1.0000+010	1.0000-006	1.0000+006	1.0000-006	1.0000+006
ARO	T	F	F	1.0000+010	1.0000-006	1.0000+006	1.0000-006	1.0000+006
BZA	T	F	F	1.0000+010	1.0000-006	1.0000+006	1.0000-006	1.0000+006
PAN	T	F	F	1.0000+010	1.0000-006	1.0000+006	1.0000-006	1.0000+006
CO	T	F	F	1.0000+010	1.0000-002	1.0000+006	1.0000-002	1.0000+006

REACTION PARAMETERS RECORD

RATE CONST	PHOTOL	TEMP	ACT ENERGY	REF TEMP
1 6.0000+001	T	F	.0000	.0000
2 2.6400+008	F	F	.0000	.0000
3 1.4340+003	F	T	1.4500+003	2.9200+002
4 2.2800+000	F	T	2.4500+003	2.9800+002
5 8.0400+005	F	F	.0000	.0000
6 4.6200+003	F	T	1.0000+003	2.9800+002
7 3.0000+002	F	T	1.5250+003	2.9800+002
8 8.4000+005	F	F	.0000	.0000
9 2.6400+004	F	F	.0000	.0000

10	F	9.0000-003	F	.0000	.0000
11	F	1.6800+006	F	.0000	.0000
12	F	9.0000-003	T	-1.0600+004	2.9800+002
13	F	7.2000+005	F	.0000	.0000
14	F	9.0000+005	F	.0000	.0000
15	F	1.2000+003	F	.0000	.0000
16	F	9.0000+004	F	.0000	.0000
17	F	1.6200+005	F	.0000	.0000
18	F	1.6200+005	F	.0000	.0000
19	F	2.5200+006	F	.0000	.0000
20	F	4.8000-001	F	.0000	.0000
21	F	4.8000-001	F	.0000	.0000
22	F	3.6000+004	F	.0000	.0000
23	F	3.6000+004	F	.0000	.0000
24	F	7.2000+005	F	.0000	.0000
25	F	1.4400-001	F	.0000	.0000
26	F	2.2800+005	F	.0000	.0000
27	F	7.2000+005	F	.0000	.0000
28	F	7.2000+005	F	.0000	.0000
29	F	2.3000+005	F	.0000	.0000
30	F	4.6000+005	F	.0000	.0000
31	F	3.0000+004	F	.0000	.0000
32	F	3.0000+002	F	.0000	.0000
33	F	1.2000+004	F	.0000	.0000
34	F	3.0000+002	F	.0000	.0000
35	F	1.1400+006	F	.0000	.0000
36	T	8.1000-002	F	.0000	.0000
37	T	1.2150-001	F	.0000	.0000
38	F	6.0000+006	F	.0000	.0000
39	F	1.2000+005	F	.0000	.0000
40	F	1.6800+000	T	1.2500+004	2.9800+002
41	F	2.4000+005	F	.0000	.0000
42	F	2.4000+005	F	.0000	.0000
43	F	7.2000+005	F	.0000	.0000
44	F	4.8000+005	F	.0000	.0000
45	F	1.2000+005	F	.0000	.0000
46	F	7.2000+005	F	.0000	.0000
47	F	4.8000+005	F	.0000	.0000
48	F	1.2000+005	F	.0000	.0000
49	F	4.0200+004	F	.0000	.0000
50	F	1.4400+004	F	.0000	.0000
51	F	5.4000+003	F	.0000	.0000
52	F	9.0000+003	F	.0000	.0000
53	F	2.0400+004	F	.0000	.0000
54	F	2.5500+004	F	.0000	.0000
55	F	5.1000+003	F	.0000	.0000
56	F	3.6000+005	F	.0000	.0000
57	F	9.6000+004	F	.0000	.0000
58	F	9.0000+005	F	.0000	.0000
59	F	6.0000+006	F	.0000	.0000
60	F	1.8000+003	F	.0000	.0000

Exhibit IX-9 (Continued)

61	9.0000+002	F	F	.0000	.0000
62	2.1000+006	F	F	.0000	.0000
63	3.6000+001	F	F	.0000	.0000
64	6.0000+005	F	F	.0000	.0000
65	2.1600+000	T	F	.0000	.0000
66	5.4000+004	F	F	.0000	.0000
67	4.8000+004	F	F	.0000	.0000
68	5.4000+005	F	F	.0000	.0000
69	3.0000-002	F	F	.0000	.0000

STOICHIOMETRIC COEFFICIENTS RECORD

ALPHA	5.0000-001
BETA	4.8000-001
GAMMA	1.0000+000
ETA	1.0000-001

B. THE SIMULATION CONTROLS FILE

The Simulation Controls (SIMCONTROL) file, generally the last to be prepared, is the input file likely to be varied the most frequently. As previously mentioned, this file can routinely be prepared as a separate job step within each airshed simulation run.

Figure IX-2 is an information flow diagram for use in setting up the job control for a SIMCONTROL file creation run. The program that creates the SIMCONTROL file is called SPREP. It requires as input a CONTROL packet and a SIMULATION packet, which are described in detail in the next section. The printed output from SPREP consists of input numbers, error messages, if any, and the values written to the SIMCONTROL file (see Section B.3 of this chapter for sample input and output listings). The file itself is written to FORTRAN Unit 1, and the file format is given in Chapter IX of the Systems Manual.

1. CONTROL Packet Rules for the SIMCONTROL File

An abbreviated CONTROL packet is used to create the SIMCONTROL file. The packet names and identifies the type of file to be created, and it must be entered before any other packet. The contents of each card in the CONTROL packet are described in Table IX-5, and the format is shown in Exhibit IX-10.

2. SIMULATION Packet Rules for the SIMCONTROL File

The SIMULATION packet must follow the CONTROL packet in the input deck used to create the SIMCONTROL file. The contents of each card in the SIMULATION packet are described in Table IX-6 and the format is shown in Exhibit IX-11.




Figure IX-2. Information Flow Diagram for Use in Creation of the SIMCONTROL File

Table IX-5. CONTROL Packet for the SIMCONTROL File

<u>Card Number and Name</u>	<u>Item and Columns</u>	<u>Format</u>	<u>Units</u>	<u>Comments</u>
¹ Packet Header	Header 1-10	10A1	--	Must be CONTROL, left adjusted
² File Name	File name 1-10	10A1	--	Must be SIMCONTROL, left adjusted
³ File Identifier	Identifier 1-60	60A1	--	Any 60 characters; the file identifier will appear on the File Description Header Record
⁴ Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTAN Format
		1-10	11-20	21-30	31-40	41-50	51-60
1	Packet Header	CONTROL SIMCONTROL END					10A1
2	File Name						10A1
3	File Identifier						60A1
4	Packet Terminator						10A1

Exhibit IX-10. CONTROL Packet Format for the SIMCONTROL File

Table IX-6. SIMULATION Packet for the SIMCONTROL File

Card Number and Name	Item and Columns	Format	Units	Comments
¹ Packet Header	Header 1-10	10A1	--	Must be SIMULATION, left adjusted
² File Identifier	Identifier 1-60	60A1	--	Any 60-characters; to provide a unique identifier, change this card for each run
³ Time Limits of the Run				Beginning date and time must appear within a time interval on the AIRQUALITY file, and the entire time span shown here must be included within the time span of every other time-varying data file; when restarting a run from an intermediate stopping point, these time limits must be changed
	Beginning date 1-10	I10	Julian date (yyddd)	yy is the last two digits of the year and ddd is the three-digit Julian date
	Beginning time 11-20	I10	Military time (hhmm)	hh is hours and mm is minutes--this time will be internally converted to hours and fraction
	End date 21-30	I10	Julian date (yyddd)	Same format as beginning date
	End time 31-40	I10	Military time (hhmm)	Same format as beginning time
⁴ Simulation Options	Restart flag 1-10	L10	--	For each flag; .TRUE. means "yes, do it," and .FALSE. means "no, don't do it" Set to TRUE if this is a restart; the simulation program will not perform steady-state computations on initial concentrations if the restart flag is TRUE

Table IX-6 (Continued)

Card Number and Name	Item and Columns	Format	Units	Comments
4 (cont'd)	Surface removal flag 11-20	L10	--	Set to TRUE if the effects of pollutant uptake at the surface are to be calculated; when the surface removal flag is TRUE, there must be either a TERRAIN file or a nonzero vegetation factor specified on Card 6 of this packet
	PTSOURCE flag 21-30	L10	--	Set to TRUE if elevated point source emissions from a PTSOURCE file are to be included in the simulation; if flag is TRUE, there must be a PTSOURCE file; if it is FALSE, the PTSOURCE file, if present, will be ignored
	ROADWAY flag 31-40	L10	--	Set to TRUE if there is a ROADWAY file; flag may be reset to FALSE by the simulation program if there is no surface layer or if no reactive species are being simulated; if flag is TRUE, there must be a ROADWAY file; if flag is set to FALSE or reset to FALSE under the conditions described above, the ROADWAY file, if present, will be ignored. (Use FALSE).
	TEMPERATUR flag 41-50	L10	--	Set to TRUE if there is a TEMPERATUR file; if flag is TRUE, there must be a TEMPERATUR file; if it is FALSE, the TEMPERATUR file, if present, will be ignored; when flag is FALSE, an ambient temperature of 25°C will be assumed, and the nominal input values of the reaction rate constants will be employed in the chemistry calculations (i.e., temperature effects will be ignored)

Table IX-6 (Continued)

Card Number and Name	Item and Columns	Format	Units	Comments
4 (cont'd)	TERRAIN flag 51-60	L10	--	Set to TRUE if there is a TERRAIN file; if flag is TRUE, the TERRAIN file must be included; if it is false, the TERRAIN file, if present, will be ignored; when flag is FALSE, a default value for surface roughness must be specified on Card 6 of this packet, and a default vegetation factor must also be specified on Card 6 if surface uptake effects are to be calculated
5 More Simulation Options	Concentration variation flag 1-10	L10	--	Set to TRUE if subgrid scale concentration variation is to be calculated; if flag is TRUE, concentration variation will be calculated at each time step and averaged over the same period that concentrations are averaged; the average concentration variations will be output on the VARIATION file; the flag will be reset to FALSE in the program if there is no surface layer or no ROADWAY file
6 Default Terrain Values	Default surface roughness 1-10	F10.0	m	Must be included whether or not the values are required This value will be used to calculate the vertical diffusivity if the TERRAIN file is not input to the run; if the TERRAIN file is input, this value will be ignored

Table IX-6 (Continued)

Card Number and Name	Item and Columns	Format	Units	Comments
6 (cont'd)	Default vegetation factor 11-20	F10.0	--	Pollutant uptake capability of the surface relative to that of alfalfa; this value will be used to calculate surface deposition if the TERRAIN file is not input to the run; if the TERRAIN file is input or if surface removal effects are not to be calculated, this value will be ignored
7 Integration Controls	Maximum time slice 1-10	F10.0	hr	The largest simulation time interval during which the boundary conditions at the segment interfaces will be held constant; this parameter is used with the next one to determine the time slice size used in the Airshed Simulation Program (see Chapter IV); if the maximum slice is set very large (i.e., 1. or more), the calculated time slice will be limited by the maximum number of steps in a slice (or, if the time steps are very large, by the output time intervals or the intervals on the input files); if the maximum slice is set small relative to the typical time step calculated, it will be the limiting factor in computing the time slice size to be used
IX-43	Maximum number of steps in a slice 11-20	I10	--	This parameter is used with the previous one to calculate the time slice size used in the Airshed Simulation Program; if this number is set very large, the slice will be limited by the maximum time slice size; if the number is small, the slice will be limited by

Table IX-6 (Continued)

Card Number and Name	Item and Columns	Format	Units	Comments
7 (cont'd)				
8 Chemistry Integration Controls	Minimum chemistry time step 1-10	F10.0	hr	Provides a lower limit on the chemistry step size; the overall time step size for each segment will be determined by the maximum wind speed in the segment; within each cell, however, the time step can be further reduced for the chemistry step; if the chemistry step fails to converge or gives negative concentrations at this step size, the program will terminate
	Maximum number of iterations 11-20	I10	--	If the chemistry step does not converge within this number of iterations for any cell at a given time step, the chemistry step size for that cell will be halved and the iterative procedure will begin again
	Relative error tolerance 21-30	F10.0	--	Convergence criterion for the chemistry step--when the relative change in concentration for all species is less than this number, the iterative procedure is said to have converged; if the relative change in concentration for any species is greater than this number, another iteration will be performed

Table IX-6 (Continued)

Card Number and Name	Item and Columns	Format	Units	Comments
8 (cont'd)	Darkness criterion 31-40	F10.0	Same as for RADFACTOR on the METSCALARS file	If the calculated RADFACTOR, which varies continuously in time, is less than this number, night chemistry will be used; if the calculated RADFACTOR is greater than this number, the normal (daytime) chemistry will be used; if the simulation is performed on inert species only or if the night chemistry mechanism has been disabled, this number is ignored
9 Output Intervals	Instantaneous output interval 1-10	F10.0	hr	Instantaneous concentrations are written to the output file INSTANT at the beginning of the simulation and at this time interval thereafter; if the end of a time slice will go past the output time, the slice will be reduced to hit the output time exactly; instantaneous concentrations are also written when time-averaged concentrations are written, enabling a restart from the beginning of any averaging period
	Average output intervals 11-20	F10.0	hr	Starting at the beginning of the simulation, concentrations will be averaged over this interval and written to the AVERAGE file at the end of the interval; if the end of a time slice will go past the end of an averaging interval, the slice will be reduced to correspond to the end of the interval exactly

Table IX-6 (Continued)

Card Number and Name	Item and Columns	Format	Units	Comments
10 Print Options				
	Print file history 1-10	I10	--	Six options are read, but only five are used If this field is set to =1, a one-line message will be printed each time a time interval record is read on any data file; if set to blank or zero, the file read messages will not be printed
	Print storage allocation 11-20	I10	--	If this field is set to =1, all storage allocation pointers and controls will be printed; this information is useful only for program debugging; if set to blank or zero, the information will not be printed
	Print instantaneous concentrations 21-30	I10	--	If set positive, this is the number of vertical levels of concentrations that will be printed at the end of each instantaneous output interval (see Card 9); the boundary cells printed may contain irrelevant information and, therefore, the printouts should be used for debugging only; concentration maps will be printed for each segment, for each species, for each level up to the number specified, but not exceeding the number of levels modeled; if set to blank or zero, instantaneous concentrations will not be printed
	Print average concentrations 31-40	I10	--	If set positive, this is the number of vertical levels of average concentrations that will be printed at the end of each averaging interval (see Card 9); format and order of the average concentration printout is the same as that of the instantaneous concentration option; if set to blank or zero, average concentrations will not be printed

Table IX-6 (Concluded)

<u>Card Number and Name</u>	<u>Item and Columns</u>	<u>Format</u>	<u>Units</u>	<u>Comments</u>
10 (cont'd)	Print concentra- tion variations 41-50	I10	--	If set positive, concentration variations will be printed after instantaneous and after average concentrations as selected above. If set to blank or zero, if both options above are zero, or if concentration variations are not calculated, concentration variations are not printed
¹¹ Packet Terminator	Terminator 1-3	10A1	--	Must be END, left adjusted

Card Number	Card Identifier	Column Number					FORTRAN Format
		1-10	11-20	21-30	31-40	41-50	
1	Packet Header	SIMULATION					10A1
2	Run Identification	beg date	beg time	end date	end time		60A1
3	Time Limits of the Run	restart	surface removal	pt srces	roadway	temp	4I10
4	Simulation Options	conc vartn				terrain	6L10
5	More Simulation Options	surface roughness	vegetation				6L10
6	Default Terrain Values	max time slice	max # steps in slice				2F10.0
7	Integration Time Interval Controls	min chem step	max # iter	rel error tol	dark crit		F10.0, I10
8	Chemistry Integration Controls	instant file history	average storage allocation	instant conc	average conc	conc vartn	F10.0, I10 2F10.0
9	Output intervals	END					2F10.0
10	Print Options						6I10
11	Packet Terminator						10A1

Exhibit IX-11. SIMULATION Packet Format for the SIMCONTROL File

3. SPREP Sample Input and Output

Exhibit IX-12 is a listing of an input deck used to create a SIMCONTROL file. Exhibit IX-13 is the printout that was generated by SPREP; it first lists the values on the input cards as they are read in, and then shows these values put out to the SIMCONTROL file.

```

CONTROL
SIMCONTROL
RAPS TEST RUN CONTROLS FOR JUNE-JULY 1978
END
SIMULATION
RAPS 4-KM DAY 195 -- 4-HR RUN 07/13/76 C-BOND II 8-79
76195 0500 76195 0900 T T T
F F
.5 1.
.1 1
.003 20 .01 .01
1. 1.
1 1 1 1
END

```

```

CONTROL
SIMCONTROL
RAPS TEST RUN CONTROLS FOR JUNE-JULY 1978
END
SIMULATION
RAPS 4-KM DAY 195 -- 4-HR RUN 07/13/76 C-BOND II 8-79
76195 500 76195 900 F T T T
F T T T
F
5.0000-001 1.0000+000
1.0000-001 1
3.0000-003 20 1.0000-002 1.0000-002
1.0000+000 1.0000+000 1 1 0 0
1 1 1 1 0 0
END

```

Exhibit IX-13. Sample SPREP Output for
the SIMCONTROL File

***** SIMCONTROL FILE *****

FILE DESCRIPTION HEADER RECORD
 FILE TYPE = SIMCONTROL
 FILE ID = RAPS TEST RUN CONTROLS FOR JUNE-JULY 1978
 NO OF SEGMENTS = 0
 NO OF SPECIES = 0
 BEG DATE = 0
 BEG TIME = 0.
 END DATE = 0
 END TIME = 0.

SIMULATION CONTROLS RECORD
 RUN ID = RAPS 4-KM DAY 195 -- 4-HR RUN 07/13/76 C-BOND II 8-79

BEG DATE = 76195
 BEG TIME = 5.00
 END DATE = 76195
 END TIME = 9.00

RESTART FLAG = F
 SINK FLAG = T
 PTS FLAG = T
 RMY FLAG = F
 TEMP FLAG = T
 TERR FLAG = T

CONC VAR FLAG = F
 DEF ROUGHNESS = .5000
 DEF VEGETAT'N = 1.0000

MAX TIME SLICE = .1000
 MAX STEPS = 1

MIN STEP SIZE = .0030
 MAX ITERS = 20
 ERR TOL = .010000
 DARK CRITERION = .0100

INST INTERVAL = 1.00
 AVG INTERVAL = 1.00

PRINT OPTIONS = 1
 1
 1
 1
 1
 0
 0

DBRPT PRINT\$

X AIRSHED SIMULATION

After all the input data files have been prepared as described in the preceding chapters, running the Airshed Simulation Program is simply a matter of properly assigning all the input files and arranging to save all the desired output files. That is, running the simulation is primarily a job control function, since the bulk of the input and output processing is performed outside of this step.

This chapter discusses job control in terms of input, scratch, and output files; describes and presents samples of the printed output; and discusses the error messages generated by the program. Also included is a worksheet that can be used to keep track of files.

A. JOB CONTROL

Figure X-1 shows the information flow for the Airshed Simulation Program. (Each group of files is discussed in more detail later.) Dotted lines indicate a possible creation of the SIMCONTROL file in a separate job step, and a possible restart using a previously generated output INSTANT file as an input AIRQUALITY file. Because the actual job control statements required are highly dependent on a particular implementation or computer, they are not specified here, but should be developed by the computer personnel who implement the system.

Tables X-1, X-2, and X-3 show the FORTRAN unit assignments of the Airshed Simulation Program's input, scratch, and output files, respectively. Currently, these unit assignments are compiled in the program by data statements in the subprogram BLKDAT. For instructions on changing the assignments, see Section VII.H. of the Systems Manual. The local file designation that corresponds to each data file should be entered in the tables for each specific implementation:




Figure X-1. Information Flow Diagram for the Airshed Simulation Program

Table X-1. Input File Assignments

<u>File Name</u>	<u>Unit No.</u>	<u>LBL lfn*</u>	<u>Optional File</u>	<u>File Closed During Simulation</u>
AIRQUALITY	3	AIRQ		✓
BOUNDARY	11	BOUND		
DIFFBREAK	12	DIFBK		
EMISSIONS	13	EMISS		
METSCALARS	7	METS		
PTSOURCE	14	POINTS	✓	
REGIONTOP	15	REGTOP		
ROADWAY	16	ROAD	✓	
TEMPERATUR	17	TEMP	✓	
TERRAIN	4	TERAIN	✓	✓
TOPCONC	18	TOPCON		
WIND	19	WIND		
CHEMPARAM	2	CPARAM		✓
SIMCONTROL	1	SIMCTL		✓

* "lfn" means local file name.

Table X-2. Scratch File Assignments

<u>File Name</u>	<u>Unit No.</u>	<u>LBL lfn</u>	<u>Optional File</u>	<u>File Closed During Simulation</u>
INTERINST	30	TAPE30		
BON1	37	†	*	
BON2	38	†	*	
CON1	33	TAPE33	*	
CON2	34	TAPE34		
CUM1	35	TAPE35	*	
CUM2	36	TAPE36		
SEG1	31	TAPE31	*	
SEG2	32	TAPE32		

* Not used for runs with only one segment.

† The LBL system utilizes large core memory instead of these files; UNIVAC uses extended memory.

Table X-3. Output File Assignments

<u>File Name</u>	<u>Unit No.</u>	<u>LBL lfn</u>	<u>Optional File</u>	<u>File Closed During Simulation</u>
AVERAGE	21	AVERAG	✓	
INSTANT	22	INST	✓	
VARIATION	23	CONVAR	✓	
Execution Trace	6	OUTPUT		

- > For the LBL CDC 7600 system, six-character mnemonic names are used instead of "TAPEnn."
- > For the UNIVAC 1100 systems, the internal file names are the unit numbers themselves.
- > For IBM systems, the DD names are of the form "FTnnF001."

1. Input Files

Table X-1 lists fourteen input files--twelve M.E.B. files and two control files. Four of the M.E.B. files are optional: PTSOURCE, ROADWAY, TEMPERATUR, and TERRAIN; all other input files must be present. For more information on selecting input file options and providing default values for the data omitted, see the Section IX.B on preparation of the SIMCONTROL file.

2. Scratch Files

Table X-2 shows the nine scratch files that might be used by the simulation. The actual number of files used and the method of assigning them are governed by the particular implementation of the system. For example, at LBL, only seven of the files are used, and the other two are represented by vectors in large core memory. See Section VII.B of the Systems Manual for more detailed information on the scratch files.

3. Output Files

As shown in Table X-3, the Airshed Simulation Program can write up to three binary data files, which are described in detail in Chapter IX of the Systems Manual. The presence or absence of these files is determined by parameters on the SIMCONTROL file:

- > AVERAGE will be written if the averaging interval is less than 99.0 hours.
- > INSTANT will be written at the beginning of the simulation, at the instantaneous output interval, and also at the end of each averaging interval if that time does not coincide with an instantaneous output time. If both the instantaneous output interval and the averaging interval are greater than 99.0 hours, INSTANT will not be written at all.
- > VARIATION will be written if the concentration variation option is TRUE and the averaging interval is less than 99.0 hours.

B. PRINTED OUTPUT

The printed output from the simulation program appears on the Execution Trace file--ordinarily the standard print unit--and always contains at least the following information:

- > A complete display of the contents of the SIMCONTROL and CHEMPARAM files.
- > The region description as specified on the BOUNDARY file. This description serves as the standard for the run: the horizontal grid parameters on all other spatially varying files and the vertical distribution parameters on all other vertically varying files must match those of the BOUNDARY file.
- > The header information from each M.E.B. file. If the files were uniquely identified at the times they were created, this information completely defines all data input to the run.
- > A message when each non-time-varying file is closed.
- > A message at the end of each time slice indicating elapsed CPU time (if the host computer provides the capability).
- > A message at the termination of the run.

As indicated on the SIMCONTROL file, additional printed output options are also available that are primarily useful for debugging:

- > The file history printout consists of a message printed whenever a time interval record is read from any file. During early simulation runs, this information can help the user follow the progress of the run.
- > The storage allocation printout consists of tables listing pointers to scratch storage. Each entry is the relative location of a data array in a single storage vector. To interpret these tables, see Section VII.B of the Systems Manual.
- > Instantaneous and average concentration arrays may be printed at the same time they are written on the files. They are printed by segments, within each segment by species, and within each species by vertical level. These printouts contain values in the boundary cells that do not necessarily represent the actual boundary values at the time; thus, they should be used only for program debugging or for preliminary runs for which the binary output files are not to be saved.

Exhibit X-1 is an annotated excerpt of the output from a successful Airshed Simulation Program run that contains samples of all the normal and optional information printed.

If the Airshed Simulation Program is unable to perform the chemistry step successfully for any cell, it will give a "crash printout," showing the values in all data arrays in the vicinity of the cell where the error occurred. Also included are the values in the local vectors used by the simulation. A sample of the crash printout is shown in Exhibit X-2. The user should examine this printout and look for anomalous values of

***** SIMCONTROL FILE *****

FILE DESCRIPTION HEADER RECORD

FILE TYPE = SIMCONTROL
FILE ID = RAPS TEST RUN CONTROLS FOR JUNE-JULY 1978
NO OF SEGMENTS = 0
NO OF SPECIES = 0
BEG DATE = 0
BEG TIME = 0.
END DATE = 0
END TIME = 0.

SIMULATION CONTROLS RECORD

RUN ID = RAPS 4-KM DAY 195 -- 4-HR RUN 07/13/76 C-BOND II 8-79
BEG DATE = 76195
BEG TIME = 5.00
END DATE = 76195
END TIME = 9.00

RESTART FLAG = F
SINK FLAG = T
PTS FLAG = T
RMY FLAG = F
TEMP FLAG = T
TERR FLAG = T

CONC VAR FLAG = F

DEF ROUGHNESS = .5000
DEF VEGETAT'N = 1.0000

MAX TIME SLICE = .1000
MAX STEPS = 1

MIN STEP SIZE = .0030
MAX ITERS = 20
ERROR TOL = .010000
DARK CRITERION = .0100

INST INTERVAL = 1.00
AVG INTERVAL = 1.00

FILE HISTORY = 1
STORAGE ALLOC = 1
LFVELS INST = 1
LEVELS AVG = 1
CONC VAR = 0
OPT 3 = 0

FILE 1 SIMCONTROL CLOSED.

***** CHEMPARAM FILE *****

FILE DESCRIPTION HEADER RECORD

FILE TYPE = CHEMPARAM
FILE ID = CHEMISTRY PARAMETERS NEW CHEM HIGHER PARAFINS LOWER LIMT
NO OF SEGMENTS = 0
NO OF SPECIES = 11
BEG DATE = 0
END DATE = 0
END TIME = 0

SPECIES DESCRIPTION HEADER RECORD

NO
NO2
O3
ETH
OLE
PAR
CARB
APO
BZA
PAN
CO

CHEMISTRY DEFINITION RECORD

MECHANISM ID = CARBON BOND MECHANISM -- NOVEMBER 78
NO OF REACTIONS = 69
NO OF COEFFS = 4

SPECIES PARAMETERS RECORD

SPEC NAME	REACT	SSIC	SSBC	DVRES	LOW BD SS	UP BD SS	LOW BD NUM	UP BD NUM
NO	T	F	F	2.8000+001	1.0000-005	1.0000+006	1.0000-005	1.0000+006
NO2	T	F	F	1.1100-002	1.0000-004	1.0000+006	1.0000-004	1.0000+006
O3	T	T	T	1.4700-002	1.0000-009	1.0000+006	1.0000-009	1.0000+006
ETH	T	F	F	1.0000+010	1.0000-006	1.0000+006	1.0000-006	1.0000+006
OLE	T	F	F	1.0000+010	1.0000-006	1.0000+006	1.0000-006	1.0000+006
PAR	T	F	F	1.0000+010	1.0000-003	1.0000+006	1.0000-004	1.0000+006
CARB	T	F	F	1.0000+010	1.0000-006	1.0000+006	1.0000-006	1.0000+006
APO	T	F	F	1.0000+010	1.0000-006	1.0000+006	1.0000-006	1.0000+006
BZA	T	F	F	1.0000+010	1.0000-006	1.0000+006	1.0000-006	1.0000+006
PAN	T	F	F	1.0000+010	1.0000-006	1.0000+006	1.0000-006	1.0000+006
CO	T	F	F	1.0000+010	1.0000-002	1.0000+006	1.0000-002	1.0000+006

REACTION PARAMETERS RECORD

RATE CONST	PHOTOL	TEMP	ACT ENERGY	REF TEMP
1 6.0000+001	T	F	.0000	.0000
2 2.6400+008	F	F	.0000	.0000
3 1.4340+003	F	T	1.4500+003	2.9600+002
4 2.8000+000	F	T	2.4500+003	2.9800+002
5 8.0400+005	F	F	.0000	.0000
6 4.6200+003	F	T	1.0000+003	2.9800+002
7 3.0000+002	F	T	1.5250+003	2.9800+002
8 8.0000+005	F	F	.0000	.0000
9 2.6400+004	F	F	.0000	.0000

10	9.0000-003	F	F	.0000	.0000
11	1.6800+006	F	F	.0000	.0000
12	9.0000-003	F	T	-1.0600+004	2.9300+002
13	7.2000+005	F	F	.0000	.0000
14	9.0000+005	F	F	.0000	.0000
15	1.2000+003	F	F	.0000	.0000
16	9.0000+004	F	F	.0000	.0000
17	1.6200+005	F	F	.0000	.0000
18	1.6200+005	F	F	.0000	.0000
19	2.5200+006	F	F	.0000	.0000
20	4.8000-001	F	F	.0000	.0000
21	4.8000-001	F	F	.0000	.0000
22	3.6000+004	F	F	.0000	.0000
23	3.6000+004	F	F	.0000	.0000
24	7.2000+005	F	F	.0000	.0000
25	1.4400-001	F	F	.0000	.0000
26	2.2800+005	F	F	.0000	.0000
27	7.2000+005	F	F	.0000	.0000
28	7.2000+005	F	F	.0000	.0000
29	2.3000+005	F	F	.0000	.0000
30	4.6000+005	F	F	.0000	.0000
31	3.0000+004	F	F	.0000	.0000
32	3.0000+002	F	F	.0000	.0000
33	1.2000+004	F	F	.0000	.0000
34	3.0000+002	F	F	.0000	.0000
35	1.1400+006	F	F	.0000	.0000
36	8.1000-002	T	F	.0000	.0000
37	1.2150-001	T	F	.0000	.0000
38	6.0000+006	F	F	.0000	.0000
39	1.2000+005	F	F	.0000	.0000
40	1.6800+000	F	T	1.2500+004	2.9300+002
41	2.4000+005	F	F	.0000	.0000
42	2.4000+005	F	F	.0000	.0000
43	7.2000+005	F	F	.0000	.0000
44	4.8000+005	F	F	.0000	.0000
45	1.2000+005	F	F	.0000	.0000
46	7.2000+005	F	F	.0000	.0000
47	4.8000+005	F	F	.0000	.0000
48	1.2000+005	F	F	.0000	.0000
49	4.0200+004	F	F	.0000	.0000
50	1.4400+004	F	F	.0000	.0000
51	5.4000+003	F	F	.0000	.0000
52	9.0000+003	F	F	.0000	.0000
53	2.0400+004	F	F	.0000	.0000
54	2.5500+004	F	F	.0000	.0000
55	5.1000+003	F	F	.0000	.0000
56	3.6000+005	F	F	.0000	.0000
57	9.6000+004	F	F	.0000	.0000
58	9.0000+005	F	F	.0000	.0000
59	6.0000+006	F	F	.0000	.0000
60	1.0000+003	F	F	.0000	.0000
61	9.0000+002	F	F	.0000	.0000

Exhibit X-1 (Continued)

62	2.1000+006	F	F	.0000	.0000
63	3.6000+001	F	F	.0000	.0000
64	6.0000+005	F	F	.0000	.0000
65	2.1600+000	T	F	.0000	.0000
66	5.4000+004	F	F	.0000	.0000
67	4.8000+004	F	F	.0000	.0000
68	5.4000+005	F	F	.0000	.0000
69	3.0000-002	F	F	.0000	.0000

STOICHIOMETRIC COEFFICIENTS RECORD

ALPHA 5.0000-001
 BETA 4.8000-001
 GAMMA 1.0000+000
 ETA 1.0000-001

FILE 2 CHEMPARAM CLOSED.

Exhibit X-1 (Continued)

LOCAL POINTERS

1 1
2 5
3 9
4 13
5 17
6 21
7 25
8 36
9 47
10 168
11 185
12 202
13 219
14 236
15 253
16 168
17 172
18 177
19 188
20 232
21 237
22 248
23 253
24 269
25 285
26 289
27 253
28 257
29 261
30 265
31 269
32 273
33 278
34 282
35 253
36 264
37 275
38 286
39 407
40 418

BOUNDARY INDEX TABLE FOR SEGMENT 1

ROW	0	WEST	0	EAST	0
1	0	0	0	0	0
2	2	0	0	16	0
3	2	0	0	16	0
4	2	0	0	16	0
5	2	0	0	16	0
6	2	0	0	16	0
7	2	0	0	16	0
8	2	0	0	16	0
9	2	0	0	16	0
10	2	0	0	16	0
11	2	0	0	16	0
12	2	0	0	16	0
13	2	0	0	16	0
COL					
1	0	SOUTH	0	NORTH	0
2	2	0	11	2	36
3	2	0	11	2	37
4	2	0	11	2	38
5	2	0	11	2	39
6	2	0	11	2	40
7	2	0	11	2	41
8	2	0	11	2	42
9	2	0	11	2	43
10	2	0	11	2	44
11	2	0	11	2	45
12	2	0	11	2	46
13	2	0	11	2	47
14	2	0	11	2	48
15	2	0	11	2	49
16	2	0	11	2	50
17	0	0	0	0	0

BOUNDARY INDEX TABLE FOR SEGMENT 2

ROW		WEST		EAST	
1	2	0	0	16	0
2	2	0	0	16	0
3	2	0	0	16	0
4	2	0	0	16	0
5	2	0	0	16	0
6	2	0	0	16	0
7	2	0	0	16	0
8	2	0	0	16	0
9	2	0	0	16	0
10	2	0	0	16	0
11	2	0	0	16	0
12	2	0	0	16	0
13	0	0	0	0	0
COL		SOUTH		NORTH	
1	0	0	0	0	0
2	3	1	172	12	0
3	3	1	173	12	0
4	3	1	174	12	0
5	3	1	175	12	0
6	3	1	176	12	0
7	3	1	177	12	0
8	3	1	178	12	0
9	3	1	179	12	0
10	3	1	180	12	0
11	3	1	181	12	0
12	3	1	182	12	0
13	3	1	183	12	0
14	3	1	184	12	0
15	3	1	185	12	0
16	3	1	186	12	0
17	0	0	0	0	0

Exhibit X-1 (Continued)

RAPS 4-KM DAY 195 -- 4-HR RUN 07/13/76 C-80ND II 0-79

***** REGION DESCRIPTION *****

HORIZONTAL GRID	X	Y
REFERENCE ORIGIN (UTM - METERS)	725000.	4252000. (ZONE 15)
REGION ORIGIN (M FROM REF. ORG.)	-19000.	-16000.
CELL SPACING (M)	4000.	4000.
NUMBER OF CELLS	17	22

VERTICAL DISTRIBUTION

NO. CELLS IN LOWER LAYER = 2

NO. CELLS IN UPPER LAYER = 2

SURFACE LAYER HT (M) = 0.

MIN HT LOWER LAYER CELLS (M) = 50.

MIN HT UPPER LAYER CELLS (M) = 200.

TOTAL NO. VERTICAL CELLS = 4

SEGMENTS	IORGX	IORGY	NOX	NOY
1	0	0	17	13
2	0	9	17	13

BEGINNING OF TABLES RELATIVE TO BEGINNING OF AVAILABLE SPACE

SEGMENT	1
LOCAL	131
BOUNDARY	559
SEG SCRATCH	2295
LAST WORD	22756

SEGMENT ALLOCATION TABLE

1	1	2
2	0	0
3	0	9
4	17	17
5	13	13
6	80	129
7	0	0
8	221	221
9	884	884
10	9724	9724
11	2431	2431
12	1736	1736
13	1	1337
14	9724	9724
15	0	9724
16	9724	9724
17	0	9724
18	10101	10738
19	0	10101
20	0	0
21	0	0
22	0	0
23	0	0
24	0	0
25	0	0
26	0	0
27	0	0
28	0	0
29	1	1
30	1	1
31	1	1
32	1	0
33	0	1
34	1	1
35	53	53
36	105	105
37	173	173
38	0	0
39	0	0
40	0	241
41	241	0
42	1	1
43	1	1
44	885	885
45	2432	2432

46	2653	2653
47	2874	2874
48	3095	3095
49	3316	3316
50	3537	3537
51	3758	3758
52	3979	3979
53	4200	4200
54	5084	5084
55	5968	5968
56	6189	6189
57	6410	6410
58	6631	6631
59	0	0
60	0	0
61	9062	9062
62	9142	9191
63	9222	9320
64	10102	10739
65	0	0

FILE - AIRQUALITY ID = INITIAL POLLUTANT CONCENTRATIONS ST LOUIS 500 76195
 SEGMENTS = 2 SPECIES = 11
 TIME SPAN = 76195 5.00 TO 76195 5.02
 725000.42-2000. 15 -19000. -16000. 4000. 17 22 4 2 2 .00 50.00 200.00

SEGMENTS
 0 0 17 13
 0 9 17 13

SPECIES ON AIRQUALITY FILE
 NO. NAME NO. WITHIN RUN
 1 NO 1
 2 NO2 2
 3 O3 3
 4 ETH 4
 5 OLE 5
 6 PAR 6
 7 CARB 7
 8 ARO 8
 9 BZA 9
 10 PAN 10
 11 CO 11
 FILSKP READS TIME INTERVAL 76195 5.00 76195 5.02 ON UNIT 3

FILE = BOUNDARY ID = BOUNDARY DEFINITION AND CONCENTRATIONS
 SEGMENTS = 2 SPECIES = 11
 TIME SPAN = 76195 5.00 TO 76195 24.00
 725000.4252000. 15 -19000. -16000. 4000. 17 22 4 2 2 .00 50.00 200.00

SEGMENTS
 0 0 17 13
 0 9 17 13

SPECIES ON BOUNDARY FILE
 NO. NAME NO. WITHIN RUN
 1 NO 1
 2 NO2 2
 3 O3 3
 4 ETH 4
 5 OLE 5
 6 PAR 6
 7 CARB 7
 8 ARO 8
 9 BZA 9
 10 PAN 10
 11 CO 11
 FILSKP READS TIME INTERVAL 76195 5.00 76195 6.00 ON UNIT 11

FILE = DIFFBREAK ID = HEIGHT OF THE MIXED LAYER
 SEGMENTS = 2 SPECIES = 0
 TIME SPAN = 76195 5.00 TO 76195 24.00
 725000.4252000. 15 -19000. -16000. 4000. 17 22 0 2 2 .00 50.00 200.00

SEGMENTS
 0 0 17 13
 0 9 17 13
 FILSKP READS TIME INTERVAL 76195 5.00 76195 6.00 ON UNIT 12

FILE = EMISSIONS ID = RAPS EMISSIONS (17 X 22) DAY195 07/13/76
 SEGMENTS = 2 SPECIES = 8
 TIME SPAN = 76195 5.00 TO 76195 24.00
 725000.4252000. 15 -19000. -16000. 4000. 17 22 0 2 2 .00 50.00 200.00

SEGMENTS
 0 0 17 13
 0 9 17 13

SPECIES ON EMISSIONS FILE
 NO. NAME NO. WITHIN RUN
 1 NO 1
 2 NO2 2
 3 ETH 4
 4 OLE 5
 5 PAR 6
 6 CARB 7
 7 ARO 8
 8 CO 11
 FILSKP READS TIME INTERVAL 76195 5.00 76195 6.00 ON UNIT 13

FILE = METSCALARS ID = VALUES FOR METEOROLOGICAL SCALARS
 SEGMENTS = 0 SPECIES = 0
 TIME SPAN = 76195 4.00 TO 76195 24.00
 725000.4252000. 15 -19000. -16000. 4000. 17 22 4 2 2 .00 50.00 200.00

FILSKP READS TIME INTERVAL 76195 4.00 76195 5.00 ON UNIT 7

TGRADBELOW TGRADABOVE EXPCCLASS RADFACTOR CONCWATER ATMOSPRESS
 -.010 .004 -1.000 .008 12687.000 .990
 FILSKP READS TIME INTERVAL 76195 5.00 76195 6.00 ON UNIT 7

FILE = PTSOURCE ID = POINT SOURCES FOR ST. LOUIS 76195 4X4 GRID
 SEGMENTS = 2 SPECIES = 7
 TIME SPAN = 76195 5.00 TO 76195 24.00
 725000.4252000. 15 -19000. -16000. 4000. 17 22 4 2 2 .00 50.00 200.00

SEGMENTS

0 0 17 13
 0 9 17 13

SPECIES ON PTSOURCE FILE
 NO. NAME NO. WITHIN RUN

1 NO 1
 2 NO2 2
 3 OLE 5
 4 PAR 6
 5 CARB 7
 6 ARO 8
 7 CO 11

FILSKP READS TIME INTERVAL 76195 5.00 76195 6.00 ON UNIT 14

FILE = REGIONTOP ID = HEIGHT OF THE TOP OF THE MODELING REGION
 SEGMENTS = 2 SPECIES = 0
 TIME SPAN = 76195 5.00 TO 76195 24.00
 725000.4252000. 15 -19000. -16000. 4000. 17 22 0 2 2 .00 50.00 200.00

SEGMENTS

0 0 17 13
 0 9 17 13

FILSKP READS TIME INTERVAL 76195 5.00 76195 6.00 ON UNIT 15

FILE = TEMPERATUR ID = TEMPERATURE FIELD FOR ST. LOUIS DAY 195
 SEGMENTS = 2 SPECIES = 0
 TIME SPAN = 76195 5.00 TO 76195 24.00
 725000.4252000. 15 -19000. -16000. 4000. 17 22 0 2 2 .00 50.00 200.00

SEGMENTS

0 0 17 13
 0 9 17 13

FILSKP READS TIME INTERVAL 76195 5.00 76195 6.00 ON UNIT 17

FILE = TERRAIN ID = SURFACE ROUGHNESS AND VEGETATIVE FACTORS
 SEGMENTS = 2 SPECIES = 0
 TIME SPAN = 76195 5.00 TO 76195 24.00
 725000.4252000. 15 -19000. -16000. 4000. 17 22 0 2 2 .00 50.00 200.00

SEGMENTS
0
0

0 17 13
9 17 13

FILE = TOPCONC ID = POLLUTANT CONCENTRATIONS ABOVE THE MODELING REGION
SEGMENTS = 2 SPECIES = 11
TIME SPAN = 76195 5.00 TO 76195 24.00
725000.4252000. 15 -19000. -16000. 4000. 17 22 0 2 2 .00 50.00 200.00

SEGMENTS
0
0

0 17 13
9 17 13

SPECIES ON TOPCONC FILE
NO. NAME NO. WITHIN RUN

1 NO 1
2 NO2 2
3 O3 3
4 ETH 4
5 OLE 5
6 PAR 6
7 CARB 7
8 ARO 8
9 BZA 9
10 PAN 10
11 CO 11

FILSKP READS TIME INTERVAL 76195 .00 76195 24.00 ON UNIT 18

FILE = WIND ID = WIND FIELD FOR ST. LOUIS DIVERGENCE ALGORITHM USED
SEGMENTS = 2 SPECIES = 0
TIME SPAN = 76195 5.00 TO 76195 24.00
725000.4252000. 15 -19000. -16000. 4000. 17 22 4 2 2 .00 50.00 200.00

SEGMENTS
0
0

0 17 13
9 17 13

FILSKP READS TIME INTERVAL 76195 5.00 76195 6.00 ON UNIT 19

TGRADBELOW TGRADABOVE EXPCCLASS RADFACTOR CONCHWATER ATMOSPRESS
-.010 .004 .000 .084 12687.000 .990

FILE 4 TERRAIN CLOSED.

TZERO READS TIME INTERVAL 76195 6.00 76195 7.00 ON UNIT 12 DIFFBREAK
TZERO READS TIME INTERVAL 76195 6.00 76195 7.00 ON UNIT 15 REGIONTOP

Exhibit X-1 (Continued)

FILE 3 AIRQUALITY CLOSED.

76195	5.00	SEG	1	MXMAX	MYMAX	DTHAX	DT	NDT		
			2	22453.	9603.	.089	.089	1		
				22453.	9603.	.089	.089	1		
TIME =	76195	5.089		SLICE =	.0891	ELAPSED CPU TIME =	.000 SECS	TOTAL ELAPSED CPU TIME =	.000 SECS	
76195	5.09	SEG	1	MXMAX	MYMAX	DTHAX	DT	NDT		
			2	22453.	9603.	.089	.089	1		
				22453.	9603.	.089	.089	1		
TIME =	76195	5.178		SLICE =	.0891	ELAPSED CPU TIME =	.000 SECS	TOTAL ELAPSED CPU TIME =	.000 SECS	
76195	5.18	SEG	1	MXMAX	MYMAX	DTHAX	DT	NDT		
			2	22453.	9603.	.089	.089	1		
				22453.	9603.	.089	.089	1		
TIME =	76195	5.267		SLICE =	.0891	ELAPSED CPU TIME =	.000 SECS	TOTAL ELAPSED CPU TIME =	.000 SECS	
76195	5.27	SEG	1	MXMAX	MYMAX	DTHAX	DT	NDT		
			2	22453.	9603.	.089	.089	1		
				22453.	9603.	.089	.089	1		
TIME =	76195	5.356		SLICE =	.0891	ELAPSED CPU TIME =	.000 SECS	TOTAL ELAPSED CPU TIME =	.000 SECS	
76195	5.36	SEG	1	MXMAX	MYMAX	DTHAX	DT	NDT		
			2	22453.	9603.	.089	.089	1		
				22453.	9603.	.089	.089	1		
TIME =	76195	5.445		SLICE =	.0891	ELAPSED CPU TIME =	.000 SECS	TOTAL ELAPSED CPU TIME =	.000 SECS	
76195	5.45	SEG	1	MXMAX	MYMAX	DTHAX	DT	NDT		
			2	22453.	9603.	.089	.089	1		
				22453.	9603.	.089	.089	1		
TIME =	76195	5.534		SLICE =	.0891	ELAPSED CPU TIME =	.000 SECS	TOTAL ELAPSED CPU TIME =	.000 SECS	
76195	5.53	SEG	1	MXMAX	MYMAX	DTHAX	DT	NDT		
			2	22453.	9603.	.089	.089	1		
				22453.	9603.	.089	.089	1		
TIME =	76195	5.624		SLICE =	.0891	ELAPSED CPU TIME =	.000 SECS	TOTAL ELAPSED CPU TIME =	.000 SECS	
76195	5.62	SEG		MXMAX	MYMAX	DTHAX	DT	NDT		

1	22453.	9603.	.089	.089	1			
2	22453.	9603.	.089	.089	1			
TIME = 76195 5.713 SLICE = .0891 ELAPSED CPU TIME = .000 SECS TOTAL ELAPSED CPU TIME = .000 SECS								
76195 5.71	SEG	WXMAX	DTMAX	DT	NDT			
1	22453.	9603.	.089	.089	1			
2	22453.	9603.	.089	.089	1			
TIME = 76195 5.802 SLICE = .0891 ELAPSED CPU TIME = .000 SECS TOTAL ELAPSED CPU TIME = .000 SECS								
76195 5.80	SEG	WXMAX	DTMAX	DT	NDT			
1	22453.	9603.	.089	.089	1			
2	22453.	9603.	.089	.089	1			
TIME = 76195 5.891 SLICE = .0891 ELAPSED CPU TIME = .000 SECS TOTAL ELAPSED CPU TIME = .000 SECS								
76195 5.89	SEG	WXMAX	DTMAX	DT	NDT			
1	22453.	9603.	.089	.089	1			
2	22453.	9603.	.089	.089	1			
TIME = 76195 5.980 SLICE = .0891 ELAPSED CPU TIME = .000 SECS TOTAL ELAPSED CPU TIME = .000 SECS								
76195 5.98	SEG	WXMAX	DTMAX	DT	NDT			
1	22453.	9603.	.089	.020	1			
2	22453.	9603.	.089	.020	1			
TIME = 76195 6.000 SLICE = .0202 ELAPSED CPU TIME = .000 SECS TOTAL ELAPSED CPU TIME = .000 SECS								

AVG CONCENTRATIONS AT 76195 6.00 FOR SPECIES 1 NO												
SEGMENT= 1 LEVEL=1												
	1	2	3	4	5	6	7	8	9	10	11	12
	13	14	15	16	17							
13	8.44-004	5.04-003	3.31-003	4.85-003	4.08-003	2.75-003	3.18-003	3.95-003	4.13-003	1.87-003	1.28-003	4.01-004
	4.22-004	5.02-004	4.38-004	3.56-004	3.19-004							
12	8.45-004	1.48-002	5.33-003	5.07-003	5.01-003	3.73-003	5.43-003	6.32-003	5.77-003	3.48-003	7.91-004	6.04-004
	5.06-004	4.47-004	2.98-004	2.74-004	3.20-004							
11	8.47-004	5.29-003	9.43-003	8.66-003	5.13-003	4.94-003	7.93-003	1.18-002	1.24-002	3.61-003	1.33-003	5.41-004
	4.66-004	3.19-004	3.77-004	3.18-004	3.20-004							
10	8.48-004	2.38-003	4.72-003	4.76-003	4.03-003	3.34-003	3.62-003	2.89-003	2.21-003	1.78-003	1.35-003	4.64-004
	5.56-004	4.52-004	5.52-004	5.00-004	3.21-004							
9	8.50-004	1.45-003	2.57-003	4.12-003	4.34-003	2.72-003	2.48-003	2.56-003	2.23-003	4.71-004	4.17-004	4.99-004
	6.03-004	7.12-004	6.07-004	4.27-004	3.22-004							
8	8.51-004	1.15-003	1.48-003	1.99-003	2.94-003	3.52-003	3.25-003	1.15-003	5.71-004	4.51-004	2.87-004	3.09-004
	4.08-004	6.75-004	7.37-004	4.88-004	3.22-004							
7	8.53-004	8.15-004	8.88-004	1.05-003	1.31-003	1.81-003	1.44-003	1.23-003	4.94-004	4.00-004	2.79-004	2.87-004
	3.02-004	3.71-004	4.63-004	5.07-004	3.23-004							
6	8.54-004	4.91-004	6.41-004	8.83-004	1.14-003	1.46-003	5.81-004	5.00-004	4.34-004	4.55-004	3.41-004	2.93-004
	3.05-004	3.64-004	4.10-004	4.14-004	3.23-004							
5	8.56-004	4.07-004	5.30-004	7.01-004	8.49-004	1.52-003	5.45-004	4.00-004	3.29-004	2.98-004	3.13-004	2.72-004
	3.08-004	3.55-004	3.94-004	4.17-004	3.24-004							
4	8.57-004	3.25-004	4.37-004	5.52-004	8.59-004	1.59-003	4.73-004	3.34-004	3.07-004	2.96-004	3.33-004	2.56-004
	2.91-004	3.36-004	3.75-004	3.85-004	3.25-004							
3	8.59-004	2.62-004	3.38-004	4.93-004	1.18-003	4.14-003	2.68-004	2.89-004	3.01-004	3.05-004	3.60-004	2.55-004
	2.71-004	3.09-004	3.40-004	3.40-004	3.25-004							
2	3.01-004	2.56-004	3.07-004	3.43-004	5.22-004	7.81-004	2.69-004	2.95-004	2.95-004	2.88-004	2.78-004	2.75-004
	2.67-004	2.77-004	2.95-004	3.12-004	3.26-004							
1	2.00-003	3.03-004	3.05-004	3.06-004	3.08-004	3.09-004	3.11-004	3.12-004	3.14-004	3.15-004	3.17-004	3.18-004
	3.20-004	3.22-004	3.23-004	3.25-004	2.00-003							

AVG CONCENTRATIONS AT 76195 6.00 FOR SPECIES 2 NO2												
SEGMENT= 1 LEVEL=1												
	1	2	3	4	5	6	7	8	9	10	11	12
	13	14	15	16	17							
13	9.16-003	1.76-002	1.89-002	2.41-002	2.45-002	2.07-002	2.07-002	2.13-002	2.05-002	1.52-002	1.25-002	7.28-003
	6.64-003	6.24-003	5.03-003	4.01-003	3.68-003							
12	9.15-003	2.27-002	2.03-002	2.24-002	2.34-002	2.14-002	2.36-002	2.48-002	2.48-002	2.17-002	1.06-002	8.43-003
	6.68-003	5.65-003	4.26-003	3.67-003	3.68-003							
11	9.15-003	1.69-002	2.26-002	2.40-002	2.17-002	2.17-002	2.51-002	2.90-002	3.09-002	2.49-002	1.29-002	7.44-003
	5.95-003	4.84-003	4.75-003	3.89-003	3.68-003							
10	9.15-003	1.29-002	1.83-002	1.99-002	1.99-002	1.94-002	2.07-002	2.04-002	1.85-002	1.57-002	1.13-002	6.95-003
	6.87-003	5.82-003	5.71-003	4.63-003	3.68-003							
9	9.15-003	9.62-003	1.34-002	1.72-002	1.87-002	1.66-002	1.66-002	1.73-002	1.74-002	7.61-003	6.71-003	6.94-003
	7.30-003	7.43-003	5.89-003	4.29-003	3.68-003							
8	9.15-003	7.96-003	9.83-003	1.14-002	1.44-002	1.62-002	1.57-002	1.02-002	7.50-003	6.28-003	5.20-003	5.27-003
	5.85-003	6.96-003	6.49-003	4.61-003	3.68-003							
7	9.15-003	6.18-003	6.84-003	7.98-003	9.56-003	1.12-002	1.02-002	9.11-003	5.95-003	5.28-003	4.79-003	4.72-003
	4.66-003	4.88-003	4.87-003	4.59-003	3.68-003							
6	9.15-003	4.86-003	5.81-003	7.13-003	8.57-003	9.35-003	6.29-003	5.93-003	5.56-003	5.48-003	4.90-003	4.58-003
	4.54-003	4.89-003	4.27-003	4.17-003	3.68-003							
5	9.14-003	4.36-003	5.13-003	6.19-003	7.53-003	9.26-003	5.66-003	4.97-003	4.69-003	4.50-003	4.47-003	4.18-003
	4.26-003	4.75-003	4.30-003	4.14-003	3.68-003							

4	9.14-003	3.90-003	4.54-003	5.48-003	7.47-003	9.28-003	4.80-003	4.43-003	4.35-003	4.30-003	4.36-003	3.91-003
	4.05-003	4.18-003	3.99-003	3.68-003								
3	9.14-003	3.55-003	4.05-003	5.30-003	8.91-003	1.40-002	3.55-003	4.04-003	4.16-003	4.20-003	4.31-003	3.75-003
	3.80-003	3.92-003	3.93-003	3.79-003	3.67-003							
2	3.70-003	3.52-003	3.79-003	4.15-003	5.16-003	5.81-003	3.63-003	3.87-003	3.90-003	3.86-003	3.80-003	3.69-003
	3.52-003	3.64-003	3.66-003	3.67-003	3.67-003							
1	2.00-003	3.70-003	3.70-003	3.69-003	3.69-003	3.69-003	3.69-003	3.69-003	3.69-003	3.68-003	3.68-003	3.68-003
	3.68-003	3.68-003	3.68-003	3.68-003	2.00-003							

AVG CONCENTRATIONS AT 76195 6.00 FOR SPECIES 3 O3

SEGMENT= 1 LEVEL=1

	1	2	3	4	5	6	7	8	9	10	11	12
13	2.08-002	1.10-002	1.33-002	1.21-002	1.41-002	1.82-002	1.85-002	1.75-002	1.69-002	2.16-002	2.58-002	3.18-002
	3.16-002	3.07-002	2.98-002	2.50-002	2.43-002							
12	2.08-002	6.92-003	1.14-002	1.23-002	1.35-002	1.63-002	1.51-002	1.44-002	1.43-002	1.96-002	2.84-002	3.36-002
	3.29-002	3.15-002	2.93-002	2.52-002	2.43-002							
11	2.08-002	1.06-002	8.51-003	9.60-003	1.32-002	1.40-002	1.17-002	9.47-003	9.39-003	2.07-002	2.99-002	3.69-002
	3.62-002	3.41-002	3.02-002	2.62-002	2.43-002							
10	2.08-002	1.47-002	1.23-002	1.31-002	1.50-002	1.66-002	1.64-002	1.83-002	2.06-002	2.55-002	2.95-002	3.66-002
	3.48-002	3.35-002	2.91-002	2.54-002	2.43-002							
9	2.08-002	1.68-002	1.47-002	1.32-002	1.43-002	1.74-002	1.77-002	1.88-002	2.22-002	3.09-002	3.27-002	3.29-002
	3.22-002	3.10-002	2.83-002	2.54-002	2.43-002							
8	2.09-002	1.83-002	1.69-002	1.53-002	1.48-002	1.45-002	1.59-002	2.20-002	2.62-002	2.90-002	3.14-002	3.20-002
	3.12-002	2.92-002	2.74-002	2.53-002	2.43-002							
7	2.09-002	1.79-002	1.71-002	1.71-002	1.72-002	1.70-002	1.91-002	2.15-002	2.57-002	2.80-002	3.04-002	3.14-002
	3.09-002	2.90-002	2.55-002	2.39-002	2.43-002							
6	2.09-002	1.94-002	1.85-002	1.79-002	1.77-002	1.83-002	2.22-002	2.37-002	2.54-002	2.71-002	2.93-002	3.08-002
	3.06-002	2.94-002	2.31-002	2.35-002	2.43-002							
5	2.09-002	2.04-002	1.97-002	1.92-002	1.88-002	1.83-002	2.24-002	2.41-002	2.54-002	2.67-002	2.76-002	2.81-002
	2.73-002	2.57-002	2.41-002	2.33-002	2.43-002							
4	2.09-002	2.15-002	2.10-002	2.05-002	1.93-002	1.84-002	2.32-002	2.43-002	2.52-002	2.60-002	2.64-002	2.69-002
	2.65-002	2.56-002	2.43-002	2.33-002	2.43-002							
3	2.09-002	2.27-002	2.23-002	2.14-002	1.86-002	1.48-002	2.45-002	2.47-002	2.51-002	2.56-002	2.57-002	2.61-002
	2.59-002	2.52-002	2.41-002	2.33-002	2.43-002							
2	2.43-002	2.33-002	2.32-002	2.30-002	2.23-002	2.20-002	2.43-002	2.44-002	2.47-002	2.50-002	2.52-002	2.50-002
	2.49-002	2.45-002	2.39-002	2.33-002	2.43-002							
1	2.00-002	2.43-002	2.43-002	2.43-002	2.43-002	2.43-002	2.43-002	2.43-002	2.43-002	2.43-002	2.43-002	2.43-002
	2.43-002	2.43-002	2.43-002	2.43-002	2.00-002							

AVG CONCENTRATIONS AT 76195 6.00 FOR SPECIES 4 ETH

SEGMENT= 1 LEVEL=1

	1	2	3	4	5	6	7	8	9	10	11	12
13	1.71-003	5.07-003	6.97-003	9.06-003	9.41-003	6.57-003	5.67-003	5.38-003	4.87-003	2.99-003	2.39-003	1.98-003
	1.94-003	1.96-003	1.64-003	1.10-003	1.09-003							
12	1.71-003	4.86-003	5.59-003	6.55-003	6.84-003	6.18-003	6.41-003	6.34-003	5.47-003	4.16-003	2.55-003	2.44-003
	2.15-003	1.94-003	1.41-003	1.06-003	1.09-003							
11	1.71-003	4.09-003	5.25-003	5.35-003	5.52-003	5.66-003	6.80-003	6.89-003	6.40-003	5.36-003	4.04-003	2.85-003
	2.25-003	1.72-003	1.53-003	1.18-003	1.09-003							
10	1.71-003	3.65-003	4.62-003	4.95-003	4.68-003	4.73-003	4.77-003	4.20-003	3.39-003	2.98-003	2.70-003	2.79-003
	2.71-003	2.20-003	2.07-003	1.57-003	1.09-003							
9	1.71-003	2.44-003	2.94-003	3.73-003	4.38-003	4.05-003	3.85-003	3.35-003	2.40-003	2.11-003	2.18-003	2.37-003
	2.56-003	2.62-003	2.09-003	1.33-003	1.09-003							
8	1.71-003	1.64-003	2.08-003	2.57-003	3.36-003	3.75-003	3.64-003	2.41-003	1.66-003	1.72-003	1.47-003	1.55-003

7	1.63-003	2.40-003	2.31-003	1.39-003	1.09-003	2.53-003	2.16-003	1.78-003	1.61-003	1.32-003	1.35-003
	1.71-003	1.49-003	1.77-003	1.93-003	2.27-003						
6	1.38-003	1.49-003	1.49-003	1.39-003	1.09-003	2.14-003	1.47-003	1.33-003	1.77-003	1.42-003	1.28-003
	1.71-003	1.37-003	1.50-003	1.84-003	2.11-003						
5	1.32-003	1.45-003	1.27-003	1.23-003	1.09-003	1.99-003	1.28-003	1.13-003	1.19-003	1.27-003	1.17-003
	1.71-003	1.38-003	1.42-003	1.51-003	1.61-003						
4	1.21-003	1.27-003	1.27-003	1.21-003	1.09-003	2.08-003	1.28-003	1.11-003	1.15-003	1.29-003	1.13-003
	1.71-003	1.28-003	1.38-003	1.45-003	1.66-003						
3	1.16-003	1.21-003	1.21-003	1.16-003	1.09-003	2.17-003	1.07-003	1.13-003	1.16-003	1.33-003	1.14-003
	1.71-003	1.14-003	1.22-003	1.32-003	1.63-003						
2	1.14-003	1.16-003	1.16-003	1.11-003	1.09-003	1.40-003	1.09-003	1.13-003	1.13-003	1.14-003	1.13-003
	1.09-003	1.12-003	1.18-003	1.20-003	1.31-003						
1	1.11-003	1.12-003	1.13-003	1.11-003	1.09-003	1.09-003	1.09-003	1.09-003	1.09-003	1.09-003	1.09-003
	1.09-003	1.09-003	1.09-003	1.09-003	1.09-003						
	1.09-003	1.09-003	1.09-003	1.09-003	1.09-003						

AVG CONCENTRATIONS AT 76195 6.00 FOR SPECIES 5 OLE												
SEGMENT= 1 LEVEL=1												
	1	2	3	4	5	6	7	8	9	10	11	12
13	13	14	15	16	17							
	3.48-003	9.23-003	1.24-002	1.51-002	1.48-002	9.94-003	8.48-003	8.05-003	7.35-003	5.12-003	4.05-003	3.41-003
12	3.25-003	3.15-003	2.75-003	2.16-003	2.20-003							
	3.48-003	8.01-003	9.45-003	1.07-002	1.07-002	9.33-003	9.42-003	9.57-003	8.37-003	6.39-003	4.23-003	3.98-003
11	3.51-003	3.16-003	2.53-003	2.12-003	2.20-003							
	3.48-003	6.37-003	7.91-003	8.14-003	9.27-003	8.32-003	9.63-003	1.01-002	9.83-003	8.28-003	6.21-003	4.43-003
10	3.63-003	2.96-003	2.66-003	2.27-003	2.20-003							
	3.48-003	5.36-003	6.58-003	6.96-003	6.57-003	6.64-003	6.80-003	6.46-003	6.12-003	6.64-003	4.76-003	4.27-003
9	4.05-003	3.42-003	3.20-003	2.65-003	2.20-003							
	3.48-003	3.80-003	4.49-003	5.43-003	5.72-003	5.45-003	5.48-003	5.11-003	4.33-003	3.81-003	3.73-003	3.78-003
8	3.84-003	3.80-003	3.21-003	2.42-003	2.20-003							
	3.48-003	2.78-003	3.36-003	3.78-003	4.61-003	5.06-003	5.04-003	3.83-003	3.04-003	3.07-003	2.82-003	2.84-003
7	3.06-003	3.55-003	3.41-003	2.48-003	2.20-003							
	3.48-003	2.55-003	2.85-003	3.04-003	3.42-003	3.72-003	3.44-003	3.17-003	2.84-003	2.84-003	2.53-003	2.53-003
6	2.53-003	2.62-003	2.58-003	2.48-003	2.20-003							
	3.48-003	2.43-003	2.56-003	2.90-003	3.19-003	3.24-003	2.58-003	2.46-003	2.60-003	2.90-003	2.54-003	2.40-003
5	2.43-003	2.66-003	2.33-003	2.31-003	2.20-003							
	3.48-003	2.44-003	2.48-003	2.56-003	2.67-003	3.05-003	2.34-003	2.20-003	2.26-003	2.34-003	2.34-003	2.24-003
4	2.27-003	2.34-003	2.34-003	2.30-003	2.20-003							
	3.48-003	2.34-003	2.43-003	2.50-003	2.72-003	3.13-003	2.33-003	2.16-003	2.20-003	2.26-003	2.34-003	2.19-003
3	2.21-003	2.27-003	2.28-003	2.24-003	2.20-003							
	3.48-003	2.20-003	2.28-003	2.38-003	2.69-003	3.23-003	2.12-003	2.18-003	2.21-003	2.27-003	2.38-003	2.19-003
2	2.19-003	2.22-003	2.22-003	2.20-003	2.20-003							
	2.20-003	2.19-003	2.24-003	2.26-003	2.37-003	2.47-003	2.16-003	2.19-003	2.20-003	2.20-003	2.20-003	2.19-003
1	2.18-003	2.19-003	2.20-003	2.20-003	2.20-003							
	2.20-003	2.20-003	2.20-003	2.20-003	2.20-003	2.20-003	2.20-003	2.20-003	2.20-003	2.20-003	2.20-003	2.20-003
	2.20-003	2.20-003	2.20-003	2.20-003	2.20-003							

+ 5.2
 PL = -1

LOCAL VARIABLES

K	THOLD	THNEW	THAVG	HTOLD	HTNEW	HTAVG	AER	FACT	WZOLD	WZNEW	XKZ
1	20.	20.	20.	10.	10.	10.	0.	0.0000	0.	0.	0.
2	20.	20.	20.	30.	30.	30.	0.	0.0000	0.	0.	2.319E+03
3	20.	20.	20.	50.	50.	50.	0.	0.0000	0.	0.	2.432E+03
4	20.	20.	20.	70.	70.	70.	0.	0.0000	0.	0.	2.224E+03
5	109.	118.	114.	134.	139.	137.	0.	0.0000	0.	0.	1.954E+03
6							0.	0.0000	-2.491E+02	-2.700E+02	7.635E+02

CONTEM ARRAY (STEPS 3 AND 4)

SPEC	1	2	3	4	5
1	1.216E+00	1.217E+00	1.198E+00	1.169E+00	9.529E-01

SPEC	VD	SRC	FLUX
1	1.000E-10	0.	2.197E+00

STEP 3 VECTORS

K	Y1-1	Y1-2	Y1-3	A	B	C	Y	X	CTEST	Z	AOMEGA
1	0.	0.	0.	0.	0.	0.	0.	0.	1.22E+00	9.38E-01	1.30E+00
2	0.	6.96E-01	3.04E-01	0.	1.30E+00	-3.04E-01	1.22E+00	1.22E+00	1.23E+00	9.83E-01	1.51E+00
3	3.04E-01	4.18E-01	2.78E-01	-3.04E-01	1.58E+00	-2.78E-01	1.20E+00	1.20E+00	1.20E+00	1.12E+00	1.30E+00
4	2.78E-01	6.46E-01	7.57E-02	-2.78E-01	1.35E+00	-7.07E-02	1.18E+00	1.17E+00	1.18E+00	9.53E-01	1.01E+00
5	1.28E-02	9.10E-01	0.	-1.20E-02	1.01E+00	0.	9.50E-01	9.53E-01	1.02E+00	0.	0.

MET SCALARS

TGRADBELOW	TGRADABOVE	EXTCLASS	RADFACTOR	CONCWATER	ATMOSPRESS
-.009	.029	-1.000	.220	13000.000	.840
ATTACT	TTMBEG	TTMEND	FRKBEG	FRKDEL	FACTRK
.001	5.000	6.000	0.000	.220	.055

MISC SCALARS									
ZREF	10.000	WYMAX	10000.000	WAVW	10440.307	WAVE	10440.307	WAVS	10440.307
DTMAX	.322	DT	.100	NDT	1	ISEQ	2		
EL	62.889	USTAR	986.072	DIFRES					
TIME =	76210	SLICE =	.1000	ELAPSED CPU TIME =	.096 SECS	TOTAL ELAPSED CPU TIME =	3.736 SECS		

Exhibit X-2 (Concluded)

any data. Check that printed values correspond to the data expected from the input files.

If no readily apparent errors can be found in the model inputs, then the available input and output should be examined by someone familiar with the technical components of the model. In undertaking the diagnosis, one should note the cause of the failure (iteration limit exceeded or negative concentration predicted). First, attention should be given to reaction rate constants and stoichiometric coefficients. Next, the predicted concentrations should be examined. Usually, one will note predictions for one or more pollutants that fall outside the expected nominal range of values for the particular contaminants in question. The development of an understanding of how these concentration values occurred will often suggest means for resolving the problem. For example, a very high NO concentration prediction may be causing the model to predict negative O₃ concentrations. The user might subsequently find that the NO emissions rate from a point source was in error by a factor of 100. Skill in diagnosing such problems requires some familiarity with the physical and chemical processes that take place in the atmosphere as well as an understanding of how these processes are treated in the model.

C. ERROR CONDITIONS

Table X-4 lists error conditions that could cause the Airshed Simulation Program to terminate before the simulation is completed. These are situations detected by the program itself rather than by the operating system, and the program will exit normally. Included in the table are the names of the subroutines in which the error messages are printed.

Table X-4. Airshed Simulation Program Error Conditions

<u>Error Condition</u>	<u>Subroutine(s) That Print Errors</u>
Control file errors	
File improperly named	SCREAD, CHREAD
Species or coefficient required by built-in chemical mechanism is missing	SPECID
Reactive species not listed in built-in mechanism	SPECID
Allocation errors	
Space allocation exceeded--region dimensions too large	ALLOC
M.E.B. file errors	
File missing or improperly named	HDRCK
Time span on file does not encompass time span of run	HDRCK
Region or segment definition does not match that on BOUNDARY file	HDRCK
Time intervals on file are not contiguous	FILSKP, FILCK
Unexpected end-of-file	Any file-read routine
Chemistry errors	
Negative concentrations at minimum step size	STEP4
Nonconvergence of concentration values at minimum step size	STEP4
Nonconvergence of [HO ₂] iteration	CHEM
Other errors	
Program about to run out of time	FINISH

XI DISPLAY AND ANALYSIS

Concentration values predicted by the Airshed Simulation Program are saved on binary files and are thus available for any display and analysis techniques that might be developed. At present, there is one program available to handle the airshed simulation output files. Currently, it can be used only for the display of the concentration data, but analysis capabilities can be easily added. In this chapter, the general capabilities of the display program are discussed, followed by descriptions and examples of its input and output. A detailed description of the program is given in the Systems Manual.

A. CAPABILITIES OF THE DISPLAY PROGRAM

The display program provides for two distinct operating modes: prediction and comparison. In the "prediction" mode, concentration predictions are read from one airshed simulation run, and concentration maps and vertical concentration profiles are printed. Capabilities that could be added to the program in this mode include contour mapping of concentration isopleths and calculation of some simple statistics, such as hourly maximum concentrations for each species, frequency of exceeding certain specified levels, and concentrations averaged over time periods longer than that used by the simulation.

In the "comparison" mode, which has been provided for but not yet implemented, one set of concentrations would be subtracted from another, and all further display and analysis would be performed on the resulting array of differences. The comparison mode could be used for validating model predictions against observed data as well as assessing the impact of different model scenarios.

The display program is currently capable of processing a region of up to 30 x 30 grid cells in the horizontal plane, with a maximum of 13 chemical species. These maximum dimensions can be changed by recompiling the program.

B. INPUT REQUIRED BY THE DISPLAY PROGRAM

As illustrated in Figure XI-1, the input to the display program consists of the following:

- > Card-supplied display options and print controls.
- > Three data files used by the simulation program.
- > One output concentration file from the simulation program.
- > Optionally, a second concentration data file.


This section discusses first the data files that are to be input, and then details the contents and format of the input cards.

1. Data File Input

If concentration maps and vertical profiles are requested (currently the only features available), the BOUNDARY, DIFFBREAK, and REGIONTOP files used for the simulation run must be input. The BOUNDARY file describes the segmentation layout and defines the boundary of the simulated area in the horizontal plane. The DIFFBREAK and REGIONTOP files are used to calculate vertical heights at selected stations. If the simulation has been performed with more than 1 segment, it is the segmented versions of the BOUNDARY, DIFFBREAK, and REGIONTOP files that must be provided to the display program.

One of the Airshed Simulation Program output files containing predicted concentration values must also be input. The concentration values can be instantaneous (INSTANT) or averaged over a time interval (AVERAGE); the output intervals for both files are specified in the SIMCONTROL file. The display program recognizes the file type from the header record, and formats the output accordingly.

If a comparison run is to be made (an option not yet fully implemented), a second concentration file must also be input. This file could contain concentration fields gridded from observed data using the AIRQUALITY data preparation program, or it could contain the results from another airshed simulation run.



* This option is not yet available.

Figure XI-1. Information Flow Diagram for the Display Program

All input files must contain the same segment structure; that is, all must be either unsegmented or segmented according to the same segment layout.

2. Card Input

The display program requires the following data to be input on cards:

- > Output display options
- > Names of species to be examined
- > Vertical level to be considered
- > Print controls
- > Measurement station and landmark names and locations
- > Display units conversion factors
- > User comments to appear on output.

The exact structure of each data card is shown in Table XI-1; Exhibit XI-1 is a sample input deck. Consistent with assumptions used in both the data preparation and simulation programs, the following conventions are generally followed in specifying data fields on each card:

- > Integer input is in 10-character fields, up to six per card.
- > Real number input is floating point in 10-character fields, up to six per card.
- > Alphanumeric input is read and stored as one character per machine word.

Table XI-1. Display Program Control Input Definition

Card Number and Name	Item and Columns	Format	Comments
1			
Output Options	KMAP 1-10	I10	Map selection flag: 1, if concentration maps are desired; 0, if no maps are desired
	KCOMP 11-20	I10	Comparison option selection flag: 1, if comparison of two concentration files is required; 0, if no comparison is required
	KSTNFL 21-30	I10	If greater than 0, writes station predictions to unit 12.
	KALLFL 31-40	I10	If greater than 0, writes concentration field predictions to unit 16.
2			
Species Count	NSPECP 1-10	I10	Number of species to be examined: must be ≤ 13
3+			
Species Names	((SPNAME(I,J), J = 1, 10), I = 1, NSPECP) 1-60	6(10A1)	Alphanumeric names of species to be examined--10 characters per name, left adjusted, six names per card; each name must correspond to a name used in the Airshed Simulation Program run; the species can be named in any order
4			
Vertical Level	NLEVEL 1-10	I10	Vertical level to be examined and mapped
5			
Map Print Times (only if KMAP = 1)			Print types must correspond to times for which data on the concentration data files are available
	DATPRS 1-10	I10	Print start date (Julian date)
	TPRS 11-20	F10.2	Print start time (hours past midnight)

Table XI-1 (Continued)

Card Number and Name	Item and Columns	Format	Comments
5			
Map Print Times (con't)			
	DTPR 21-30	F10.2	Print interval (hours)
	DATPRF 31-40	I10	Print finish date (Julian date)
	TPRF 41-50	F10.2	Print finish time (hours past midnight)
The next four cards (Nos. 6 through 9) are to be input only for the comparison mode (not yet implemented)			
6			
Comparison Times (only if KCOMP = 1)			Comparison times must correspond to times for which data on the data files are available
	DATSCS 1-10	I10	Comparison start date (Julian date)
	TSCS 11-20	F10.2	Comparison start time (hours past midnight)
	DTSC 21-30	F10.2	Comparison interval (hours)
	DATSCF 31-40	I10	Comparison finish date (Julian date)
	TSCF 41-50	F10.2	Comparison finish time (hours)
7			
Comparison Station Count (only if KCOMP = 1)	NSTATC 1-10	I10	Number of stations at which concentrations are to be com- pared; must be ≤ 16 ; this number is used to determine how many Card 8's are to be read

Table XI-1 (Continued)

Card Number and Name	Item and Columns	Format	Comments
8+ Comparison Stations (only if KCOMP = 1)	((STATNA(I,J), J = 1, 20), I = 1, NSTATC) 1-60	3(20A1)	Alphanumeric names of stations at which concentrations are to be compared--20 characters per name, left adjusted, three names per card; each name must match a station name listed on Card 11.
9 Comparison Options (only if KCOMP = 1)	KPLOT 1-10	I10	Comparison plot flag: 1, if plots are desired; 0, if no plots are needed
	KSTAT 11-20	I10	Statistics option flag: 1, if comparative statistics are to be calculated; 0, if no statistics are to be calculated
10 Point Counts	NOSTN 1-10	I10	Number of stations at which concentrations are to be calculated--must be ≤ 16 ; stations are also included on concentration maps
	NOLAND 11-20	I10	Number of landmarks to be included on concentration maps--must be ≤ 8

Table XI-1 (Continued)

Card Number and Name	Item and Columns	Format	Comments
11+ Station	Station Name 1-20	20A1	There must be NOSTN of these cards Alphanumeric station name, left adjusted
	x-location 21-30	F10.0	x-coordinate of the station, measured in meters from the reference origin
	y-location 31-40	F10.0	y-coordinate of the station, measured in meters from the reference origin
12+ Landmark	Landmark name 1-20	20A1	There must be NOLAND of these cards Alphanumeric landmark name, left adjusted
	x-location 21-30	F10.0	x-coordinate of the landmark, measured in meters from the reference origin
	y-location 31-40	F10.0	y-coordinate of the landmark, measured in meters from the reference origin
13+ Output Units	(IOUNTS(I), I = 1, NSPECP) 1-60	6I10	Output conversion flags, six per card; the number and order must correspond to the species named on Cards 3+; internal units are in $\mu\text{g}/\text{m}^3$ for AEROSOLS and ppm for all other species; different units, however, can be selected for dis- play output using IOUNTS as follows: 1 = ppm; 2 = pptm; 3 = pphm; 4 = ppb; 5 = $\mu\text{g}/\text{m}^3$

Table XI-1 (Concluded)

Card Number and Name	Item and Columns	Format	Comments
14 User Comment	NOTE 1-80	20A4	Note--up to 80 characters--written on header page of display output; it is referred to on that page as "*COMMENTS*"
15 Region Name	REGION 1-80	20A4	Region description note--up to 80 characters--to be used in entitling display output header page

NO CARB	1 9 NO2 ARO	0 03 CO	ETH	OLE	PAR
	1 76195 21	05.00 0	1.00	76195	09.01
101		19183.0	27862.0		
102		17518.0	34045.0		
103		22588.0	30467.0		
104		22312.0	25304.0		
105		18706.0	24453.0		
106		13660.0	25566.0		
107		15179.0	30610.0		
108		23407.0	39102.0		
109		30802.0	27886.0		
110		22209.0	20826.0		
111		13812.0	20479.0		
112		8938.0	28913.0		
113		12738.0	37820.0		
114		19320.0	45456.0		
115		32111.0	45799.0		
116		37777.0	38083.0		
117		35560.0	20818.0		
118		18065.0	11256.0		
119		4759.0	18547.0		
120		-1921.0	33909.0		
121		7414.0	50376.0		
	4	4	4	4	3
	4	4	2		

USER COMMENT
ST. LOUIS REGION

Exhibit XI-1. Sample Input for the Display Program

C. OUTPUT PRODUCED BY THE DISPLAY PROGRAM

The display program first prints a header page, including the alphanumeric region description supplied in the input deck, the dimensions of the simulated area of the grid, the input user comment, and the run identifier from the simulation run that produced the concentration predictions. A sample of the display program header page is shown in Exhibit XI-2.

The display program, operating in prediction mode, currently produces two types of output for each time interval on the input concentration file.

- > Vertical concentration profiles. At each station location input, the concentrations at each vertical level are printed for each designated species. The heights of the diffusion break (mixing depth) and top of the region are also printed at each station. An example of vertical profile output is shown in Exhibit XI-3.
- > Ambient concentration maps. Maps are printed of concentrations in all horizontal grid cells (excluding boundary cells) at the vertical level designated by the user. Printout is confined to those hours and species designated by the user. A separate map is produced for each species at each print time. Station sites and landmarks are also printed on each concentration map. An example of the concentration maps is shown in Exhibit XI-4.

Operating in comparison mode, the display program would calculate residuals for a designated vertical level by subtracting the concentration field on the "comparison" file from the corresponding field on the primary concentration file. Among the statistics calculated for these residuals would be the average value, standard deviation, and correlation coefficient. Calculation of other statistics could be readily incorporated into the program. These statistics would be calculated for each designated species at each print time. Maps of residuals could also be generated for each desired species at each specified print time.

```

URBAN SCALE AIR POLLUTION SIMULATION MODEL OF
ST. LOUIS REGION

'INPUT PARAMETERS'

MESH SPACING IN X-DIRECTION  4.0000000+003      MESH SPACING IN Y-DIRECTION  4.0000000+003
NUMBER OF MESH POINTS IN X-DIRECTION , 15      NUMBER OF MESH POINTS IN Y-DIRECTION , 20
NUMBER OF VERTICAL MESH POINTS  4

'COMMENTS'
USER COMMENT
'RUN ID'

RAPS 4-KM DAY 195 -- 4-HR RUN 07/13/76  C-BOND II 8-79

```

Exhibit XI-2. Standard Display Program Header Page

VERTICAL AVERAGE CONCENTRATION PROFILES ABOVE SELECTED SITES ON 76195 BETWEEN THE HOURS OF 5. AND 6. LST

	116	MIXING DEPTH=	194.6 METERS,	TOP OF REGION=	594.6 METERS
NO	(PPB)	.54	.06		
HO2	(PPB)	5.89	2.89	2.88	
O3	(PPB)	30.56	77.00	76.98	

RUN ID =RAPS 4-KM DAY 195 -- 4-HR RUN 07/13/76 C-BOND II 8-79

PANEL 1	AVERAGE AMBIENT CONCENTRATIONS(PPB) OF O3																ON 76195 BETWEEN THE HOURS OF		5. AND	6. LST
	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16					
21 *	22	21	21	21	21	21	22	22	23	24	24	24	23	23	21	*				
20 *	20	19	18	18	18	19	20	21	23	24	24	24	23	24	23	*				
19 *	18	17	16	15	16	18	20	20	20	22	24	24	23	24	23	*				
18 *	17	15	13	13	14	16	20	21	20	19	20	24	25	25	24	*				
17 *	15	13	11	11	12	14	21	25	26	24	22	23	27	25	24	*				
16 *	13	10	7	8	13	14	19	25	28	27	27	29	29	27	24	*				
15 *	13	10	9	10	12	14	17	20	24	26	28	30	31	28	24	*				
14 *	15	14	12	12	15	18	19	20	24	26	30	32	32	30	25	*				
13 *	10	13	12	13	17	18	17	16	21	26	33	33	32	30	26	*				
12 *	6	11	12	12	16	14	14	14	18	29	34	34	32	30	26	*				
11 *	11	9	10	13	14	12	9	9	21	30	37	36	34	30	26	*				
10 *	15	12	13	15	17	16	18	21	25	29	37	35	34	29	25	*				
9 *	17	15	13	14	17	18	19	22	31	33	33	32	31	28	25	*				
8 *	18	17	15	15	14	16	22	26	29	31	32	31	29	27	25	*				
7 *	18	17	17	17	17	19	21	26	28	30	31	31	29	26	24	*				
6 *	19	18	18	18	18	22	24	25	27	29	31	31	29	23	23	*				
5 *	20	20	19	19	18	22	24	25	27	28	28	27	26	24	23	*				
4 *	22	21	20	19	18	23	24	25	26	26	27	27	27	24	23	*				
3 *	23	22	21	19	15	25	25	25	26	26	26	26	25	24	23	*				
2 *	23	23	23	22	22	24	24	24	25	25	25	25	25	24	23	*				

REFERENCES

- Anderson, G. E., S. R. Hayes, M. J. Hillyer, J. P. Killus, and P. V. Mundkur. 1977. "Air Quality in the Denver Metropolitan Region: 1974-2000." Systems Applications, Inc., San Rafael, CA (EPA-908/1-77-002).
- Briggs, G. A. 1975. Plume rise predictions. In Lectures on Air Pollution and Environmental Impact Analyses. D. A. Haugen, ed., American Meteorological Society, Boston, Massachusetts.
- Builtjes, P.J.H., K. D. van den Hout, and S. D. Reynolds. 1982. "Evaluation of the Performance of a Photochemical Dispersion Model in Practical Applications." Presented at the 13th International Technical Meeting on Air Pollution Modeling and Its Applications, 14-17 September 1982, Ile des Embiez, France.
- Deardorff, J. W. 1972. Numerical investigation of neutral and unstable planetary boundary layers. J. Atmos. Sci., 32:1794-1807.
- Haney, J. L, T. W. Tesche, and J. P. Killus. 1983. "Application of the Systems Applications Airshed Model to the Philadelphia Metropolitan Area: 19 July 1979 Ozone Episode." Systems Applications, Inc., San Rafael, CA (SYSAPP-83/057).
- Hayes, S. R. 1978. "Performance Measures and Standards for Air Quality Dispersion Models." Systems Applications, Inc., San Rafael, CA (Publication 78-93).

- Hillyer, M. J., S. D. Reynolds, and P. M. Roth. 1979. "Procedures for Evaluating the Performance of Air Quality Simulation Models." Systems Applications, Inc., CA (Publication 79-25R).
- Jerskey, T. N., and J. H. Seinfeld. 1976. "Continued Research in Mesoscale Air Pollution Simulation Modeling--Volume IV: Examination of the Feasibility of Modeling Photochemical Aerosol Dynamics." Systems Applications, Inc., San Rafael, CA (EPA-600/4-76-016d).
- Jerskey, T. N., J. H. Seinfeld, F. Gelbard, and L. E. Reid. 1976. "Continued Research in Mesoscale Air Pollution Simulation Modeling--Volume VII: Mathematical Modeling of Urban Aerosol Dynamics." Systems Applications, Inc., San Rafael, CA (Publication 76-144).
- Killus, J. P., J. P. Meyer, D. R. Durran, G. E. Anderson, T. N. Jerskey, G. Z. Whitten, and S. D. Reynolds. 1977. "Continued Research in Mesoscale Air Pollution Simulation Modeling--Volume V: Refinements in Numerical Analysis, Transport, Chemistry, and Pollutant Removal." Systems Applications, Inc., San Rafael, CA (Publication 77-142).
- Lamb, R. G. 1976. "Continued Research In Mesoscale Air Pollution Simulation Modeling--Volume II: Modeling of Microscale Phenomena." Systems Applications, Inc., San Rafael, CA (EPA-600/4-76-061c).
- Lamb, R. G., W. H. Chen, and J. H. Seinfeld. 1975. Numerico-empirical analyses of atmospheric diffusion theories. J. Atmos. Sci., 32:1794-1807.
- Lamb, R. G., W. R. Shu, D. R. Durran, J. H. Seinfeld, and L. E. Reid. 1977. "Continued Research In Mesoscale Air Pollution Simulation Modeling--Volume VI: Further Studies in the Modeling of Microscale Phenomena." Systems Applications, Inc., San Rafael, CA (Publication 77-143).

Liu, M. K., T. N. Jerskey, J. P. Meyer, J. Ames, and G. W. Lundberg. 1977. "Application of a Methodology for the Design of a Carbon Monoxide Monitoring Network at Las Vegas." Systems Applications, Inc., San Rafael, CA (SAI 77-16; EPA-600/4-78-053).

Liu, M. K., and J. H. Seinfeld. 1975. On the validity of grid and trajectory models of urban air pollution. Atmos. Environ., 9:555-574.

Liu, M. K., D. C. Whitney, S.D. Reynolds, and P. M. Roth. 1973. "Further Development and Evaluation of a Simulation Model for Estimating Ground Level Concentrations of Photochemical Pollutants--Volume III: Automation of Meteorological and Air Quality Data for the SAI Urban Airshed Model." Systems Applications, Inc., San Rafael, CA (SAI 73-32).

Liu, M. K., D. C. Whitney, and P. M. Roth. 1976b. Effects of atmospheric parameters on the concentration of photochemical pollutants. J. Appl. Meteorol., 15:829-835.

Liu, M. K., D. C. Whitney, J. H. Seinfeld, and P. M. Roth. 1976a. "Continued Research in Mesoscale Air Pollution Simulation Modeling--Volume I: Assessment of Prior Model Evaluation Studies and Analysis of Model Validity and Sensitivity." Systems Applications, Inc., San Rafael, CA. (SAI 75-23; EPA-600/4-76-016a).

Reynolds, S. D. 1977. "The Systems Applications, Incorporated Urban Airshed Model: An Overview of Recent Developmental Work." International Conference on Photochemical Oxidant Pollution and Its Control, Systems Applications, Inc., San Rafael, CA (EPA-600/3-77-001b).

- Reynolds, S. D., J. Ames, T. A. Hecht, J. P. Meyer, D. C. Whitney, and M. A. Yocke. 1976. "Continued Research in Mesoscale Air Pollution Simulation Modeling--Volume II: Refinements in the Treatments of Chemistry, Meteorology, and Numerical Integration Procedures." Systems Applications, Inc., San Rafael, CA (SAI 75-24R; EPA-600/4-76-016b).
- Reynolds, S. D., J. Ames, G. W. Lundberg, and P. V. Munkur. 1978. "Application of the SAI Airshed Model to the Evaluation of Alternative Population Growth Forecasts for the South Coast Air Basin." Systems Applications, Inc., San Rafael, CA (Publication 78-124).
- Reynolds, S. D., H. Hogo, W. R. Oliver, and L. E. Reid. 1982. "Application of the SAI Airshed Model to the Tulsa Metropolitan Area. Systems Applications, Inc., San Rafael, CA (SYSAPP-82/004).
- Reynolds, S. D., M. K. Liu, T. A. Hecht, P. M. Roth, and J. H. Seinfeld. 1973a. "Further Development and Validation of a Simulation Model for Estimating Ground Level Concentrations of Photochemical Pollutants." Systems Applications, Inc., San Rafael, CA (Publication 73-19).
- Reynolds, S. D., M. K. Liu, T. A. Hecht, P. M. Roth, and J. H. Seinfeld. 1974. Mathematical modeling of photochemical air pollution--III. Evaluation of the model. Atmos. Environ., 8:563-596.
- Reynolds, S. D., L. Reid, M. Hillyer, J. P. Killus, T. W. Tesche, R. I. Pollack, G. E. Anderson, and J. Ames. 1979. "Photochemical Modeling of Transportation Control Strategies--Volume I. Model Development, Performance Evaluation, and Strategy Assessment." Systems Applications, Inc., San Rafael, CA (Publication 79-37R).

Reynolds, S. D., P. M. Roth, and J. H. Seinfeld. 1973b. Mathematical modeling of photochemical air pollution--I. Formulation of the model. Atmos. Environ., 7:1033-1061.

Reynolds, S. D., and J. H. Seinfeld. 1975. Interim evaluation of strategies for meeting ambient air quality standards for photochemical oxidant. Environ. Sci. Technol., 9:433-447.

Roth, P. M., S. D. Reynolds, P.J.W. Roberts, J. H. Seinfeld, T. A. Hecht, and C. L. Nelson. 1971. "Development of A Simulation Model for Estimating Ground Level Concentrations of Photochemical Pollutants." Systems Applications, Inc., San Rafael, CA.

Roth, P. M., S. D. Reynolds, T.W. Tesche, P. D. Gutfreund, and C. Seigneur. 1984. An appraisal of emissions control requirements in the California South Coast Air Basin. Environ. Int., 9:549-571.

Roth, P. M., P.J.W. Roberts, M. K. Liu, S. D. Reynolds, and J. H. Seinfeld. 1974. Mathematical modeling of photochemical air pollution--II. A model and inventory of pollutant emissions. Atmos. Environ., 8:97-130.

Seigneur, C. S., T. W. Tesche, D. A. Stewart, M. K. Liu, P. M. Roth, and W. R. Oliver. 1983. Effect of Power Plant Emissions of NO_x on Ozone Levels in Three Different Environments." Systems Applications, Inc., San Rafael, CA (SYSAPP-83/023).

Souten, D. R., T. W. Tesche, and W. R. Oliver. 1981. "Use of the Airshed Grid Model to Evaluate the Air Quality Impacts of Alternative Air Pollution Control Policies on the South Coast Air Basin." Systems Applications, Inc., San Rafael, CA (SYSAPP-80/220).

- Stern, R., and B. Schere. 1982. "Simulation of a Photochemical Smog Episode in the Rhine-Ruhr Area with a Three-Dimensional Grid Model." Presented at the 13th International Technical Meeting on Air Pollution and Its Application, 14-17 September 1982, Ile des Embiez, France.
- Tesche, T. W., and C. S. Burton. 1978. "Simulated Impact of Alternative Emissions Controls Strategies on Photochemical Oxidants in Los Angeles." Systems Applications, Inc., San Rafael, CA (Publication 78-22R).
- Tesche, T. W., W. R. Oliver, and J. L. Haney. 1982. "Photochemical Modeling of the SCE Ivanpah Generating Station." Systems Applications, Inc., San Rafael, CA (SYSAPP-82/212).
- Tesche, T. W., W. R. Oliver, H. Hogo, P. Saxena, and J. L. Haney. 1983a. "Assessment of NO_x Emission Control Requirements in the California South Coast Air Basin, Volume IV, Appendix A: Performance Evaluation of the Systems Applications Airshed Model for the 26-27 June 1974 O_3 Episode in the South Coast Air Basin." Systems Applications, Inc., San Rafael, CA (SYSAPP-83/037).
- Tesche T. W., W. R. Oliver, H. Hogo, P. Saxena, and J. L. Haney. 1983b. "Assessment of NO_x Emission Control Requirements in the California South Coast Air Basin, Volume IV, Appendix B: Performance Evaluation of the Systems Applications Airshed Model for the 7-8 November 1978 NO_2 Episode in the South Coast Air Basin." San Rafael, CA (SYSAPP-83/038).
- Tesche, T. W., C. Seigneur, L. E. Reid, P. M. Roth, W. R. Oliver, and J. C. Cassmassi. 1981. "Sensitivity of Complex Photochemical Model Estimates to Detail in Input Information." System Applications, Inc. San Rafael, CA (SAI 81-5).

Whitten, G. Z., and H. Hogo, 1977. "Mathematical Modeling of Simulated Photochemical Smog." Systems Applications, Inc., San Rafael, CA (EPA-600/3-77-001).

Whitten, G. Z., H. Hogo, and J. P. Killus. 1980. The Carbon-Bond Mechanism: A condensed kinetic mechanism for photochemical smog. Environ. Sci. Technol., 14:690-700.

TECHNICAL REPORT DATA <i>(Please read Instructions on the reverse before completing)</i>		
1. REPORT NO.	2.	3. RECIPIENT'S ACCESSION NO.
4. TITLE AND SUBTITLE		5. REPORT DATE
SAI AIRSHED MODEL OPERATIONS MANUALS Volume I -- User's Manual		6. PERFORMING ORGANIZATION CODE
7. AUTHOR(S) J. Ames, T.C. Myers, L.E. Reid, D.C. Whitney, S.H. Golding, S.R. Hayes, S.D. Reynolds		8. PERFORMING ORGANIZATION REPORT NO. EM78-89R2
9. PERFORMING ORGANIZATION NAME AND ADDRESS Systems Applications, Inc. 101 Lucas Valley Road San Rafael, CA 94903		10. PROGRAM ELEMENT NO. CDWA1A/01-5006 (FY-85)
		11. CONTRACT/GRANT NO. Contract No. 68-02-2429
12. SPONSORING AGENCY NAME AND ADDRESS Atmospheric Sciences Research Laboratory -- RTP, NC Office of Research and Development U.S. Environmental Protection Agency Research Triangle Park, North Carolina 27711		13. TYPE OF REPORT AND PERIOD COVERED (8/76 - 9/79)
		14. SPONSORING AGENCY CODE EPA/600/09
15. SUPPLEMENTARY NOTES		
16. ABSTRACT		
This report presents a general view of the Systems Applications, Inc. (SAI) Airshed Model as well as detailed operating instructions for the user. Included are discussions of all the files needed to run the model, the data preparation programs that produce each file, the input formats and data preparation methods, samples of input and output, and information flow diagrams that illustrate the job stream control on any computer. Chapter II presents a technical summary of the SAI Airshed Model; Chapter III contains an overview of the model as a system of computer programs, outlining the five main functions that must be performed by users and programs together. Chapter IV discusses some of the concepts and terms basic to an understanding of the system, followed in Chapter V by descriptions of the job control notations that will be used throughout this manual. Chapters VI through XI examine in detail the five main functions of the system, providing input and output definitions and examples, and job control diagrams for each program that must be exercised.		
17. KEY WORDS AND DOCUMENT ANALYSIS		
a. DESCRIPTORS	b. IDENTIFIERS/OPEN ENDED TERMS	c. COSATI Field/Group
18. DISTRIBUTION STATEMENT	19. SECURITY CLASS (This Report) UNCLASSIFIED	21. NO. OF PAGES
RELEASE TO PUBLIC	20. SECURITY CLASS (This page) UNCLASSIFIED	22. PRICE